



Natural Resources Conservation Service

United States  
Department of  
Agriculture

**Natural  
Resources  
Conservation  
Service**

# National Agronomy Manual

---



October 2002

The United States Department of Agriculture (USDA) prohibits discrimination in all its programs and activities on the basis of race, color, national origin, gender, religion, age, disability, political beliefs, sexual orientation, and marital or familial status. (Not all prohibited bases apply to all programs.) Persons with disabilities who require alternate means for communication of program information (Braille, large print, audiotape, etc.) should contact the USDA's TARGET Center at (202) 720-2600 (voice and TDD).

To file a complaint of discrimination, write USDA, Director, Office of Civil Rights, Room 326W, Whitten Building, 14th and Independence Avenue, SW, Washington, DC 20250-9410, or call (202) 720-5964 (voice or TDD). USDA is an equal opportunity employer.

---

<b>Contents:</b>	<b>Subpart 500A Authority</b>	500-1	
	500.00 Soil Conservation and Domestic Allotment Act of 1935 .....	500-1	
	500.01 Purpose of the Agronomy Manual .....	500-1	
	<hr/>		
	<b>Subpart 500B Agronomic policies</b>	500-2	
	500.10 Location of policy .....	500-2	
	500.11 Amendments to NAM .....	500-2	
	<hr/>		
	<b>Subpart 500C Responsibilities of agronomists</b>	500-2	
	500.20 Responsibilities of national, State, area, and field agronomists .....	500-2	
	500.30 Technical information—preparing, transferring, and training .....	500-3	
	500.40 Certification .....	500-3	
	500.50 Affiliation with professional organizations .....	500-3	



---

**Subpart 500A Authority****500.00 Soil Conservation and Domestic  
Allotment Act of 1935**

The basic legislation for soil and water conservation programs by the Natural Resources Conservation Service (NRCS) is the Soil Conservation and Domestic Allotment Act, Public Law 74-46 of 1935 (16 U.S.C. 590a-590f). This original act recognized that agronomy, the science of field crop production, is essential in fulfilling the agency's responsibilities. The Buchanan Amendment to the Agricultural Appropriations Bill for FY 1930 (Public Law 70-769) led to the enactment of Public Law 74-46. In 1933, the Soil Erosion Service was established as a temporary agency of the Department of the Interior. The agency was transferred to USDA in 1935 and named the Soil Conservation Service (SCS). In 1994, the Natural Resources Conservation Service was established by Public Law 103-354, the Department of Agriculture Reorganization Act (7 U.S.C. 6962).

The NRCS combines the authorities of the former Soil Conservation Service as well as five natural resource conservation cost-share programs previously administered by other USDA agencies. The mission of the NRCS is to provide leadership in a partnership effort to help people conserve, maintain and improve our natural resources and environment. NRCS provides technical assistance through local conservation districts on a voluntary basis to land users, communities, watershed groups, Federal and State agencies, and other cooperators. The agency's work focuses on erosion reduction, water quality improvement, wetland restoration and protection, fish and wildlife habitat improvement, range management, stream restoration, water management, and other natural resource problems.

**500.01 Purpose of the Agronomy Manual**

The National Agronomy Manual (NAM) contains policy for agronomy activities and provides technical procedures for uniform implementation of agronomy tools and applications.

## Subpart 500B Agronomic policies

### 500.10 Location of policy

Agronomic policies are contained in specific parts and subparts of this National Agronomy Manual as appropriate.

### 500.11 Amendments to NAM

The NAM will be amended as needed, as additional research is completed, existing methods or procedures are updated, or as new technology is developed and approved for use in the NRCS. The national agronomist is responsible for updating this manual.

## Subpart 500C Responsibilities of agronomists

### 500.20 Responsibilities of national, State, area, and field agronomists

The national agronomist, nutrient management, and pest management specialists at the national level, cooperating scientists for agronomy, and agronomists on the institutes and center staffs provide staff assistance in all NRCS programs and provide national leadership on NRCS agronomy related activities. They are responsible for:

- assisting upper management in formulating and recommending national policies, procedures, and standards;
- technical leadership and guidance; quality control;
- national coordination of agronomy with other NRCS technical fields; and
- promoting and maintaining relations with groups and agencies that have common interest in agronomy.

State agronomists provide staff assistance to the State Conservationist for all agronomy and related functions. They are responsible for:

- Assisting in developing State policies, procedures, and instructions, and coordinating them with other States within the region.
- Providing technical leadership and guidance to other agronomists and appropriate personnel within the State.
- Collaborating with other State staff members to ensure interdisciplinary action in all NRCS programs.
- Training field personnel.
- Participating in agronomy components of appraisals and reviews.
- Maintaining working relations with research centers and other cooperating agencies.
- Developing and revising of all aspects of Field Office Technical Guides related to agronomy.
- Providing assistance in interdisciplinary technical reviews of project plans, environmental impact statements, and other technical materials.
- Coordinating agronomy functions with other States in the region and across regional boundaries as appropriate.

Area or zone agronomists provide staff assistance in all NRCS programs. They are responsible for carrying out the requirements of conservation agronomy consistent with technical proficiency, training, interdisciplinary action, and quality control within their administrative area. In some cases, these agronomists may carry out some of the responsibilities of the state agronomists if so delegated.

Field office agronomists are usually in training positions. Training is provided by agronomists at the area or State level.

Agronomists in the above positions may provide specific functions through team or ad hoc assignments at a national, regional, or State level.

Each agronomist has the responsibility to develop their training needs inventory and to work with their supervisor to obtain technical training to improve their overall agronomic expertise.

Standards of performance for agronomists are contained in the NRCS Personnel Manual.

### **500.30 Technical information—preparing, transferring, and training**

Agronomists use technical information that has been developed at centers, institutes, national, or State level and maintain technical materials for the administrative area they serve. State staff agronomists develop and review field office technical guide materials and ensure materials are technically correct, comprehensive, and useful to the end user. NRCS policy on preparing and maintaining technical guides is in Title 450-GM, Part 401. In addition, state agronomists are responsible for technical notes and other agronomy technical materials that are applicable to the State.

Agronomists issue technical information at the area, state, or national level. This may include original information, research notes, papers, or excerpts of such material. Agronomists are encouraged to submit articles for publication or presentation at professional meetings. Technical information presented or prepared for publication shall have an appropriate technical and or administrative review and include crediting of appropriate references.

Agronomists receive and provide training necessary to maintain technical competency at all administrative levels. Training includes but is not limited to National Employee Development Courses, workshops, conferences, and university courses.

### **500.40 Certification**

Agronomists at all levels of the agency are encouraged to obtain professional certification(s). Examples of certification programs include the Certified Crop Adviser (CCA) and Certified Professional Agronomists (CPAg) under ARCPACS of the American Society of Agronomy, Certified Professional in Erosion and Sediment Control (CPESC) of the Soil and Water Conservation Society, and state pesticide applicator licenses. Continuing educational requirements of most certification programs provide excellent opportunities to stay abreast of advances in technology.

### **500.50 Affiliation with professional organizations**

Agronomists at all levels are encouraged to be active members of professional scientific societies, such as the American Society of Agronomy, Soil Science Society of America, Crop Science Society of America, the Soil and Water Conservation Society. These organizations provide opportunities to interact with researchers at the national and State level and to stay current on the latest technology.





---

<b>Contents:</b>	<b>Subpart 501A Introduction</b>	501-1
	501.00 Overview of Content in Part 501 Water Erosion .....	501-1
<hr/>		
	<b>Subpart 501B Water erosion</b>	501-1
	501.10 Forms of water erosion .....	501-1
	501.11 The water erosion process .....	501-1
<hr/>		
	<b>Subpart 501C Estimating sheet and rill erosion</b>	501-2
	501.20 How, why, and by whom water erosion is estimated .....	501-2
	501.21 Methods of estimating sheet and rill erosion .....	501-2
	501.22 The Revised Universal Soil Loss Equation .....	501-3
	501.23 Limitations of the equation .....	501-3
	501.24 Alternative methods of applying RUSLE .....	501-3
	501.25 Data needed to support RUSLE .....	501-3
	501.26 Tools for using RUSLE .....	501-4
<hr/>		
	<b>Subpart 501D RUSLE factors</b>	501-4
	501.30 The average annual soil loss estimate, A .....	501-4
	501.31 The rainfall and runoff erosivity factor, R .....	501-4
	501.32 The soil erodibility factor, K .....	501-4
	501.33 The slope length and steepness factors, L and S .....	501-5
	501.34 The cover-management factor, C .....	501-5
	501.35 The support practice factor, P .....	501-5
<hr/>		
	<b>Subpart 501E Principles of water erosion control</b>	<b>501-6</b>
	501.40 Overview of principles .....	501-6
	501.41 Relation of control to RUSLE factors .....	501-6
<hr/>		
	<b>Subpart 501F References</b>	501-7
<hr/>		
<b>Exhibits</b>	<b>Exhibit 501-1</b> Acceptable class and half-class factor K values for use in RUSLE where K values are adjusted for seasonal variability	501-8



---

**Subpart 501A Introduction****501.00 Overview of Content in Part 501 Water Erosion**

Part 501 presents Natural Resources Conservation Service (NRCS) policy and procedures for estimating soil erosion by water. It explains the types, the method used to estimate, and the control of soil erosion by water. NRCS technical guidance related to water erosion shall conform to policy and procedures set forth in this part.

The Agricultural Research Service (ARS) has primary responsibility for erosion prediction research within the U.S. Department of Agriculture (USDA). ARS is the lead agency for developing erosion prediction technology, including the Revised Universal Soil Loss Equation (RUSLE). The technology in RUSLE is documented to the publication *Predicting Soil Erosion by Water: A Guide to Conservation Planning With Revised Universal Soil Loss Equation*, U.S. Department of Agriculture Handbook 703, hereafter referred to as *Agriculture Handbook 703*.

---

**Subpart 501B Water erosion****501.10 Forms of water erosion**

Forms of soil erosion by water include sheet and rill, ephemeral gully, classical gully, and streambank. Each succeeding type is associated with the progressive concentration of runoff water into channels as it moves downslope. Sheet erosion, sometimes referred to as interrill erosion, is the detachment of soil particles by raindrop impact and the removal of thin layers of soil from the land surface by the action of rainfall and runoff. Rill erosion is the formation of small, generally parallel channels formed by runoff water. Rills usually do not re-occur in the same place. Ephemeral gullies are concentrated flow channels formed when rills converge to form shallow channels. They are alternately filled with soil by tillage operations and re-formed in the same general location by subsequent runoff events. Classical gullies are also concentrated flow channels formed when rills converge. These are well defined, permanent incised drainageways that cannot be crossed by ordinary farming operations.

Other forms of erosion that are related to soil erosion by water include stream channel and geologic. Stream channel erosion refers to the degradation of channels and waterways. Geologic erosion refers to long-term erosion effects, as opposed to accelerated erosion events discussed in the Subpart.

No reliable methods exist for predicting the rate of ephemeral gully, classical gully, stream channel, or geologic erosion. The remainder of this part deals only with prediction and control of sheet and rill erosion.

**501.11 The water erosion process**

The processes of sheet and rill erosion are detachment, transport, and deposition of soil particles caused by raindrop impact and surface runoff.

Detachment is the removal of particles from the soil mass and is expressed in units, such as tons per acre. When soil particles are removed from the mass, they are referred to as sediment.

The movement of sediment downslope is sediment transport. A measure of sediment transport is sediment load. Sediment load on a slope increases with distance downslope as long as detachment is occurring. That is, detachment adds to the sediment load.

Where runoff is slowed at the base of a slope or by dense vegetation, deposition occurs, which is the transfer of sediment from the sediment load to the soil mass. That is, deposition removes sediment from the sediment load, and accumulates on the soil surface.

Two types of deposition, remote and local, occur. Remote deposition occurs some distance away from the origin of the sediment. Deposition at the toe of a concave slope, on the uphill side of vegetative strips, and in terrace channels are examples of remote deposition. Local deposition is where sediment is deposited near, within several inches, of where it is detached. Deposition in microdepressions and in low gradient furrows are examples of local deposition.

## Subpart 501C Estimating sheet and rill erosion

### 501.20 How, why, and by whom water erosion is estimated

NRCS estimates soil erosion by water as part of its technical assistance to land users. In conservation planning, erosion estimates are made for an existing management system and compared with alternative systems and with soil loss tolerance, T, values.

In addition, soil loss estimates are used to inventory natural resources, evaluate the effectiveness of conservation programs and land treatment, and estimate sediment production from fields that might become sediment yield in watersheds.

In March 1995, NRCS adopted RUSLE as the official tool for predicting soil erosion by water. NRCS continues to use USLE for certain provisions of Farm Bill programs and for the NRCS National Resources Inventory (NRI).

### 501.21 Methods of estimating sheet and rill erosion

Efforts to predict soil erosion by water started in the 1930's. Cook (1936) identified the major variables that affect erosion by water. Zingg (1940) published the first equation for calculating field soil loss. Smith and Whitt (1947) presented an erosion-estimating equation that included most of the factors present in modern soil loss equations. The Musgrave equation (Musgrave 1947) was a soil loss equation developed for farm planning. Finally, an effort was initiated to develop a national equation from the various state and regional equations that existed in the 1950's. In 1954, the Agricultural Research Service established the National Runoff and Soil Loss Data Center at Purdue University in West Lafayette, Indiana, to consolidate all available erosion data. Using the data assembled at the Data Center, Wischmeier and Smith (1965) developed the Universal Soil Loss Equation (USLE).

The USLE was a consolidation of several regional soil loss equations, and was based on summarizing and statistical analyses of more than 10,000 plot-years of basic runoff and soil loss data from 49 U.S. locations (Agriculture Handbook 703, 1997; Wischmeier and Smith 1965, 1978).

The USLE was designed to provide a convenient working tool for conservationists. It quantifies soil erosion as a product of six factors representing rainfall and runoff erosiveness, soil erodibility, slope length, slope steepness, cover-management practices, and supporting practices.

### 501.22 The Revised Universal Soil Loss Equation

Since March 1995, the Revised Universal Soil Loss Equation (RUSLE) has been used by NRCS to estimate soil loss by water (Agriculture Handbook 703.).

RUSLE predicts long-term average annual soil loss from sheet and rill erosion. RUSLE is an update of the Universal Soil Loss Equation (USLE) as described in Agriculture Handbook 537 (Wischmeier and Smith 1978). RUSLE utilizes a computer program to facilitate the calculations. RUSLE technology reflects the analysis of research data that were unavailable when Agriculture Handbook 282 (Wischmeier and Smith 1965) and Agriculture Handbook 537 were completed.

### 501.23 Limitations of the equation

The term *Universal* distinguishes the USLE and RUSLE from State and regionally based models that preceded them. However, the use of the USLE and RUSLE is limited to situations where factors can be accurately evaluated and to conditions for which they can be reliably applied (Wischmeier 1978; Agriculture Handbook 703, 1997).

RUSLE predicts long-term average annual soil loss carried by runoff from specific field slopes under specified cover and management systems. It is substantially less accurate for the prediction of specific erosion events associated with single storms and short-term random fluctuations.

RUSLE also estimates sediment yield for the amount of eroded soil leaving the end of a slope with certain support practices (see 501.35). It does not predict sediment yield for the amount of sediment that is delivered to a point in a watershed, such as the edge of a field, that is remote from the origin of the detached soil particles. Nor does RUSLE predict erosion that occurs in concentrated flow channels.

### 501.24 Alternative methods of applying RUSLE

ARS released RUSLE in 1992 as a computer program in the DOS environment. The model calculates soil loss from a field slope using values for each factor and using data elements from climate, plant, and field operation data bases.

Since 1993, RUSLE has been implemented in many NRCS field offices in hardcopy form in the Field Office Technical Guide (FOTG). State and area agronomists have developed tables and charts containing values for each of the RUSLE factors. Since the RUSLE module in Field Office Computing System (FOCS) is no longer supported by the Information Technology Center, NRCS will continue to implement RUSLE technology using charts and tables in the FOTG.

### 501.25 Data needed to support RUSLE

RUSLE uses soil erodibility, K, values from the NASIS Soils Database. Climatic data is obtained from National Weather Service weather stations with reliable long-term data. State and area agronomists have developed cover and management factor, C, values for common cropping systems.

The crop data base in the DOS RUSLE program contains plant growth and residue production parameters. These variables for key crops are listed in chapter 7 of Agriculture Handbook 703. Values for many of these parameters are available in a data base for a wide variety of plants. A user interface, the Crop Parameter Intelligent Data System (CPIDS) (Deer-Ascough et al. 1995), allows the user to search the data base. The USDA, ARS, National Soil Erosion Research Laboratory, West Lafayette, Indiana, maintains CPIDS.

Development and maintenance of data bases used by NRCS in erosion prediction models are the responsibility of NRCS agronomists at the State and national levels. Refer to Part 509 in this Manual for more detailed information on data base management and instructions. The national agronomist maintains a data base management plan that identifies the process of developing and maintaining data bases needed to support RUSLE. Data bases for some States are available in electronic format on the Fort Worth server.

## 501.26 Tools for using RUSLE

Maps of rainfall and runoff factors,  $R$  and  $R_{eq}$  (see part 501.31) for the continental United States plus Hawaii are available in Agriculture Handbook 703, figures 2-1 to 2-5 and figures 2-15 and 2-16. Additional climate-related data and inputs are available in this chapter. Most states and Basin Areas have developed county-based climatic maps for their areas. These contain the greater detail that is desired when applying RUSLE to specific field situations, and are available in NRCS State offices.

Soil erodibility factor,  $K$ , values for RUSLE are available in the NASIS Soils Database and in other soils data bases and tables. In areas of the United States where  $K$  values are adjusted to account for seasonal variability, (Agriculture Handbook 703) tables are available in State offices that show how the values are rounded to the nearest class and subclass.

Four slope length and steepness,  $L$  and  $S$ , table options are available in RUSLE.  $LS$  values can be obtained from tables 4-1 to 4-4 in Agriculture Handbook 703. The RUSLE computer program also calculates  $LS$  factor values for both uniform and complex slopes.

Cover and management factor,  $C$ , values are available in electronic table format in tables in most State offices and in the Field Office Technical Guide. Hardcopy tables are available in most State offices.

Support practice factor,  $P$ , values are calculated using tables available in the FOTG in many states. Copies, where available, can be obtained from the State office. Table values for common stripcropping and buffer strip systems are available in the FOTG of some states.

## Subpart 501D RUSLE factors

### 501.30 The average annual soil loss estimate, $A$

The long time average annual soil loss,  $A$ , is the computed spatial average soil loss and temporal average soil loss per unit of area, expressed in the units for  $K$  and for the period selected for  $R$ .

As applied by NRCS, the units for  $K$  and the period for  $R$  are selected so that  $A$  is expressed in tons per acre per year. RUSLE predicts the soil loss carried by runoff from specific field slopes in specified cover and management systems.

### 501.31 The rainfall and runoff erosivity factor, $R$

The rainfall and runoff erosivity factor,  $R$ , is the product of total storm energy times the maximum 30-minute intensity. Stated another way, the average annual total of the storm energy and intensity values in a given location is the rainfall erosion index,  $R$ , for the locality. The  $R$  factor represents the long-term average annual summation of the Erosivity Index (EI) for extended period of record.

In dryland cropping areas of the Northwest Wheat and Range Region, the effect of melting snow, rain on snow, and/or rain on thawing soil poses unique problems. An equivalent  $R$  value,  $R_{eq}$ , is calculated for these areas to account for this added runoff.

### 501.32 The soil erodibility factor, $K$

The soil erodibility factor,  $K$ , is a measure of erodibility for a standard condition. This standard condition is the unit plot, which is an erosion plot 72.6 feet (22.1 ) long on a 9 percent slope, maintained in continuous fallow, tilled up and down hill periodically to control weeds and break crusts that form on the soil surface. The erodibility factor  $K$  represents the combined effect of susceptibility of soil to detachment, transport of sediment and the amount and rate of runoff caused by a particular rainfall event. Soil properties that affect soil erodibility include texture, structure, per-

meability and organic matter content. Values for K should be selected from those given in the NRCS soil survey database in NASIS or in published reports the RUSLE soil erodibility nomograph can also be used to estimate K values for most soils. Soil erodibility K varies by season. It tends to be high in early spring during and immediately following thawing, and other periods when the soil is wet. NRCS further modifies the seasonally adjusted K by rounding the value to the nearest K factor class or half-class (exhibit 501-1).

Rock fragments in the soil profile affect the soil erodibility factor <sup>1/</sup>. The K value is adjusted upwards to account for rock fragments in the soil profile of sandy soils that reduce infiltration. No adjustment to the K value is recommended by NRCS for rocks in the profile of medium and heavy textured soils.

### 501.33 The slope length and steepness factors, L and S

The slope length factor, L, is the ratio of soil loss from the field slope length to soil loss from a 72.6-foot length under identical conditions.

The slope steepness factor, S, is the ratio of soil loss from the field slope gradient to soil loss from a 9 percent slope under otherwise identical conditions.

In erosion prediction as used by NRCS, the factors L and S are evaluated together, and LS values for uniform slopes can be selected from tables 4-1, 4-2, 4-3, and 4-4 in Agriculture Handbook 703.

The slope length is defined as the horizontal distance from the origin of overland flow to the location of either concentrated flow or deposition. Slope lengths normally do not exceed 400 feet because sheet and rill flows will almost always coalesce into concentrated flow paths within that distance. Lengths longer than 1,000 feet should not be used in RUSLE.

Slope length and steepness determinations are best made in the field. In conservation planning, the hillslope profile representing a significant portion of the field having the most severe erosion is often chosen. Slope lengths are best determined by pacing out flow paths and making measurements

directly on the ground. Steep slopes should be converted to horizontal distances. Slope steepness determinations are best made in the field using a clinometer, Abney level or similar device. Chapter 4, Agriculture Handbook 703 contains additional guides for choosing and measuring slopes.

Most naturally occurring hillslope profiles are irregular in shape. When the slope profile is significantly curved (convex or concave, or sigmoid.convex at the shoulder and concave at the toe), the conservationist should represent it as a series of slope segments, using the irregular slope procedure in the RUSLE computer program.

### 501.34 The cover-management factor, C

The cover-management factor, C, is the ratio of soil loss from an area with specified cover and management to soil loss from an identical area in tilled continuous fallow. The C factor is used most often to compare the relative impacts of management options on conservation plans.

The impacts of cover and management on soil losses are divided into a series of subfactors in RUSLE. These include the impacts of previous vegetative cover and management, canopy cover, surface roughness, and in some cases the impact of soil moisture.

In RUSLE, these subfactors are assigned values, and when multiplied together yield a soil loss ratio (SLR). Individual SLR values are calculated for each period over which the important parameters are assumed to remain constant. Each SLR value is then weighted by the fraction of rainfall and runoff erosivity, EI, associated with the corresponding period, and these weighted values are combined (summed) into an overall C factor value.

### 501.35 The support practice factor, P

The support practice factor, P, is the ratio of soil loss with a support practice like contouring, stripcropping, or terracing to soil loss with straight-row farming up and down the slope.

The contour P subfactor accounts for the beneficial effects of redirected runoff that modifies the flow pattern because of ridges or oriented roughness that are partially or completely oriented along the contour.

<sup>1/</sup> Rock fragments on the soil surface are accounted for in the C factor.



The contour P subfactor includes the effects of storm severity, ridge height, off-grade contouring, slope length and steepness, infiltration, and soil cover and roughness.

The stripcropping P subfactor is a support practice where strips of clean-tilled or nearly clean-tilled crops are alternated with strips of close growing vegetation, or strips with relatively smooth tilled soil surfaces are alternated with strips with rough tilled surfaces.

The stripcropping P subfactor evaluates what are variously described as contour stripcropping, cross-slope stripcropping, field stripcropping, buffer strips and vegetated filter strips.

Terraces in RUSLE are support practices where high and large ridges of soil are constructed across the slope at intervals. These ridges and their accompanying channels intercept runoff and divert it around the slope or into a closed outlet. Terraces can affect sheet and rill erosion by reducing slope length and cause deposition in the terrace channel.

Tile drainage, under optimum conditions, can reduce erosion by reducing runoff. Because of a lack of support data, NRCS does not use the tile drainage subfactor in RUSLE, except in the Willamette Valley in the Oregon and Puget Sound basin in Washington.

In addition to the support practice factor, P, used in conservation planning, RUSLE estimates sediment yield for contour strips and terraces. The sediment yield, or delivery ratio, used in RUSLE is the ratio to the amount of sediment leaving the end of the slope length to the amount of sediment produced on the slope length.

## Subpart 501E Principles of water erosion control

### 501.40 Overview of principles

The principle factors that influence soil erosion by water are climate, soil properties, topography, vegetative cover, and conservation practices. Climate and soil properties are conditions of the site and are not modified by ordinary management measures. Conservation treatment primarily involves manipulation of vegetative cover, modification of topography, and manipulation of soil conditions in the tillage zone.

The greatest deterrent to soil erosion by water is vegetative cover, living or dead, on the soil surface. Cover and cultural practices influence both the detachment of soil particles and their transport. Growing plants and plant residue absorb the energy of raindrops, decrease the velocity of runoff water, and help create soil conditions that resist erosion. Cultural practices that affect vegetative cover include crop rotations, cover crops, management of crop residue, and tillage practices.

### 501.41 Relation of control to RUSLE factors

In conservation planning, the cover and management factor, C, and the support practices factor, P, can be manipulated in RUSLE to develop alternatives for erosion reduction. In addition, where slope length is reduced with some terrace and diversion systems, the slope length and steepness factor, LS, will be reduced.

Using RUSLE technology, estimates of erosion reduction are illustrated in the subfactors of factor C.

Benefits to erosion control are achieved in the:

- prior land use subfactor by increasing the mass of roots and buried residue and increasing periods since soil disturbance,
- canopy cover subfactor by increasing the canopy cover of the field area and low raindrop fall height from the canopy,
- surface cover subfactor by increasing the ground cover of plant residue, and by permanent cover such as rock fragments,
- surface roughness subfactor by increasing the random surface roughness that ponds water, and thereby reduces the erosive effect of raindrops and traps sediment, and



- soil moisture subfactor by growing moisture-depleting crops. This benefit is only applied in RUSLE in the Northwest Wheat and Range Region of the western United States.

When support practices are applied, they become integral parts of a resource management system for controlling soil erosion by water. Contour farming, contour stripcropping, and conservation buffers form ridges on or near the contour that slow runoff and trap sediment. Terraces and diversions intercept concentrated runoff flows and, in many cases, shorten the length of slope.

Some erosion control practices, such as grassed waterways and water control structures, do not substantially reduce sheet and rill erosion. While these can be effective erosion control practices in a resource management system, they are not a part of the soil loss reduction that is estimated by RUSLE.

## Subpart 501F References

- Cook, H.L. 1936. The nature and controlling variables of the water erosion process. *Soil Sci. Soc. Am. Proc.* 1:60-64.
- Deer-Ascough, L.A., G.A. Weesies, J.C. Ascough II, and J.M. Laflen. 1995. Plant Parameter Database for Erosion Prediction Models. *Applied Engineering in Agriculture*, 11(5):659-666.
- Foster, G.R., G.A. Weesies, D.K. McCool, D.C. Yoder, and K.G. Renard. 1997. Revised Universal Soil Loss Equation User's Manual. U.S. Department of Agriculture, Natural Resources Conservation Service. (unpublished draft).
- Musgrave, G.W., and R.A. Norton. 1937. Soil and water conservation investigations at the Soil Conservation Experiment Station Missouri Valley Loess Region, Clarinda, Iowa, Progress Report, 1931-35. U.S. Department of Agriculture Tech. Bull. 558.
- Renard, K.G., G.R. Foster, G.A. Weesies, D.K. McCool, and D.C. Yoder, coordinators. 1997. Predicting Soil Erosion by Water: A Guide to Conservation Planning With the Revised Universal Soil Loss Equation (RUSLE). U.S. Department of Agriculture Handbook No. 703, 404 pp.
- Smith, D.D., and D.M. Whitt. 1947. Estimating soil losses from field areas of claypan soil. *Soil Sci. Soc. Am.* 12:485-490.
- Wischmeier, W.H., and D.D. Smith. 1965. Predicting rainfall-erosion losses from cropland east of the Rocky Mountains: Guide for selection of practices for soil and water conservation. U.S. Department of Agriculture Handbook No. 282.
- Wischmeier, W.H., and D.D. Smith. 1978. Predicting rainfall erosion losses: A guide to conservation planning. U.S. Department of Agriculture Handbook No. 537.
- Zingg, A.W. 1940. Degree and length of land slope as it affects soil loss in runoff. *Agric. Eng.* 21:59-64.

# Subpart 501G

# Exhibit

**Exhibit 501-1** Acceptable class and half-class factor K values for use in RUSLE where K values are adjusted for seasonal variability.

Original K value <sup>1/</sup>	Minimum value <sup>2/</sup>	Maximum value <sup>3/</sup>	Acceptable class and half-class K factor values <sup>4/</sup>					
0.02	0.016	0.024	0.02					
0.05	0.04	0.06	0.05					
0.10	0.08	0.12	0.08	0.10	0.12			
0.15	0.12	0.18	0.12	0.15	0.17			
0.17	0.136	0.204	0.15	0.17	0.20			
0.20	0.16	0.24	0.17	0.20	0.22	0.24		
0.24	0.192	0.288	0.20	0.22	0.24	0.26	0.28	
0.28	0.224	0.336	0.24	0.26	0.28	0.30	0.32	
0.32	0.256	0.384	0.26	0.28	0.30	0.32	0.35	0.37
0.37	0.296	0.444	0.30	0.32	0.35	0.37	0.40	0.43
0.43	0.344	0.516	0.35	0.37	0.40	0.43	0.46	0.49
0.49	0.392	0.588	0.40	0.43	0.46	0.49	0.52	0.55
0.55	0.44	0.66	0.46	0.49	0.52	0.55	0.60	0.64
0.64	0.512	0.768	0.52	0.55	0.60	0.64	0.70	0.76

1/ Original K value from the soils data base for a specific map unit or soil component.

2/ Minimum value is 80% of the original K value, and is the cap for acceptable minimum class and half-class values.

3/ Maximum value is 120% of the original K value, and is the cap for the acceptable maximum class and half-class values.

4/ Acceptable class and half-class K factor values, were approved 4/15/94 by a joint committee of NRCS soil scientists and agronomists, under the leadership of H.R. Sinclair, lead soil scientist.

Contents:	<b>Subpart 502A</b>	<b>Introduction</b>	502-1
		502.00 Overview .....	502-1
	<b>Subpart 502B</b>	<b>Wind erosion</b>	502-1
		502.10 The wind erosion problem .....	502-1
		502.11 The wind erosion process .....	502-2
	<b>Subpart 502C</b>	<b>Estimating wind erosion</b>	502-3
		502.20 How, why, and by whom wind erosion is estimated .....	502-3
		502.21 Methods of estimating wind erosion .....	502-3
		502.22 The wind erosion equation .....	502-3
		502.23 Limitations of the equation .....	502-5
		502.24 Alternative procedures for using the WEQ .....	502-5
		502.25 Data to support the WEQ .....	502-6
		502.26 Using WEQ estimates with USLE or RUSLE calculations .....	502-6
		502.27 Tools for using the WEQ .....	502-6
	<b>Subpart 502D</b>	<b>WEQ Factors</b>	502-7
		502.30 The wind erosion estimate, E .....	502-7
		502.31 Soil erodibility index, I .....	502-7
		502.32 Soil roughness factor K, ridge and random roughness .....	502-10
		502.33 Climatic factor, C .....	502-12
		502.34 Unsheltered distance, L .....	502-14
		502.35 Vegetative cover factor, V .....	502-16
	<b>Subpart 502E</b>	<b>Principles of wind erosion control</b>	502-17
		502.40 General .....	502-17
		502.41 Relation of control to WEQ factors .....	502-17
		502.42 Tolerances in wind erosion control .....	502-18
	<b>Subpart 502F</b>	<b>Example problems</b>	502-19
	<b>Subpart 502G</b>	<b>References</b>	502-99

<b>Figures</b>	<b>Figure 502-1</b>	The wind erosion process	502-2
	<b>Figure 502-2</b>	Graphic of knoll erodibility	502-9
	<b>Figure 502-3</b>	Detachment, transport, and deposition on ridges and furrows	502-10

	<b>Figure 502-4</b>	Chart to determine soil ridge roughness factor, $K_{rd}$ , from ridge roughness, $K_r$ , (inches)	502-10
	<b>Figure 502-5</b>	Unsheltered distance L	502-14
	<b>Figure 502-6</b>	Unsheltered distance L, perennial vegetation (pasture or range)	502-14
	<b>Figure 502-7</b>	Unsheltered distance L – windbreak or barrier	502-14
	<b>Figure 502-8</b>	Unsheltered distance L, stripcropping system	502-15
<b>Exhibits</b>	<b>Exhibit 502-1</b>	Example E table	502-21
	<b>Exhibit 502-2</b>	Wind erodibility groups and wind erodibility index	502-22
	<b>Exhibit 502-3</b>	Sieving instructions	502-23
	<b>Exhibit 502-4</b>	Ridge roughness factor, $K_{rd}$ , graphs	502-26
	<b>Exhibit 502-5</b>	Ridge roughness factor, $K_{rd}$ , tables	502-31
	<b>Exhibit 502-6</b>	Random roughness factor, $K_{rr}$ , graph	502-47
	<b>Exhibit 502-7a</b>	Example of erosive wind data available for specific locations	502-49
	<b>Exhibit 502-7b</b>	Example of wind erosion calculation using the management period procedure	502-50
	<b>Exhibit 502-8</b>	C factor map, United States	502-51
	<b>Exhibit 502-9</b>	Procedures for developing local C factors	502-52
	<b>Exhibit 502-10</b>	Flat small grain equivalent charts	502-57
	<b>Exhibit 502-11</b>	Estimating small grain equivalents for untested vegetation	502-95
	<b>Exhibit 502-12</b>	Estimating small grain equivalents of mixed vegetative cover that has two or more components	502-97
	<b>Exhibit 502-13</b>	Crop yield-residue conversion (Reserved, to be developed)	502-98
	<b>Exhibit 502-14</b>	Residue reduction by tillage (Reserved, to be developed)	502-98
	<b>Exhibit 502-15</b>	E Tables; Soil loss from wind erosion in tons per acre per year (Insert appropriate E tables for local values of climatic factor, C)	502-98
	<b>Exhibit 502-16</b>	Wind physics (Reserved to be developed)	502-98
<b>Exhibit 502-17</b>	Wind erosion control exhibits (Reserved, to be developed)	502-98	
<b>Tables</b>	<b>Table 502-1</b>	Knoll erodibility adjustment factor for I	502-8
	<b>Table 502-2</b>	I adjustment guidelines for crusts	502-8
	<b>Table 502-3</b>	Wind erosion direction factors	502-15
	<b>Table 502-4</b>	Crop tolerance to blowing soil	502-19
	<b>Table 502-5A</b>	Angle of deviation = 0 degrees; $I = <134$	502-32
	<b>Table 502-5B</b>	Angle of deviation = 22.5 degrees; $I = <134$	502-32

<b>Table 502-5C</b>	Angle of deviation = 45 degrees; I = <134	502-33
<b>Table 502-5D</b>	Angle of deviation = 67.5 degrees; I = <134	502-33
<b>Table 502-5E</b>	Angle of deviation = 90 degrees; I = <134	502-34
<b>Table 502-5F</b>	Angle of deviation = 0 degrees; I = 134	502-34
<b>Table 502-5G</b>	Angle of deviation = 22.5 degrees; I = 134	502-35
<b>Table 502-5H</b>	Angle of deviation = 45 degrees; I = 134	502-35
<b>Table 502-5I</b>	Angle of deviation = 67.5 degrees; I = 134	502-36
<b>Table 502-5J</b>	Angle of deviation = 90 degrees; I = 134	502-36
<b>Table 502-5K</b>	Angle of deviation = 0 degrees; I = 160 and 180	502-37
<b>Table 502-5L</b>	Angle of deviation = 22.5 degrees; I = 160 and 180	502-37
<b>Table 502-5M</b>	Angle of deviation = 45 degrees; I = 160 and 180	502-38
<b>Table 502-5N</b>	Angle of deviation = 67.5 degrees; I = 160 and 180	502-38
<b>Table 502-5O</b>	Angle of deviation = 90 degrees; I = 160 and 180	502-39
<b>Table 502-5P</b>	Angle of deviation = 0 degrees; I = 220	502-39
<b>Table 502-5Q</b>	Angle of deviation = 22.5 degrees; I = 220	502-40
<b>Table 502-5R</b>	Angle of deviation = 45 degrees; I = 220	502-40
<b>Table 502-5S</b>	Angle of deviation = 67.5 degrees; I = 220	502-41
<b>Table 502-5T</b>	Angle of deviation = 90 degrees; I = 220	502-41
<b>Table 502-5U</b>	Angle of deviation = 90 degrees; I = 250	502-42
<b>Table 502-5V</b>	Angle of deviation = 22.5 degrees; I = 250	502-42
<b>Table 502-5W</b>	Angle of deviation = 45 degrees; I = 250	502-43
<b>Table 502-5X</b>	Angle of deviation = 67.5 degrees; I = 250	502-43
<b>Table 502-5Y</b>	Angle of deviation = 90 degrees; I = 250	502-44
<b>Table 502-5Z</b>	Angle of deviation = 0 degrees; I = 310	502-44
<b>Table 502-5AA</b>	Angle of deviation = 22.5 degrees; I = 310	502-45
<b>Table 502-5BB</b>	Angle of deviation = 45 degrees; I = 310	502-45
<b>Table 502-5CC</b>	Angle of deviation = 67.5 degrees; I = 310	502-46
<b>Table 502-5DD</b>	Angle of deviation = 90 degrees; I = 310	502-46
<b>Table 502-6</b>	Table converts random roughness heights (standard deviation in inches) to WEQ K subfactors (Krr) for random roughness. Krr values vary by I factors assigned to soil Wind Erodibility Groups	502-47
<b>Table 502-7</b>	Random roughness (standard deviation) core values	502-48
<b>Table 502-8a</b>	Wind erosion direction factor; angle of deviation 1/ = 0 degrees	502-54
<b>Table 502-8b</b>	Wind erosion direction factor; angle of deviation 1/ = 22.5 degrees	502-54
<b>Table 502-8c</b>	Wind erosion direction factor; angle of deviation 1/ = 45 degrees	502-55
<b>Table 502-8d</b>	Wind erosion direction factor; angle of deviation 1/ = 67.5 degrees	502-55
<b>Table 502-8e</b>	Wind erosion direction factor; angle of deviation 1/ = 90 degrees	502-56



---

**Subpart 502A Introduction****502.00 Overview**

Part 502 presents Natural Resources Conservation Service (NRCS) policy and procedures for estimating wind erosion. It explains the Wind Erosion Equation (WEQ) and provides guidance and reference on wind erosion processes, prediction, and control. NRCS technical guidance related to wind erosion conforms to policy and procedures in this part.

This part will be amended as additional research on wind erosion and its control is completed and published. The national agronomist is responsible for updating this chapter and coordinating wind erosion guidance with Agricultural Research Service (ARS).

NRCS cooperating scientists may supplement this manual. However, appropriate supplements prepared by cooperating scientists are to be submitted to the national agronomist for review and concurrence before issuance. State supplements are to be reviewed and approved by the national agronomist before being issued to field offices.

Understanding the erosive forces of wind is essential to the correct use of the Wind Erosion Equation and interpretation of wind erosion data. NRCS predicts erosion rates, assesses potential damage, and plans control systems for wind erosion.

The Agricultural Research Service has primary responsibility for erosion prediction research within the U.S. Department of Agriculture (USDA). Wind erosion research is conducted by the Wind Erosion Research Unit at Manhattan, Kansas, and the Cropping Systems Research Unit at Big Spring, Texas.

---

**Subpart 502B Wind erosion****502.10 The wind erosion problem**

Wind is an erosive agent. It detaches and transports soil particles, sorts the finer from the coarser particles, and deposits them unevenly. Loss of the fertile topsoil in eroded areas reduces the rooting depth and, in many places, reduces crop yield. Abrasion by airborne soil particles damages plants and constructed structures. Drifting soil causes extensive damage also. Sand and dust in the air can harm animals, humans, and equipment.

Some wind erosion has always occurred as a natural land-forming process, but it has become detrimental as a result of human activities. This *accelerated* erosion is primarily caused by improper use and management of the land (Stallings 1951).

Few regions are entirely safe from wind erosion. Wherever the soil surface is loose and dry, vegetation is sparse or absent, and the wind sufficiently strong, erosion will occur unless control measures are applied (1957 Yearbook of Agriculture). Soil erosion by wind in North America is generally most severe in the Great Plains. The NRCS annual report of wind erosion conditions in the Great Plains shows that wind erosion damages from 1 million to more than 15 million acres annually, averaging more than 4 million acres per year in the 10-state area. USDA estimated that nearly 95 percent of the 6.5 million acres put out of production during the 1930's suffered serious wind erosion damage (Woodruff 1975). Other major regions subject to damaging wind erosion are the Columbia River plains; some parts of the Southwest and the Colorado Basin, the muck and sandy areas of the Great Lakes region, and the sands of the Gulf, Pacific, and Atlantic seaboard.

In some areas, the primary problem caused by wind erosion is crop damage. Some crops are tolerant enough to withstand or recover from erosion damage. Other crops, including many vegetables and specialty crops, are especially vulnerable to wind erosion damage. Wind erosion may cause significant short-term economic loss in areas where erosion rates are below the soil loss tolerance (T) when the crops grown in that area are easily damaged by blowing soil (table 502-4).

## 502.11 The wind erosion process

The wind erosion process is complex. It involves detaching, transporting, sorting, abrading, avalanching, and depositing of soil particles. Turbulent winds blowing over erodible soils cause wind erosion. Field conditions conducive to erosion include

- loose, dry, and finely granulated soil;
- smooth soil surface that has little or no vegetation present;
- sufficiently large area susceptible to erosion; and
- sufficient wind velocity to move soil.

Winds are considered erosive when they reach 13 miles per hour at 1 foot above the ground or about 18 miles per hour at a 30 foot height. This is commonly referred to as the threshold wind velocity (Lyles and Krauss 1971).

The wind transports primary soil particles or stable aggregates, or both, in three ways (fig. 502–1):

**Saltation**—Individual particles/aggregates ranging from 0.1 to 0.5 millimeter in diameter lift off the surface at a 50- to 90-degree angle and follow distinct trajectories under the influence of air resistance and gravity. The particles/aggregates return to the surface at impact angles of 6 to 14 degrees from the horizontal. Whether they rebound or embed themselves, they initiate movement of other particles/aggregates to create the *avalanching* effect. Saltating particles are the abrading *bullets* that remove the protective soil crusts and clods. Most saltation occurs within 12 inches above the soil surface and typically, the length of a saltating particle trajectory is about 10 times the height. From 50 to 80 percent of total transport is by saltation.

**Suspension**—The finer particles, less than 0.1 millimeter in diameter, are dislodged from an eroding area by saltation and remain in the air mass for an extended period. Some suspension-sized particles or aggregates are present in the soil, but many are created by abrasion of larger aggregates during erosion. From 20 percent to more than 60 percent of an eroding soil may be carried in suspension, depending on soil texture. As a general rule, suspension increases downwind, and on long fields can easily exceed the amount of soil moved in saltation and creep.

**Surface creep**—Sand-sized particles/aggregates are set in motion by the impact of saltating particles. Under high winds, the whole soil surface appears to be creeping slowly forward as particles are pushed and rolled by the saltation flow. Surface creep may account for 7 to 25 percent of total transport (Chepil 1945 and Lyles 1980).


Saltation and creep particles are deposited in vegetated strips, ditches, or other areas sheltered from the wind, as long as these areas have the capacity to hold the sediment. Particles in suspension, however, may be carried a great distance.

The rate of increase in soil flow along the wind direction varies directly with erodibility of field surfaces. The increase in erosion downwind (avalanching) is associated with the following processes:

- the increased concentration of saltating particles downwind increases the frequency of impacts and the degree of breakdown of clods and crusts, and
- accumulation of erodible particles and breakdown of clods tends to produce a smoother (and more erodible) surface.

The distance required for soil flow to reach a maximum for a given soil is the same for any erosive wind. The more erodible the surface, the shorter the distance in which maximum flow is reached. Any factor that influences the erodibility of the surface influences the increase in soil flow.

**Figure 502-1** The wind erosion process





## Subpart 502C Estimating wind erosion

### 502.20 How, why, and by whom wind erosion is estimated

Using the Wind Erosion Equation (WEQ), NRCS estimates erosion rates to

- provide technical assistance to land users,
- inventory natural resources, and
- evaluate the effectiveness of conservation programs and conservation treatment applied to the land.

Wind erosion is difficult to measure. Wind moves across the land in a turbulent, erratic fashion. Soil may blow into, within, and out of a field in several directions in a single storm. The direction, velocity, duration, and variability of the wind all affect the erosion that occurs from a wind storm. Much of the soil eroding from a field bounces or creeps near the surface; however, some of the soil blown from a field may be high above the ground in a dust cloud by the time it reaches the edge of a field (Chepil 1963).

### 502.21 Methods of estimating wind erosion

No precise method of measuring wind erosion has been developed. However, various dust collectors, remote and in-place sensors, wind tunnels, sediment samplers, and microtopographic surveys before and after erosion have been used. Each method has its limitations. Research is continuing on new techniques and new devices, on modifications to older ones, and on means to measure wind erosion.

Estimates of wind erosion can be developed by assigning numerical values to the site conditions that govern wind erosion and expressing their relationships mathematically. This is the basis of the current Wind Erosion Equation (WEQ) that considers soil erodibility, ridge and random roughness, climate, unsheltered distance, and vegetative cover.

### 502.22 The wind erosion equation

The Wind Erosion Equation (WEQ) erosion model is designed to predict long-term average annual soil losses from a field having specific characteristics. With appropriate selection of factor values, the equation will estimate average annual erosion or erosion for specific time periods.

#### Development of the wind erosion equation

Drought and wind erosion during the 19th century caused wind erosion to be recognized as an important geologic phenomenon. By the late 1930's, systematic and scientific research into wind erosion was being pioneered in California, South Dakota, Texas, and in Canada and England. This research produced information on the mechanics of soil transport by wind, the influence of cultural treatment on rates of movement, and the influence of windbreaks on windflow patterns. The publication, *The Physics of Blown Sand and Desert Dunes*, (Bagnold 1941), is considered a classic by wind erosion researchers.

In 1947, USDA began the Wind Erosion Research Program at Manhattan, Kansas, in cooperation with Kansas State University. That program was started under the leadership of Austin W. Zingg, who was soon joined by W.S. Chepil, a pioneer in wind erosion research in Canada. The research project's primary purposes were to study the mechanics of wind erosion, delineate major influences on that erosion, and devise and develop methods to control it.

By 1954, Chepil and his coworkers began to publish results of their research in the form of wind erosion prediction equations (Chepil 1954; Chepil 1957; Chepil et al. 1955; Woodruff and Chepil 1956).

In 1959, Chepil released an equation

$$E = IRKFBWD$$

where:

- E = quantity of erosion
- I = soil cloddiness
- R = residue
- K = roughness
- F = soil abrasability
- B = wind barrier
- W = width of field
- D = wind direction

Wind velocity at geographic locations was not addressed in this equation (Chepil 1959).

In 1962, Chepil's group released the equation

$$E = f(ACKLV)$$

where:

A = percentage of soil fractions greater than 0.84 millimeter.

Factors C, K, L, and V were the same as in the present equation although they were not handled the same (Chepil 1962). A C-factor map for the western half of the United States was also published in 1962 (Chepil et al. 1962).

In 1963, the current form of the equation,  $E = f(ICKLV)$  was first released (Chepil 1963).

In 1965, the concept of preponderance in assessing wind erosion forces was introduced. See 502.34 for details on preponderance (Skidmore 1965 and Skidmore and Woodruff 1968).

In 1968, monthly climatic factors were published (Woodruff and Armbrust 1968). These are no longer used by NRCS. Instead, NRCS adopted a proposal for computing soil erosion by periods using wind energy distribution which was published in 1980 (Bondy et al. 1980). (See 502.24.) In 1981, the Wind Erosion Research Unit provided NRCS with data on the distribution of erosive wind energy for the United States and in 1982 provided updated annual C factors. (See exhibit 502-8.)

Although the present equation has significant limitations (see 502.23), it is the best tool currently available for making reasonable estimates of wind erosion. Currently, research and development of improved procedures for estimating wind erosion are underway.

The present Wind Erosion Equation is expressed as:

$$E = f(IKCLV)$$

where:

E = estimated average annual soil loss in tons per acre per year

f = indicates relationships that are not straight-line mathematical calculations

I = soil erodibility index

K = soil surface roughness factor

C = climatic factor

L = the unsheltered distance

V = the vegetative cover factor

The **I** factor, expressed as the average annual soil loss in tons per acre per year from a field area, accounts for the inherent soil properties affecting erodibility. These properties include texture, organic matter, and calcium carbonate percentage. **I** is the potential annual wind erosion for a given soil under a given set of field conditions. The given set of field conditions for which **I** is referenced is that of an isolated, unsheltered, wide, bare, smooth, level, loose, and non-crusted soil surface, and at a location where the climatic factor (C) is equal to 100. (For details on the **I** factor see 502.31).

The **K** factor is a measure of the effect of ridges and cloddiness made by tillage and planting implements. It is expressed as a decimal from 0.1 to 1.0. (For details on the **K** factor see 502.32.)

The **C** factor for any given locality characterizes climatic erosivity, specifically windspeed and surface soil moisture. This factor is expressed as a percentage of the **C** factor for Garden City, Kansas, which has a value of 100. (For details on the **C** factor see 502.33.)

The **L** factor considers the unprotected distance along the prevailing erosive wind direction across the area to be evaluated and the preponderance of the prevailing erosive winds. (For details on the **L** factor see 502.34.)

The **V** factor considers the kind, amount, and orientation of vegetation on the surface. The vegetative cover is expressed in pounds per acre of a flat small-grain residue equivalent. (For details on the **V** factor see 502.35.)

Solving the equation involves five successive steps. Steps 1, 2 and 3 can be solved by multiplying the factor values. Determining the effects of **L** and **V** (steps 4 and 5) involves more complex functional relationships.

Step 1:  $E_1 = I$

Factor **I** is established for the specific soil. **I** may be increased for knolls less than 500 feet long facing into the prevailing wind, or decreased to account for surface soil crusting, and irrigation.

Step 2:  $E_2 = IK$

Factor **K** adjusts  $E_1$  for tillage-induced oriented roughness,  $K_{rd}$  (ridges) and random roughness,  $K_{rr}$  (cloddiness). The value of **K** is calculated by multiplying  $K_{rd}$  times  $K_{rr}$ . ( $K = K_{rd} \times K_{rr}$ ).

Step 3:  $E_3 = IKC$

Factor C adjusts  $E_2$  for the local climatic factor.

Step 4:  $E_4 = IKCL$

Factor L adjusts  $E_3$  for unsheltered distance.

Step 5:  $E_5 = IKCLV$

Factor V adjusts  $E_4$  for vegetative cover.

- Erosion estimates developed using the critical period procedure are made using a single set of factor values (IKCL & V) in the equation to describe the critical wind erosion period conditions.
- The critical period procedure is currently used for resource inventories. NRCS usually provides specific instructions on developing wind erosion estimates for resource inventories.

### 502.23 Limitations of the equation

When the unsheltered distance,  $L$ , is sufficiently long, the transport capacity of the wind for saltation and creep is reached. If the wind is moving all the soil it can carry across a given surface, the inflow into a downwind area of the field is equal to the outflow from that same area of the field, for saltation and creep. The net soil loss from this specific area of the field is then only the suspension component. This does not imply a reduced soil erosion problem because, theoretically, there is still the estimated amount of soil loss in creep, saltation, and suspension leaving the downwind edge of the field.

Surface armoring by nonerodible gravel is not usually addressed in the **I** factor.

The equation does not account for snow cover or seasonal changes in soil erodibility. The equation does not estimate erosion from single storm events.

### 502.24 Alternative procedures for using the WEQ

The WEQ Critical Period Procedure is based on use of the Wind Erosion Equation as described by Woodruff and Siddoway in 1965 (Woodruff and Siddoway 1965). The conditions during the critical wind erosion period are used to derive the estimate of annual wind erosion.

- The Critical Wind Erosion Period is described as the period of the year when the greatest amount of wind erosion can be expected to occur from a field under an identified management system. It is the period when vegetative cover, soil surface conditions, and expected erosive winds result in the greatest potential for wind erosion.

The WEQ Management Period Procedure was published by Bondy, Lyles, and Hayes in 1980. It solves the equation for situations where site conditions have significant variation during the year or planning period where the soil is exposed to soil erosion for short periods, and where crop damage is the foremost conservation concern, rather than the extent of soil loss. The management period procedure is described as being more responsive to changing conditions throughout the cropping year but is not considered more accurate than the critical period procedure.

Comparisons should not be made between the soil erosion predictions made by the management period procedure and the critical period procedure. In other words, where a conservation system has been determined to be acceptable by the management period procedure and placed in a conservation plan or the FOTG, then only the management period procedure will be used to determine if other conservation systems, planned or applied, provide equivalent treatment.

Factor values are selected to describe management periods when cover and management effects are approximately uniform. The cropping system is divided into as many management periods as is necessary to describe the year or planning period accurately. Erosive wind energy (EWE) distribution is used to derive a weighted estimate of soil loss for the period. The general procedure is as follows:

- Solve for  $E$  in the basic equation ( $E = f(IKCLV)$ ) using management period values for  $I$ ,  $K$ ,  $L$ , and  $V$ , and the local annual value for  $C$ .
- Multiply the annual soil loss rate  $E$  obtained from management period values by the percentage of annual erosive wind energy that occurs during the management period to estimate average erosion for that management period.
- Add the management period amounts for the crop year, or add the period amounts for a total crop sequence and divide by the number of years in the sequence to estimate average annual wind erosion.

Exhibit 502–7a is an example of tables showing the expected monthly distribution of erosive wind energy at specific locations. The complete table is available for downloading at

<http://www.weru.ksu.edu/nrcs/windparm.doc>

Exhibit 502–7b shows how these values are used in the management period method computations. Erosive wind energy values are entered on the form in the column identified % EWE.

Estimates for management periods less than 1 year in duration are often useful in conservation planning. Examples include

- When crop damage (crop tolerance) during sensitive growth stages is the major concern.
- When a system or practice is evaluated for short-term effects.

States will use critical period or the management period procedure, within published guidelines, for conservation planning. The management period procedure will not be used for resource inventories unless specifically stated in instructions. Refer to individual program manuals for more specific instructions pertaining to the use of the Wind Erosion Equation.

Adjustments to the WEQ soil erodibility factor, **I**, can be made for temporary conditions that include irrigation or crusts, but such adjustments are to be used only with the management period procedure. The use of monthly preponderance data to determine equivalent field width is also applicable only to the management period procedure.

### 502.25 Data to support the WEQ

ARS has developed benchmark values for each of the factors in the WEQ. However, the NRCS is responsible for developing procedures and additional factor values for use of the equation. Field Office Technical Guides will include the local data needed to make wind erosion estimates.

ARS has computed benchmark **C** factors for locations where adequate weather data are available (Lyles 1983). **C** factors used in the field office are to reflect local conditions as they relate to benchmark **C** factors. Knowledge of local terrain features and local climate is needed to determine how point data can be extended and how interpolation between points should be done. See 502.33 for guidance.

ARS has developed soil erodibility **I** values based on size distribution of soil aggregates. Soils have been grouped by texture classes into wind erodibility groups. Wind erodibility group numbers are included in the soil survey data base in NASIS.

For further discussion of benchmark data supporting factor values, refer to subpart 502D, WEQ factors.

### 502.26 Using WEQ estimates with USLE or RUSLE calculations

The WEQ provides an estimate of average annual wind erosion from the field width along the prevailing wind erosion direction (**L**) entered in the calculation; USLE or RUSLE provide an estimate of average annual sheet and rill erosion from the slope length (**L**) entered into the model. Although both wind and water erosion estimates are in tons per acre per year, they are not additive unless the two equations represent identical flow paths across identical areas.

### 502.27 Tools for using the WEQ

Graphs and tables for determining factor values are in Subpart 502G Exhibits.

#### E tables

The ARS WEROS (Wind Erosion) computer program has produced tables that give estimated erosion (**E** values) for most of the possible combinations of **I**, **K**, **C**, **L**, and **V**. Exhibit 502–1 is an example. See 502.30 for procedures to download **E** tables.

Use of the management period procedure can be simplified through the use of worksheets on which information for each management period is documented. Subpart 502F is to include sample wind erosion computations using the Management Period Procedure.

An acceptable WEQ calculator has been developed in Microsoft Excel, and is being adapted for use in many states. A copy of this spreadsheet can be obtained from the NRCS state agronomist in Albuquerque, New Mexico. Exhibit 502.7B shows an example of this spread sheet.

Trade names mentioned are for specific information and do not constitute a guarantee or warranty of the product by the Department of Agriculture or an endorsement by the Department over other products not mentioned.

## Subpart 502D WEQ Factors

### 502.30 The wind erosion estimate, E

The wind erosion estimate, E, is the estimate of average annual tons of soil per acre that the wind will erode from an area represented by an unsheltered distance L and for the soil, climate, and site conditions represented by I, K, C, and V. The equation is an empirical formula. It was initially developed by relating wind tunnel data to observed field erosion for 3 years in the mid 1950's (Woodruff et al. 1976). The field data was normalized to reflect long-term average annual erosion assuming given conditions during the critical period without reference to change in those conditions through the year. The estimate arrived at by using the critical period procedure for estimating wind erosion does not track specific changes brought about by management and crop development; nor does it assume that critical period conditions exist all year. The calibration procedure accounted for minor changes expected to occur during a normal crop year at that time in history. The WEQ annual E is based on an annual C and field conditions during the critical wind erosion period of the year. This procedure does not account for all the effects of management.

The management period procedure for estimating wind erosion involves assigning factor values to represent field conditions expected to occur during specified time periods. Using annual wind energy distribution data, erosion can be estimated for each period of time being evaluated. The period estimates are summed to arrive at an annual estimate. Cropping sequences involving more than 1 year can be evaluated using this procedure. It also allows for a more thorough analysis of a management system and how management techniques affect the erosion estimate.

The new E tables can be downloaded from the WERU server, Manhattan, Kansas. These tables can be accessed in two ways:

- Through your WWW browser. To view, direct your web browser to: <http://www.weru.ksu.edu/nrcs>

Download the Adobe Acrobat Reader (if not already installed on your computer) by clicking on the icon and installing per the installation instructions. (Trade names mentioned are for specific information and do not constitute a guarantee or warranty of the product by the Department of Agriculture or an endorsement

by the Department over other products not mentioned.) When the Adobe Acrobat Reader is running on your browser you can click the PDF icon to view and print the table. When on the WERU Web page, copies of the files can be downloaded by clicking on the hypertext for the following:

etab.pdf for PDF or  
etab.wpd (for WordPerfect) or  
etab.ps for Postscript

- Through FTP—For those without a web browser but have FTP access, FTP to: **ftp.weru.ksu.edu** go to the appropriate directory, for example  
cd pub/nrcs/etables  
Be sure that you are in binary mode.

To download the table format of your choice, type:

**get etab.pdf** for PDF or  
**get etab.wpd** for WordPerfect or  
**get etab.ps** for Postscript

The appropriate E table will download to your computer. Exhibit 502-1 shows an example of an E table.

### 502.31 Soil erodibility index, I

I is the erodibility factor for the soil on the site. It is expressed as the average annual soil loss in tons per acre that would occur from wind erosion, when the site is:

- **Isolated** – incoming saltation is absent
- **Level** – knolls are absent
- **Smooth** – ridge roughness effects are absent and cloddiness is minimal
- **Unsheltered** – barriers are absent.
- At a location where the **C factor is 100**
- **Bare** – vegetative cover is absent
- **Wide** – the distance at which the flow of eroding soil reaches its maximum and does not increase with field size
- **Loose** – and non-crusts, aggregates not bound together, and surface not sealed.

The I factor is related to the percentage of nonerodible surface soil aggregates larger than 0.84 millimeters in diameter. For most NRCS uses, the I value is assigned for named soils based on wind erodibility groups (WEG). The WEG is included in the soil survey data base in NASIS. If the soil name is not known, exhibit 502-2 can be used to determine the WEG from the surface soil texture.



To determine erodibility for field conditions during various management periods throughout the year, follow the sieving instructions in exhibit 502-3. (Do not use this procedure to determine average annual **I** values.)

A soil erodibility index based solely on the percentage of aggregates larger than 0.84 millimeters has several potential sources of error. Some of these follow:

- Relative erodibility of widely different soils may change with a change in wind velocity over the surface of the soil.
- Calibration of the equation is based on the volume of soil removed, but the erodibility index is based on weight.
- Differences in size of aggregates have considerable influence on erodibility but no distinction for this influence is made in table 1, exhibit 502-3.
- Stability of surface aggregates influences erodibility; large durable aggregates can become a *surface armor*; less stable aggregates can be abraded into smaller, more erodible particles.
- Surface crusting may greatly reduce erodibility; erodibility may increase again as the crust deteriorates (Chepil 1958).

**Knoll erodibility**—Knolls are topographic features characterized by short, abrupt windward slopes. Wind erosion potential is greater on knoll slopes than on level or gently rolling terrain because wind flowlines are compressed and wind velocity increases near the crest of the knolls. Erosion that begins on knolls often affects field areas downwind.

Adjustments of the Soil Erodibility Index (**I**) are used where windward-facing slopes are less than 500 feet long and the increase in slope gradient from the adjacent landscape is 3

**Table 502-1** Knoll erodibility adjustment factor for **I**

Percent slope change in prevailing wind erosion direction	A Knoll adjustment of <b>I</b>	B Increase at crest area where erosion is most severe
3	1.3	1.5
4	1.6	1.9
5	1.9	2.5
6	2.3	3.2
8	3.0	4.8
10 and greater	3.6	6.8

percent or greater. Both slope length and slope gradient change are determined along the direction of the prevailing erosive wind (fig. 502-2).

Table 502-1 contains knoll erodibility adjustment factors for the Soil Erodibility Index **I**. The **I** value for the Wind Erodibility Group is multiplied by the factor shown in column A. This adjustment expresses the average increase in erodibility along the knoll slope. For comparison, column B shows the increased erodibility near the crest (about the upper 1/3 of the slope), where the effect is most severe.

No adjustment of **I** for knoll erodibility is made on level fields, or on rolling terrain where slopes are longer and slope changes are less abrupt. Where these situations occur, the wind flow pattern tends to conform to the surface and does not exhibit the flow constriction typical of knolls.

**Surface crusting**—Erodibility of surface soil varies with changing tillage practices and environmental conditions (Chepil 1958). A surface crust forms when a bare soil is wetted and dried. Although the crust may be so weak that it has virtually no influence on the size distribution of dry aggregates determined by sieving, it can make the soil less erodible. The resistance of the crust to erosion depends on the nature of the soil, intensity of rainfall, and the kind and amount of cover on the soil surface. A fully crusted soil may erode only one-sixth as much as non-crusting soil. However, a smooth crusted soil with loose sand grains on the surface is more erodible than the same field with a cloddy or ridged surface.

**Table 502-2** **I** adjustment guidelines for crusts

WEG	<b>I</b>	Max. adj. mgt prd. factor 1/	Calculated <b>I</b>	Rounded <b>I</b>
1	310	.7	217	220
1	250	.7	175	180
1	220	.7	154	160
1	180	.7	126	134
1	160	.7	112	134
2	134	.7	67	86
3	86	.4	34	38
4	86	.4	34	38
4L	86	.4	34	38
5	56	.3	17	21
6	48	.3	14	21
7	38	.3	11	12

1/ The management period adjustment to **I** has not been validated by research and is based on NRCS judgment.

Under erosive conditions, the surface crust and surface clods on fine sands and loamy fine sands tend to break down readily. On silt loams and silty clay loams the surface crust and surface clods may be preserved, and the relative erosion may be as little as one-sixth of **I**. Other soils react somewhere between these two extremes (Chepil 1959).

Because of the temporary nature of crusts, no adjustment for crusting is made for annual estimates based on the critical wind erosion period method (Woodruff and Siddoway 1973). However, crust characteristics may be estimated and adjustment to **I** may be made for management period estimates when no traffic, tillage, or other breaking of crusts is anticipated. Such adjustments may be up to, but may not exceed the percentages shown in table 502-2.

**Irrigation adjustments**—The **I** values for irrigated soils, as shown in exhibit 502-2, are applicable throughout the year. **I** adjustments for irrigation are applicable only where assigned **I** values are 180 or less.

**Adjustments based on dry sieving**—Temporal changes in the surface fraction  $> 0.84$  millimeter may be measured by dry sieving. These measurements may be used to establish a basis for adjusting **I** for conservation planning when sieving has been performed for each management period and for 3 years or more. The adjustment to **I** applies only to the respective time periods when the soil surface is influenced by changes in the nonerodible fraction. Therefore, the adjustment is used only with the management period procedure of estimating wind erosion. The procedure does expand the applicability of the equation to a management effect not previously addressed. When the **I** factor is adjusted based on the results of sieving, no additional adjustment to **I** will be made for irrigated fields. Adjustments to **I**,

based on sieving, should not be used without adequate supporting data. These adjustments reflect specific soil and management conditions and are only applicable in the area(s) from which samples were obtained and in areas that have similar soil and management conditions.

Use of adjusted soil erodibility **I** factor, arrived at by using standard rotary sieving procedures, is warranted provided it represents soil surface conditions during the appropriate management period. Adjustments may be made up to, but should not exceed, limits assigned for crusting in table 502-2.


The **I** factor adjustment may be used where applicable in determining whether an adequate conservation system is being followed. However, **I** factor adjustments are not to be used in the erodibility index ( $CI/T$ ) when determining highly erodible land because this index is the potential erodibility and not an estimate of actual erosion.

Current instructions for the National Resources Inventory (NRI) are to be followed. These instructions do not allow for any adjustment of the **I** factor. This ensures uniformity between States and allows for trend analysis.

Studies to adjust **I** should be made systematically and include all related soil in a given area. Multiple-year soil sieving data is required before adjustments are to be considered.

The National Soil Survey Center must review and concur in any proposal to adjust **I** and arrange for laboratory assistance. Adjustments to **I** must also be approved by the National Soil Survey Center and correlated across state and regional boundaries before implementation. Any adjustment to **I** must be within the framework of the existing **E** tables.

**Figure 502-2** Graphic of knoll erodibility



**Surface stability**—A significant limitation of the **I** factor is that it does not account for changes in the soil surface over time that are caused by the dynamics of wind erosion. The erodibility of a bare soil surface is based on the interaction of the following:

- Soils that have both erodible and nonerodible particles on the surface tend to stabilize if there is no incoming saltation. As the wind direction changes, the surface is disturbed, or the wind velocity increases, erosion may begin again.
- Saltation destroys crusts, clods, and ridges by abrasion.


- Fields tend to become more erodible as finer soil particles, which provide bonding for aggregation, are carried off in suspension.
- If the surface soil contains a high percentage of gravel or other nonerodible particles that are resistant to abrasion, the surface will become increasingly armored as the erodible particles are carried away. Desert pavement is the classic example of surface armoring. A surface with only nonerodible aggregates exposed to the wind will not erode further except as the aggregates are abraded.
- A surface may be virtually nonerodible and yet allow saltation and creep to cross unabated. A paved highway is an example. Other surfaces may be relatively stable and trap some, or all, of the incoming soil flow. Examples of this type of stability usually relate to some roughness, sheltering, or vegetative cover. A ridged field may trap a significant portion of the incoming soil flow until the furrows are filled and the surface loses its trapping capability. A vegetated barrier will provide a sheltered area downwind until the barrier is filled with sediment.

### 502.32 Soil roughness factor $K_r$ , ridge and random roughness


$K_{rd}$  is a measure of the effect of ridges made by tillage and planting implements. Ridges absorb and deflect wind energy and trap moving soil particles (fig. 502-3).

The  $K_r$  value is based on a standard ridge height to ridge spacing ratio of 1:4. Because of the difficulty of determining surface roughness by measuring surface obstructions, a standard roughness calibration using nonerodible gravel ridges in a wind tunnel was developed. This calibration led to the development of curves (fig. 502-4 and exhibit 502-

**Figure 502-3** Detachment, transport, and deposition on ridges and furrows



**Figure 502-4** Chart to determine soil ridge roughness factor,  $K_{rd}$ , from ridge roughness,  $K_r$ , (inches). Only this chart, representing an angle of deviation of  $0^\circ$ , will be used for the WEQ **critical period procedure**. When using the **management period procedure**, see exhibit 502-4 for graphs representing additional angles of deviation. Note: This graph represents erosive wind energy 60% parallel and 40% perpendicular to the prevailing erosive wind. —Hagen 1996



$$K_r = \frac{4(h \times h)}{s}$$

where:

$h$  = ridge height in inches

$s$  = ridge spacing in inches



4) that relate ridge roughness,  $K_r$ , to a soil ridge roughness factor,  $K_{rd}$ , (Skidmore 1965; Skidmore and Woodruff 1968; Woodruff and Siddoway 1965; and Hagen 1996).

The  $K_r$  curves are the basis for charts and tables used to determine  $K_{rd}$  factor values in the field (exhibits 502–4 and 502–5). The effect of ridges varies as the wind direction and erodibility of the soil change. To take into account the change in wind directions across a field, we consider the angle of deviation. The angle of deviation is the angle between the prevailing wind erosion direction and a line perpendicular to the row direction. The angle of deviation is 0 (zero) degrees when the wind is perpendicular to the row and is 90 degrees when the wind is parallel to the row. Following is an example of how the angle of deviation affects  $K_{rd}$  values: when evaluating a soil with an assigned  $I$  value of <134, and the prevailing erosive wind direction is perpendicular to ridges 4 inches high and 30 inches apart, then  $K_{rd}$  is 0.5. But when the prevailing erosive wind direction is parallel to those ridges, the  $K_{rd}$  value is 0.7. Random roughness, particularly in the furrows, significantly reduces wind erosion occurring from erosive winds blowing parallel to the ridges.

In 1996, ARS scientists provided a method for adjusting the WEQ  $K_{rd}$  factor with consideration for preponderance (erosive wind energy 60% parallel and 40% perpendicular to prevailing erosive wind direction) when using the Management Period Procedure. The use of preponderance recognizes that during the periods when the prevailing erosive winds are parallel to ridges, there are other erosive winds during the same period which are not parallel, thus making ridges effective during part of each period. Preponderance keeps the  $K$  factor value less than 1.0, when the  $I$  factor values are 134 or less. When estimating wind erosion rates by management periods, without the aid of a computer model, the prevailing wind erosion direction and a *default* preponderance are used for each period. This procedure more adequately addresses the effects of the ridges in wind erosion control since erosive wind directions may vary within each management period.

**Note:** When using the WEQ Excel spreadsheet model, the actual preponderance, up to and including a value of 4, for the period will be used, rather than a default value.

The WEQ  $K_{rr}$  factor accounts for random roughness. Random roughness is the nonoriented surface roughness that is sometimes referred to as cloddiness. Random roughness is usually created by the action of tillage implements.

It is described as the standard deviation (in inches) of the soil surface elevations, measured at regular intervals from a fixed, arbitrary plane above a tilled soil surface, after oriented (ridge) roughness has been accounted for. Random roughness can reduce erosion significantly. Note: The random roughness factor will only be used with the WEQ management period procedure.

Random roughness values have been developed for various levels of WEQ  $I$  factor values and surface random roughness (exhibit 502–6). Random roughness curves only adjust the  $K$  factors of a soil that has an  $I$  factor value of 134 and less.

The random roughness values used in the WEQ are the same random roughness values used in RUSLE. Random roughness (inches) from the machine operations data base in RUSLE can be used to determine WEQ random roughness values (table 502–7). However, keep in mind that these RUSLE random roughness values were determined for medium textured soils tilled at optimum moisture conditions for creating random roughness. Under most circumstances random roughness is determined by comparing a field surface to the random roughness (standard deviation) photos in the RUSLE handbook (Agriculture Handbook 703, appendix C).

The photos in Agriculture Handbook 703, appendix C, may be downloaded from:

<http://www.nrcs.usda.gov/technical/ECS/agronomy/roughness.html>

State agronomists should download, reproduce, and distribute the photographs to field offices.

When both random roughness and ridge roughness are present in the field, they are complimentary. When both are present, the  $K_{rd}$  factor for ridges and  $K_{rr}$  factor for random roughness will be multiplied together to obtain the total roughness  $K$ -factor.

Example problem: Take into consideration just one WEQ management period. The soil in the field being evaluated has an  $I$  value of 86. The field has just been fertilized with anhydrous ammonia using a knife applicator. Considering the height and spacing of the oriented roughness, the ridge roughness  $K_{rd}$  factor was determined to be 0.8. Using table 502–7, under random roughness (inches), the anhydrous applicator has a core value of 0.6. Going into the random roughness (inches) graph (exhibit 502–6), on the hori-

zontal axis to 0.6, and then vertically to the line representing an **I** factor of 86, the  $K_{rr}$  factor is rounded to 0.8. The total roughness value (**K** factor) is  $0.8 \times 0.8 = 0.64$ , then rounded to 0.6.

The major effects of random roughness on wind erosion are to raise the threshold wind speed at which erosion begins and to provide some sheltered area among the clods where moving soil can be trapped. Hence, when the effectiveness of random roughness increases the total **K**-value decreases.

Random roughness, particularly in the furrows, significantly reduces wind erosion occurring from erosive winds blowing parallel to the ridges.

Random roughness is subject to much faster degradation by rain or wind erosion than large tillage ridges. Therefore the WEQ management period, where random roughness is effective, may be of short duration.

For fields being broken out of sod, such as CRP, random roughness will be credited for erosion control. The field surface is usually covered with the crowns of plants, their associated roots, and adhering soil. The total random roughness of the field should be compared to the photos in the RUSLE handbook and credited appropriately.

**Surface roughening (emergency tillage)**—In some situations, there is a need to control erosion on bare fields where the surface crust has been destroyed or where loose grains are on the surface and can abrade an existing crust. One method to reduce the erosion hazard on such fields is emergency or planned tillage to roughen the surface or increase nonerodible clods on the surface (random roughness). This may be accomplished by one or more of the following:

- Soil that characteristically forms a crust with loose sand grains on the surface may be worked to create clods. The loose grains fall into the crevices between clods. This is the principle of sand fighting used in some emergency tillage.
- The soil may be deep tilled to bring up finer textured soil material that will form more persistent clods.
- Irrigation increases the nonerodible fraction of a soil (exhibit 502–2).
- The surface may be worked into a ridge-furrow configuration that will trap loose, moving soil.
- The soil may be tilled in strips or in widely spaced rows to provide some degree of ridge and random roughness to break the flow of saltation and creep.

### 502.33 Climatic factor, **C**

The **C** factor is an index of climatic erosivity, specifically windspeed and surface soil moisture. The factor for any given location is based on long-term climatic data and is expressed as a percentage of the **C** factor for Garden City, Kansas, which has been assigned a value of 100 (Lyles 1983). In an area with a **C** factor of 50, for example, the **IKC** value would be only half of the **IKC** for Garden City, Kansas.

The climatic factor equation is expressed as:

$$C = 34.48 \times \frac{V^3}{(PE)^2}$$

where:

- C** = annual climatic factor
- V** = average annual wind velocity
- PE** = precipitation-effectiveness index of Thornthwaite
- 34.48 = constant used to adjust local values to a common base (Garden City, Kansas)

The basis for the windspeed term of the climatic factor is that the rate of soil movement is proportional to windspeed cubed. Several researchers have reported that when windspeed exceeds threshold velocity, the soil movement is directly proportional to friction velocity cubed which, in turn, is related to mean windspeed cubed (Skidmore 1976).

The basis for the soil moisture term of the climatic factor is that the rate of soil movement varies inversely with the equivalent surface soil moisture. Effective surface soil moisture is assumed to be proportional to the Thornthwaite precipitation-effective-ness index (**PE**) (Thornthwaite 1931). The annual **PE** index is the sum of the 12 monthly precipitation effectiveness indices. The formula is expressed as follows:

$$PE = \sum^{12} 115 \times \left[ \frac{P}{(T-10)} \right]^{\frac{10}{9}}$$

where:

- PE** = the annual precipitation effectiveness index
- P** = average monthly precipitation
- T** = average monthly temperature

The **C** factor isoline map developed by NRCS in 1987 can accessed at:

<http://data4.ftw.nrcs.usda.gov/website/c-values>

Complete instructions for viewing the map are given in exhibit 502-8. The map displays C factors for all areas of the conterminous United States and Alaska. The isolines were drafted to conform with local C factors calculated from 1951–80 weather data and were correlated across state and regional boundaries. Procedures for developing local C factors are explained in exhibit 502–9.

1. Interpolation of WEQ climatic factors (C)— States may interpolate between county assigned C values to the nearest 5 units based on the National C Factor Isoline Map or the state C Factor Isoline Map in the Field Office Technical Guide (FOTG). When interpolating between values, knowledge of the local climatic and topographic conditions is extremely useful since climatic conditions can vary disproportionately between C factor value isolines.
2. Where WEQ soil loss (E) tables have been developed with C factor increments greater than 5 units, a straight line interpolation to the nearest C factor value of 5 may be made from existing E tables. Straight line interpolations can also be made from the soil losses (E) calculated with approved WEQ computer software, when C factors programmed into the model are in increments greater than 5 units.
3. C factor interpolations are for the purpose of conservation planning only and are NOT to be used in determining or adjusting previous highly erodible land (HEL) designations. However, they may be used during status reviews to determine if an individual is actively applying a conservation system. Previous national policy, regarding the changing of prior HEL designations, remains in effect.

**Effects of irrigation water on the C factor**—When irrigation water is applied to a dry soil surface, a reduction in wind erosion can be expected. A specific procedure to directly adjust the climatic factor C for irrigation is not available. However, a procedure has been developed by researchers to adjust the Erosive Wind Energy (EWE) by the fraction of time during which the soil is considered wet and nonerodible because of irrigation. See 502.31 and exhibit 502–2.

The procedures that follow adjust the Erosive Wind Energy (EWE) value which planners are to use when estimating wind erosion on irrigated fields. This adjustment is for the WEQ Management Period Procedure. States where wind

erosion is a concern should replace previous methods used to adjust for the effects of irrigation and utilize this procedure and the procedure for adjusting the **I** factor, for all plan revisions or new planning activities. This new procedure, however, does not impact designated highly erodible lands (HEL) or new determinations since management practices are not considered in the HEL formula.

Note: Irrigation adjustments to EWE and to the **I** factor, apply to fully irrigated fields and to fields that receive *supplemental* irrigation water.

- Research scientists have developed an Irrigation Factor (IF) that adjusts the EWE or period erosion loss to account for the effect of irrigation wetting the soil surface and making it less erodible. The IF takes into account the number of days in a management period, number of irrigation events during a management period, and a Texture Wetness Factor (TWF).
- To account for the *nonerodible wet* condition of various soil textures after irrigation, a TWF of 1, 2, or 3 is assigned to coarse, medium, and fine textured soil, respectively. See exhibit 502.2 for values assigned to the various soil groups.
- The IF is calculated with the following equation:  

$$\text{IF} = \frac{\text{number of days in period} - \text{nonerodible wet days in period (NEWD)}}{\text{number of days in period}}$$
 Nonerodible Wet Days (NEWD) are equal to the Texture Wetness Factor (TWF) times the number of irrigation events in the period.
- When using the WEQ to account for the effects of irrigation, multiply the EWE for the period by the IF.
- Example: A fine textured soil was irrigated three times during 45 days. Twelve percent of the annual EWE occurs during this period. Therefore:  

$$\text{TWF} = 3 \text{ for fine textured soil}$$

$$\text{Number of irrigations during the period} = 3$$

$$\text{NEWD} = (3)(3) = 9$$

$$\text{IF} = (45 \text{ days} - 9)/45 = 0.80$$

The adjusted EWE for 45 days is then determined by multiplying IF times the percentage of annual erosion wind energy during the period being evaluated.

$$\text{Adjusted EWE} = (.80)(12\%) = 9.6 \%$$

Note: The EWE shall not be adjusted for any management period where irrigation does not occur.

- The WEQ factors (C & I) used to determine the Erodibility Index (EI), will not be adjusted when determining highly erodible land (HEL) on cropland that is irrigated.

### 502.34 Unsheltered distance, L


The L factor represents the unsheltered distance along the prevailing wind erosion direction for the field or area to be evaluated. Its place in the equation is to relate the *isolated, unsheltered, and wide* field condition of **I** to the size and shape of the field for which the erosion estimate is being prepared. Because V is considered after L in the 5-step solution of the equation (502.22), the unsheltered distance is always considered as if the field were bare except for vegetative barriers.

1. L begins at a point upwind where no saltation or surface creep occurs and ends at the downwind edge of the area being evaluated (figure 502-5). The point may be at a field border or stable area where vegetation is sufficient to eliminate the erosion process. An area should be considered stable only if it is able to trap or hold virtually all expected saltation and surface creep from upwind. If vegetative barriers, grassed waterways, or other stable areas divide an agricultural field being evaluated, each subdivision will be *isolated* and shall be evaluated as a separate


*field*. Refer to the appropriate NRCS Conservation Practice Standards to determine when practices are of adequate width, height, spacing, and density to create a stable area.

2. When erosion estimates are being calculated for cropland or other relatively unstable conditions, upwind pasture or rangeland should be considered a stable border. However, if the estimate is being made for a pasture or range area, L should be determined by measuring from the nearest stable point upwind of the area or field in question (figure 502-6). The only case where L is equal to zero is where the area is fully sheltered by a barrier.
3. When a barrier is present on the upwind side of a field, measure L across the field along the prevailing wind erosion direction and subtract the distance sheltered by the barrier. Use 10 times the barrier height for the sheltered distance (figure 502-7).


**Figure 502-5** Unsheltered distance L



**Figure 502-6** Unsheltered distance L, perennial vegetation (pasture or range)



**Figure 502-7** Unsheltered distance L – windbreak or barrier



4. When a properly designed wind stripcropping system is applied, alternate strips are protected during critical wind erosion periods by a growing crop or by crop residue. These strips are considered stable. L is measured across each erosion-susceptible strip, along the prevailing wind erosion direction (figure 502–8).

The prevailing wind erosion direction is the direction from which the greatest amount of erosion occurs during the critical wind erosion period. The direction is usually expressed as one of the 16 compass points. When predicting erosion by management periods, the prevailing wind erosion direction may be different for each period (exhibit 502–7a).

Preponderance is a ratio between wind erosion forces parallel and perpendicular to the prevailing wind erosion direction. Wind forces parallel to the prevailing wind erosion direction include those coming from the exact opposite direction (180°). A preponderance of 1.0 indicates that as much wind erosion force is exerted perpendicular to the prevailing direction as along that direction. A higher preponderance indicates that more of the force is along the prevailing wind erosion direction. Wind patterns are complex; low preponderance indicates high complexity and as a result, less wind will be from the prevailing erosive wind direction than locations that have a high preponderance.

L can be measured directly on a map or calculated using a wind erosion direction factor:

- For uses of the Wind Erosion Equation involving a single annual calculation, L should be the measured distance across the area in the prevailing wind erosion direction from the stable upwind edge of the field to the downwind edge of the field. When the prevailing

wind erosion direction is at an angle that is not perpendicular to the long side of the field, L can be determined by multiplying the width of the field by the appropriate conversion factor obtained from table 502-3.

- For management period calculations, wind erosion direction factors based on preponderance are to be used instead of a measured distance to determine L except
  - Where irregular fields cannot be adequately represented by a circle, square, or rectangle.
  - Where preponderance data are not available.

Steps to determine L for management period estimates:

1. Obtain local values for prevailing the wind erosion direction and preponderance (exhibit 502–7a).
2. Measure actual length and width of the field and determine the ratio of length to width.
3. Determine angle of deviation between prevailing wind erosion direction and an imaginary line perpendicular to the long side of the field.


Using data from steps 1 through 3, determine the wind erosion direction factor from wind erosion direction factor tables, tables 502–81a-e. These are adjustment factors that account for prevailing wind erosion direction, preponderance of wind erosion forces, and size and shape of the field.

Multiply the width of the field by the wind erosion direction factor. This is the L for the field.

If a barrier is on the upwind side of the field, reduce L by a distance equal to 10 times the height of the barrier.

For circular fields,  $L = 0.915$  times the diameter, regardless of the prevailing wind erosion direction or preponderance.

**Figure 502–8** Unsheltered distance L, stripcropping system



**Table 502-3** Wind erosion direction factors<sup>1/</sup>

Angle of deviation <sup>2/</sup>	Adjustment factor
0	1.00
22.5°	1.08
45°	1.41
67.5°	2.61
90°	L = Length of field

1/ These adjustment factors are applicable when preponderance is not considered. L cannot exceed the longest possible measured distance across the field.

2/ Angle of deviation of the prevailing erosive wind from a direction perpendicular to the long side of the field.

---

### 502.35 Vegetative cover factor, V

The effect of vegetative cover in the Wind Erosion Equation is expressed by relating the kind, amount, and orientation of vegetative material to its equivalent in pounds per acre of small grain residue in reference condition Small Grain Equivalent (SGe). This condition is defined as 10 inch long stalks of small grain, parallel to the wind, lying flat in rows spaced 10 inches apart, perpendicular to the wind. Several crops have been tested in the wind tunnel to determine their SGe. For other crops, small grain equivalency has been computed using various regression techniques (Armbrust and Lyles 1985; Lyles and Allison 1980; Lyles 1981; Woodruff et al. 1974; Woodruff and Siddoway 1965). NRCS personnel have estimated SGe curves for other crops. SGe curves are in exhibit 502–10.

Position and anchoring of residue is important. In general, the finer and more upright the residue, the more effective it is for reducing wind erosion. Knowledge of these and other relationships can be used with benchmark values to estimate additional SGe values.

Research is underway to develop a method of estimating the relative erosion control value of short woody plants and other growing crops.

Several methods are used to estimate the kind, amount, and orientation of vegetation in the field. Often the task is to predict what will be in the field in some future season or seasons. Amounts of vegetation may be predicted from pro-

duction records or estimates and these amounts are then reduced by the expected or planned tillage. It may be desirable to sample and measure existing residue to determine quantity of residue. Local data should be developed to estimate surface residue per unit of crop yield and crop residue losses caused by tillage.

The crown of a plant, its associated roots, and adhering soil should also be credited when doing transects to determine residue cover. Employees will need to use their best judgment when deciding which crop curve to use when converting from percent ground cover to mass and then selecting a curve to convert the residue mass to SGe.

If you encounter a crop, residue, or a type of vegetation for which an SGe curve has not been developed, exhibits 502–11 and 502–12 give procedures to develop an interim SGe curve. Any SGe curve developed in this way must be submitted to the National Agronomists or the Cooperating Scientist for wind erosion for approval.



## Subpart 502E Principles of wind erosion control

### 502.40 General

Five principles of wind erosion control have been identified (Lyles and Swanson 1976; Woodruff et al. 1972; and Woodruff and Siddoway 1965). These are as follows:

- Establish and maintain adequate vegetation or other land cover.
- Reduce unsheltered distance along wind erosion direction.
- Produce and maintain stable clods or aggregates on the land surface.
- Roughen the land with ridge and/or random roughness.
- Reshape the land to reduce erosion on knolls where converging windflow causes increased velocity and shear stress.

The *cardinal rule* of wind erosion control is to strive to keep the land covered with vegetation or crop residue at all times (Chepil 1956). This leads to several principles that should be paramount as alternative controls are considered:

- Return all land unsuited to cultivation to permanent cover.
- Maintain maximum possible cover on the surface during wind erosion periods.
- Maintain stable field borders or boundaries at all times.

### 502.41 Relation of control to WEQ factors

The Wind Erosion Equation (WEQ) was developed to relate specific field conditions to estimated annual soil loss. Of the five factors, two (**I** and **C**) are often considered to be *fixed* while the other three (**K**, **L**, and **V**) are generally considered *variable* or management factors. This is not precisely true.

The **I** factor is related to the percentage of dry surface soil fractions greater than 0.84 millimeters. Its derivation is usually based on the Wind Erodibility Group.

However, if a special management condition is going to be maintained, such as crusts or irrigation, a modification of **I** is appropriate. Also, **I** is increased by a knoll erodibility factor where appropriate. See 502.31. This adjustment is not appropriate if the knoll condition is modified through landforming or use of barriers to protect the knoll.

Knoll erodibility adjustments to **I** relate to wind direction; low preponderance indicates that knoll erodibility will vary widely as wind direction changes.

Total **K** reflects the tilled ridge roughness and random roughness in a field. This is a management factor. Stability of tilled roughness is related, however, to soil erodibility, climate, and the other erosion factors.

Ridge roughness relates to ridge spacing in the wind erosion direction. Even with optimum orientation of rows, some of the winds will be blowing parallel to the rows when preponderance is low.

Random roughness relates to the nonoriented surface roughness that is often referred to as cloddiness. Random roughness is described as the standard deviation of elevation from a plane across a tilled area after taking into account oriented (ridge) roughness.

The **C** factor is based on long-term weather records. Conservation treatment should be planned to address the critical climatic conditions when high seasonal erosive wind energy is coupled with highly erodible field conditions.

The unsheltered distance **L** is a management factor that can be changed by altering field arrangement, stripcropping, or establishing windbreaks or other barriers. **L** is a function of field layout as it relates to prevailing wind direction and preponderance of erosive winds in the prevailing direction.

When preponderance values are high (more than 2.5 and approaching 4.0), conservation treatment should be concentrated on addressing potential erosion from the prevailing wind erosion direction.

When preponderance values are low (approaching 1.0), knowledge of local seasonal wind patterns becomes more important in planning treatment. Conservation treatment should be planned to allow for the effect of seasonal changes in the prevailing wind erosion direction.

A stable strip across an agricultural field divides the area into separate fields. Examples of stable areas include grass waterways, hedges and their sheltered area, brushy draws or ravines, roadways with grass borders, grass strips, and drainage or irrigation ditches.

To be considered stable, an area must be able to stop and hold virtually all of the expected saltation and surface creep. Be aware that an area may be stable during one crop stage, but not stable in other seasons.

V is the equivalent vegetative cover maintained on the soil surface. It is directly related to the management functions of crop establishment, tillage, harvesting, grazing, mowing, or burning.

## 502.42 Tolerances in wind erosion control

In both planning and inventory activities, NRCS compares estimated erosion to soil loss tolerance (T). T is expressed as the average annual soil erosion rate (tons/acre/year) that can occur in a field with little or no long-term degradation of the soil resource, thus permitting crop productivity to be sustained for an indefinite period.

Soil loss tolerances for a named soil are recorded in the soil survey data base in NASIS.

The normal planning objective is to reduce soil loss by wind or water to T or lower. In situations where treatment for both wind and water erosion is needed, soil loss estimates using the WEQ and USLE or RUSLE are not added together to compare to T.

Additional impacts of wind erosion that should be considered are potential offsite damages, such as air and water pollution and the deposition of soil particles.

Crop tolerance to soil blowing may also be an important consideration in wind erosion control. Wind or blowing soil, or both, can have an adverse effect on growing crops. Most crops are more susceptible to abrasion or other wind damage at certain growth stages than at others. Damage can result from desiccation and twisting of plants by the wind.

Crop tolerance can be defined as the maximum wind erosion that a growing crop can tolerate, from crop emergence to field stabilization, without an economic loss to crop stand, crop yield, or crop quality.

### (a) Blowing soil effects on crops

Some of the adverse effects of soil erosion and blowing soil on crops include:

- Excessive wind erosion that removes planted seeds, tubers, or seedlings.
- Exposure of plant root systems.
- Sand blasting and plant abrasion resulting in
  - crop injury
  - crop mortality
  - lower crop yields
  - lower crop quality
  - wind damage to seedlings, vegetables, and orchard crops.
- Burial of plants by drifting soil.

### (b) Crop tolerance to blowing soil or wind

Many common crops have been categorized based on their tolerance to blowing soil. These categories of some typical crops are listed in table 502-4. Crops may tolerate greater amounts of blowing soil than shown in table 502-4, but yield and quality will be adversely affected.

### (c) The effects of wind erosion on water quality

Some of the adverse effects of wind erosion on water quality include:

- Deposition of phosphorus (P) into surface water
- Increased Biochemical Oxygen Demand (BOD) in surface water
- Reduced stream conveyance capacity because of deposited sediment in streams and drainage canals

Local water quality guidelines under Total Maximum Daily Loads (TDML) for nutrients may require that wind erosion losses be less than the soil loss tolerance (T) in order to achieve local phosphorus (P) or other pollutant reduction goals.

For a phosphorus (P) intrapment estimation procedure, see the Core 4 manual, chapter 3C, Cross Wind Trap Strips.



## Subpart 502F Example problems

(Each state should develop example problems, common to their state, and insert in this section.) See exhibit 502–7b.

**Table 502-4** Crop tolerance to blowing soil

Tolerant T	Moderate tolerance 2 ton/ac	Low tolerance 1 ton/ac	Very low tolerance 0 to 0.5 ton/ac
Barley	Alfalfa (mature)	Broccoli	Alfalfa seedlings
Buckwheat	Corn	Cabbage	Asparagus
Flax	Onions (>30 days)	Cotton	Cantaloupe
Grain Sorghum	Orchard crops	Cucumbers	Carrots
Millet	Soybeans	Garlic	Celery
Oats	Sunflowers	Green/snap beans	Eggplant
Rye	Sweet corn	Lima beans	Flowers
Wheat		Peanuts	Kiwi fruit
		Peas	Lettuce
		Potatoes	Muskmelons
		Sweet potatoes	Onion seedlings (<30 days)
		Tobacco	Peppers
			Spinach
			Squash
			Strawberries
			Sugar beets
			Table beets
			Tomatoes
			Watermelons



# Exhibit 502-1

# Example E table

“E” tables for each combination of C & I factors are on the www browser: <http://www.weru.ksu.edu/nrcs>.  
Click on the hypertext for: **etable.doc** (for MS Word) and **etable.wpd** (for Word Perfect).

(E)* SOIL LOSS FROM WIND EROSION IN TONS PER ACRE PER YEAR											JANUARY, 1998		
C= 100	SURFACE - K=1.00										I =	86	
(L)	(V)** - FLAT SMALL GRAIN RESIDUE IN POUNDS PER ACRE												
UNSHelterED													
DISTANCE	0	250	500	750	1000	1250	1500	1750	2000	2250	2500	2750	3000
IN FEET													
10000	86.0	75.3	60.7	46.4	28.4	16.8	8.8	4.6	2.5	1.1	0.3		
8000	86.0	75.3	60.7	46.4	28.4	16.8	8.8	4.6	2.5	1.1	0.3		
6000	86.0	75.3	60.7	46.4	28.4	16.8	8.8	4.6	2.5	1.1	0.3		
4000	86.0	75.3	60.7	46.4	28.4	16.8	8.8	4.6	2.5	1.1	0.3		
3000	85.6	74.9	60.4	46.1	28.2	16.6	8.7	4.6	2.5	1.1	0.3		
2000	82.7	72.3	58.1	44.2	26.9	15.7	8.1	4.2	2.3	1.0	0.3		
1000	76.4	66.5	53.1	40.0	24.0	13.7	6.9	3.5	1.9	0.7			
800	74.2	64.6	51.5	38.6	23.0	13.0	6.6	3.3	1.8	0.7			
600	69.3	60.1	47.7	35.4	20.9	11.6	5.7	2.8	1.5	0.5			
400	62.2	53.7	42.2	31.0	17.9	9.6	4.6	2.2	1.1				
300	57.6	49.6	38.7	28.1	16.0	8.4	4.0	1.9	0.9				
200	51.4	44.1	34.1	24.4	13.6	6.9	3.2	1.4	0.7				
150	45.6	38.9	29.8	21.0	11.4	5.6	2.5	1.1	0.3				
100	39.8	33.8	25.6	17.7	9.4	4.5	1.9	0.8	0.3				
80	36.6	31.0	23.3	16.0	8.4	3.9	1.6	0.5					
60	31.4	26.4	19.6	13.2	6.7	3.0	1.2	0.4					
50	27.9	23.4	17.2	11.4	5.7	2.4	0.9						
40	24.4	20.4	14.8	9.7	4.7	1.9	0.7						
30	21.0	17.4	12.5	8.0	3.8	1.5	0.5						
20	15.9	13.0	9.1	5.6	2.5	0.9							
10	9.4	7.5	5.1	2.9	1.2	0.3							

(E)* SOIL LOSS FROM WIND EROSION IN TONS PER ACRE PER YEAR											JANUARY, 1998		
C= 100	SURFACE - K=0.90										I =	86	
(L)	(V)** - FLAT SMALL GRAIN RESIDUE IN POUNDS PER ACRE												
UNSHelterED													
DISTANCE	0	250	500	750	1000	1250	1500	1750	2000	2250	2500	2750	3000
IN FEET													
10000	77.4	67.5	54.0	40.7	24.4	14.0	7.1	3.6	2.0	0.7			
8000	77.4	67.5	54.0	40.7	24.4	14.0	7.1	3.6	2.0	0.7			
6000	77.4	67.5	54.0	40.7	24.4	14.0	7.1	3.6	2.0	0.7			
4000	76.8	66.9	53.5	40.3	24.2	13.8	7.0	3.6	1.9	0.7			
3000	75.8	66.0	52.7	39.6	23.7	13.5	6.8	3.5	1.9	0.7			
2000	73.4	63.9	50.8	38.1	22.6	12.8	6.4	3.2	1.7	0.6			
1000	67.2	58.2	46.0	34.1	19.9	11.0	5.4	2.6	1.4	0.5			
800	64.7	56.0	44.1	32.5	18.9	10.3	5.0	2.4	1.3				
600	59.7	51.5	40.3	29.4	16.8	8.9	4.3	2.0	1.0				
400	55.0	47.3	36.7	26.5	14.9	7.8	3.6	1.7	0.8				
300	51.0	43.7	33.8	24.2	13.4	6.8	3.1	1.4	0.7				
200	44.7	38.1	29.1	20.5	11.1	5.4	2.4	1.0	0.3				
150	39.1	33.2	25.1	17.4	9.2	4.3	1.8	0.8	0.2				
100	34.5	29.1	21.8	14.8	7.7	3.5	1.4	0.5					
80	31.2	26.3	19.5	13.1	6.7	2.9	1.2	0.4					
60	25.9	21.7	15.8	10.4	5.1	2.1	0.8						
50	23.1	19.2	13.9	9.0	4.3	1.8	0.7						
40	20.7	17.1	12.3	7.8	3.7	1.5	0.5						
30	17.2	14.1	10.0	6.2	2.8	1.1							
20	12.7	10.3	7.1	4.3	1.9	0.4							
10	6.2	4.9	3.2	1.7	0.6								

## Exhibit 502–2

# Wind erodibility groups and wind erodibility index

Soil texture <sup>1</sup>	EWE texture wetness factor <sup>2</sup>	Predominant soil texture class of surface layer	Wind Erodibility Group <sup>3</sup> (WEG) <sup>3</sup>	Soil Erodibility Index (I) <sup>4,5</sup> (ton/ac/yr)	Soil Erodibility Index (I) for irrigated soils (ton/ac/yr) <sup>4</sup>
C	1	Very fine sand, fine sand, sand, or coarse sand	1	310 <sup>4</sup>	310
				250	250
				220	220
				180	160
				160	134
C	1	Loamy very fine sand, loamy fine sand, loamy sand, loamy coarse sand, sapric organic soil materials, and all horizons that meet andic <sup>6</sup> soil properties as per Criteria 2 in Soil Taxonomy, regardless of the fine earth texture	2	134	104
C	1	Very fine sandy loam, fine sandy loam, sandy loam, coarse sandy loam, and noncalcareous silt loam with 35 to 50% very fine sand and <10% clay	3	86	56
F	3	Clay, silty clay, non-calcareous clay loam, or silty clay loam with more than 35% clay	4	86	56
M	2	Calcareous <sup>7</sup> loam and silt loam or calcareous clay loam and silty clay loam	4L	86	56
M	2	Non-calcareous loam and silt loam with more than 20% clay (but does not meet WEG 3 criteria), or sandy clay loam, sandy clay, and hemic organic soil materials	5	56	38
M	2	Non-calcareous loam and silt loam with more than 20% clay, or non-calcareous clay loam with less than 35% clay or silty clay loam with less than 35% clay	6	48	21
M	2	Silt and fibric organic soil material	7	38	21
—	—	Soils not susceptible to wind erosion because of surface rock and pararock fragments or wetness	8	—	—

1/ Soil texture, C = Coarse; M = Medium; F = Fine

2/ Texture wetness factor for adjustment of Erosive Wind Energy (EWE) for the period (Irrigated fields only).

3/ For all WEGs except sand and loamy sand textures, if percent rock and pararock fragments (>2mm) by volume is 15-35, reduce I value by one group with more favorable rating. If percent rock and pararock fragments by volume is 35-60, reduce I value by two favorable groups except for sands and loamy sand textures which are reduced by one group with more favorable rating. If percent rock and pararock fragments by volume is more than 60, use I value of zero for all textures except sands and loamy sand textures which are reduced by three groups with more favorable rating.

4/ The wind erodibility index is based on the relationship of dry soil aggregates greater than 0.84 millimeters to potential soil erosion. Value for irrigated soils is applicable throughout the year. Values for irrigated soils determined by Dr. E.L. Skidmore, USDA, ARS, Wind Erosion Research Unit, Manhattan, Kansas.

5/ The I factor for WEG 1 vary from 160 for coarse sands to 310 for very fine sands. Use an I value of 220 as an average figure.

6/ Vitrandic, Vitritorrandic, and Vitrxerandic Subgroups with ashy textural modifiers move one group with less favorable rating.

7/ Calcareous is a strongly or violently effervescent reaction of the fine-earth fraction to cold dilute (IN) HCL.

Soil sieving has become increasingly important because of USDA’s emphasis on advancing erosion prediction technology. Soil samples can be sieved using either a flat or a rotary sieve. The flat sieve method is useful in making onsite field determinations. However, the results are not as consistent as those achieved by the electric motor-driven rotary sieve. If the objective is to gather scientific data, consistency is important, and rotary sieving should be the chosen method.

(a) Equipment needs

- A standard number 20 flat sieve or access to a properly designed rotary sieve.
- A device for weighing samples.
- A square-nosed scoop or shovel.
- Worksheet for sieving of dry aggregates (example follows).

(b) Procedure

1. Take samples only when the soil is reasonably dry. If the soil sticks to the scoop, postpone the sampling until the soil dries sufficiently. If sieving is being done to verify the **I** factor assigned to a soil, samples should be taken during the normal wind erosion period in an area that is smooth, bare, not crusted, not sheltered by windbreaks or barriers, and at a location in the field far enough downwind for avalanching to occur. If the objective is to estimate erodibility for a specific field condition, select a smooth, bare, unsheltered area with the desired conditions. In all cases, avoid compacted or vegetated areas.
2. Use the square-nosed scoop to collect a sample from the soil surface. Try to avoid sampling more deeply than approximately 1 inch. Several small scoops may be more representative than one larger scoop of soil.
3. Gently place the sample (about 2 lb) into a padded container for transporting to a sieving location. Fill in the appropriate blanks on the form to specify field conditions and other data. If the soil sample will be done in the field with a flat sieve, proceed.
4. Weigh the sieve (including receiver) and record for later use. Place about 2 pounds of the sample on the No. 20 sieve. Remove loose vegetation without fracturing soil aggregates.
5. Determine gross weight of the sample and sieve. Subtract the weight of the sieve to determine net weight of the sample.
6. Remove the receiver and shake the sieve 50 times using moderate force. Do not bounce the sample or shake so hard that you break down the clods. Place the sieve over the receiver and shake again 50 times. If more than 0.5 ounce collects in the receiver, empty the receiver and repeat the process. If more than 0.5 ounce is again in the receiver, repeat the process again. Do not exceed a total of 200 shakes. Discard material in the receiver and weigh the sieve, receiver, and remaining aggregates in the sieve. Determine the weight of soil aggregates greater than 0.84 millimeter in diameter. Divide the weight of the sieved sample by the total weight of the soil sample to determine percentage of aggregates that exceed 0.84 millimeter.
7. Refer to table that follows to arrive at soil erodibility when using the percentage of nonerodible aggregates.

**Exhibit 502-3** Sieving instructions—continued

Soil erodibility Index I in tons/acre determined by percentage of nonerodible fractions

% units—>	0	1	2	3	4	5	6	7	8	9
Tens	ton/ac	ton/ac	ton/ac	ton/ac	ton/ac	ton/ac	ton/ac	ton/ac	ton/ac	ton/ac
0	—	310	250	220	195	180	170	160	150	140
10	134	131	128	125	121	117	113	109	106	102
20	98	95	92	90	88	86	83	81	79	76
30	74	72	71	69	67	65	63	62	60	58
40	56	54	52	51	50	48	47	45	43	41
50	38	36	33	31	29	27	25	24	23	22
60	21	20	19	18	17	16	16	15	14	13
70	12	11	10	8	7	6	4	3	3	2
80	2	—	—	—	—	—	—	—	—	—

**Exhibit 502-3** Sieving instructions—continued**ARS and NRCS Data Worksheet for Sieving of Dry Aggregates**

## Cooperative Soil Sieving Project

1. Field Office: \_\_\_\_\_ 2. Date: \_\_\_\_\_  
 3. County: \_\_\_\_\_ 4. Sampled by: \_\_\_\_\_  
 5. Sample site number: \_\_\_\_\_ 6. Soil Survey Sheet number: \_\_\_\_\_  
 7. Site location: \_\_\_\_\_  
 8. Symbol and map unit name: \_\_\_\_\_  
 9. Erosion: (yes/no) \_\_\_\_\_ 10. Tillage: \_\_\_\_\_  
 11. Ridge height (inches): \_\_\_\_\_  
 12. Ridge spacing: \_\_\_\_\_ 13. Crust thickness: \_\_\_\_\_  
 14. Date(s) and amount(s) of precipitation: \_\_\_\_\_  
 15. Total precipitation: \_\_\_\_\_  
 16. Kind of ground cover: \_\_\_\_\_  
 17. Status of ground cover: \_\_\_\_\_  
 19. Amount (lb): \_\_\_\_\_ 20. Percent ground cover: \_\_\_\_\_  
 21. Percent canopy: \_\_\_\_\_  
 22. Row pattern: \_\_\_\_\_ Row direction (Azimuth): \_\_\_\_\_  
 23. Is field irrigated: (yes/no) \_\_\_\_\_ 24. Type of irrigation: \_\_\_\_\_  
 25. Annual irrigation applied (inches): \_\_\_\_\_  
 26. Samplers comments:

To be completed by ARS

Sieving date: \_\_\_\_\_ Sieved by: \_\_\_\_\_


Soil weight, wet: \_\_\_\_\_; Soil weight, dry: \_\_\_\_\_; Percent moisture \_\_\_\_\_

Sieve size (mm)	<0.42	.42-.84	.84-2.83	2.83-6.4	6.4-12.7	>12.7	%>0.84
1st sieving (weight)							
Percent of total							
2nd sieving (weight)							
Percent of total							

Resulting I value: \_\_\_\_\_

Siever's comments





**Note:** Erosive wind energy is assumed to be 60% parallel and 40% perpendicular to prevailing erosive wind.


$$K_r = \frac{4(h \times h)}{s}$$

where:

h = ridge height in inches

s = ridge spacing in inches

**Exhibit 502-4** Ridge roughness factor,  $K_{rd}$ , graph—Continued




**Note:** Erosive wind energy is assumed to be 60% parallel and 40% perpendicular to prevailing erosive wind.

$$K_r = \frac{4(h \times h)}{s}$$

where:

- h = ridge height in inches
- s = ridge spacing in inches

**Exhibit 502-4** Ridge roughness factor,  $K_{rd}$ , graph—Continued



**Note:** Erosive wind energy is assumed to be 60% parallel and 40% perpendicular to prevailing erosive wind.


$$K_r = \frac{4(h \times h)}{s}$$

where:

h = ridge height in inches

s = ridge spacing in inches

**Exhibit 502-4** Ridge roughness factor,  $K_{rd}$ , graph—Continued



**Note:** Erosive wind energy is assumed to be 60% parallel and 40% perpendicular to prevailing erosive wind.


$$K_r = \frac{4(h \times h)}{s}$$

where:

h = ridge height in inches

s = ridge spacing in inches

**Exhibit 502-4** Ridge roughness factor,  $K_{rd}$ , graph—Continued



**Note:** Erosive wind energy is assumed to be 60% parallel and 40% perpendicular to prevailing erosive wind.

$$K_r = \frac{4(h \times h)}{s}$$

where:

$h$  = ridge height in inches

$s$  = ridge spacing in inches

<b>Table 502–5A</b>	Angle of deviation = 0 degrees; <b>I</b> = <134
<b>Table 502–5B</b>	Angle of deviation = 22.5 degrees; <b>I</b> = <134
<b>Table 502–5C</b>	Angle of deviation = 45 degrees; <b>I</b> = <134
<b>Table 502–5D</b>	Angle of deviation = 67.5 degrees; <b>I</b> = <134
<b>Table 502–5E</b>	Angle of deviation = 90 degrees; <b>I</b> = <134
<b>Table 502–5F</b>	Angle of deviation = 0 degrees; <b>I</b> = 134
<b>Table 502–5G</b>	Angle of deviation = 22.5 degrees; <b>I</b> = 134
<b>Table 502–5H</b>	Angle of deviation = 45 degrees; <b>I</b> = 134
<b>Table 502–5I</b>	Angle of deviation = 67.5 degrees; <b>I</b> = 134
<b>Table 502–5J</b>	Angle of deviation = 90 degrees; <b>I</b> = 134
<b>Table 502–5K</b>	Angle of deviation = 0 degrees; <b>I</b> = 160 and 180
<b>Table 502–5L</b>	Angle of deviation = 22.5 degrees; <b>I</b> = 160 and 180
<b>Table 502–5M</b>	Angle of deviation = 45 degrees; <b>I</b> = 160 and 180
<b>Table 502–5N</b>	Angle of deviation = 67.5 degrees; <b>I</b> = 160 and 180
<b>Table 502–5O</b>	Angle of deviation = 90 degrees; <b>I</b> = 160 and 180
<b>Table 502–5P</b>	Angle of deviation = 0 degrees; <b>I</b> = 220
<b>Table 502–5Q</b>	Angle of deviation = 22.5 degrees; <b>I</b> = 220
<b>Table 502–5R</b>	Angle of deviation = 45 degrees; <b>I</b> = 220
<b>Table 502–5S</b>	Angle of deviation = 67.5 degrees; <b>I</b> = 220
<b>Table 502–5T</b>	Angle of deviation = 90 degrees; <b>I</b> = 220
<b>Table 502–5U</b>	Angle of deviation = 0 degrees; <b>I</b> = 250
<b>Table 502–5V</b>	Angle of deviation = 22.5 degrees; <b>I</b> = 250
<b>Table 502–5W</b>	Angle of deviation = 45 degrees; <b>I</b> = 250
<b>Table 502–5X</b>	Angle of deviation = 67.5 degrees; <b>I</b> = 250
<b>Table 502–5Y</b>	Angle of deviation = 90 degrees; <b>I</b> = 250
<b>Table 502–5Z</b>	Angle of deviation = 0 degrees; <b>I</b> = 310
<b>Table 502–5AA</b>	Angle of deviation = 22.5 degrees; <b>I</b> = 310
<b>Table 502–5BB</b>	Angle of deviation = 45 degrees; <b>I</b> = 310
<b>Table 502–5CC</b>	Angle of deviation = 67.5 degrees; <b>I</b> = 310
<b>Table 502–5DD</b>	Angle of deviation = 90 degrees; <b>I</b> = 310

**Table 502–5A** Angle of deviation = 0 degrees;  $I = <134$ 

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	0.7	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
10	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
14	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
18	0.9	0.7	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
20	0.9	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
24	0.9	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
30	0.9	0.8	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
36	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
38	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
40	0.9	0.8	0.7	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502–5B** Angle of deviation = 22.5 degrees;  $I = <134$ 

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	0.8	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
10	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
14	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
18	0.9	0.7	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
20	0.9	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
24	0.9	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
30	0.9	0.8	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
36	0.9	0.8	0.7	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4
38	0.9	0.8	0.7	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4
40	0.9	0.8	0.7	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.



**Table 502-5C** Angle of deviation = 45 degrees;  $I < 134$ 

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	0.8	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
10	0.8	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
14	0.8	0.7	0.5	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
18	0.9	0.7	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
20	0.9	0.7	0.6	0.5	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4
24	0.9	0.7	0.6	0.5	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4
30	0.9	0.8	0.6	0.6	0.5	0.5	0.5	0.4	0.4	0.4	0.4	0.4
36	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.4	0.4	0.4	0.4
38	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.4	0.4	0.4	0.4
40	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.4	0.4	0.4	0.4

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5D** Angle of deviation = 67.5 degrees;  $I < 134$ 

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	0.8	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5
10	0.8	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5
14	0.9	0.7	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5
18	0.9	0.7	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5
20	0.9	0.7	0.6	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5
24	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5
30	0.9	0.8	0.7	0.6	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5
36	0.9	0.8	0.7	0.6	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5
38	0.9	0.8	0.7	0.6	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5
40	0.9	0.8	0.7	0.6	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5E** Angle of deviation = 90 degrees;  $I = <134$ 

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	0.8	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
10	0.9	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
14	0.9	0.8	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
18	0.9	0.8	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
20	0.9	0.8	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
24	0.9	0.8	0.7	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
30	0.9	0.8	0.7	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
36	0.9	0.9	0.8	0.7	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6
38	0.9	0.9	0.8	0.7	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6
40	0.9	0.9	0.8	0.7	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5F** Angle of deviation = 0 degrees;  $I = 134$ 

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	0.8	0.6	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
10	0.9	0.7	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
14	0.9	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
18	0.9	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
20	0.9	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
24	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
30	1.0	0.9	0.7	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4
36	1.0	0.9	0.8	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4
38	1.0	0.9	0.8	0.6	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4
40	1.0	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5G** Angle of deviation = 22.5 degrees; I = 134

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
10	0.9	0.7	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
14	0.9	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
18	0.9	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
20	0.9	0.8	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
24	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
30	1.0	0.9	0.7	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4
36	1.0	0.9	0.8	0.6	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4
38	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4
40	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5H** Angle of deviation = 45 degrees; I = 134

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	0.9	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
10	0.9	0.7	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
14	0.9	0.7	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
18	0.9	0.8	0.6	0.5	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4
20	0.9	0.8	0.7	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4
24	1.0	0.8	0.7	0.6	0.5	0.5	0.5	0.4	0.4	0.4	0.4	0.4
30	1.0	0.9	0.7	0.6	0.5	0.5	0.5	0.5	0.4	0.4	0.4	0.4
36	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.4	0.4	0.4	0.4
38	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.4	0.4	0.4
40	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.4	0.4	0.4

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5I** Angle of deviation = 67.5 degrees; I = 134

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	0.9	0.7	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5
10	0.9	0.7	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5
14	0.9	0.8	0.6	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5
18	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5
20	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5
24	1.0	0.9	0.7	0.6	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5
30	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5
36	1.0	0.9	0.8	0.7	0.6	0.6	0.5	0.5	0.5	0.5	0.5	0.5
38	1.0	0.9	0.8	0.7	0.6	0.6	0.5	0.5	0.5	0.5	0.5	0.5
40	1.0	0.9	0.8	0.7	0.6	0.6	0.5	0.5	0.5	0.5	0.5	0.5

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5J** Angle of deviation = 90 degrees, I = 134

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	0.9	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
10	0.9	0.8	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
14	0.9	0.8	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
18	1.0	0.8	0.7	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
20	1.0	0.9	0.8	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
24	1.0	0.9	0.8	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
30	1.0	0.9	0.8	0.7	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6
36	1.0	0.9	0.8	0.8	0.7	0.7	0.6	0.6	0.6	0.6	0.6	0.6
38	1.0	0.9	0.8	0.8	0.7	0.7	0.6	0.6	0.6	0.6	0.6	0.6
40	1.0	0.9	0.8	0.8	0.7	0.7	0.6	0.6	0.6	0.6	0.6	0.6

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5K** Angle of deviation = 0 degrees; I = 160 and 180

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	0.9	0.7	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
10	1.0	0.8	0.6	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
14	1.0	0.8	0.7	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
18	1.0	0.9	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
20	1.0	0.9	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
24	1.0	0.9	0.8	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4
30	1.0	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4
36	1.0	0.9	0.9	0.8	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4
38	1.0	0.9	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4
40	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5L** Angle of deviation = 22.5 degrees; I = 160 and 180

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	0.9	0.7	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
10	1.0	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
14	1.0	0.8	0.7	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
18	1.0	0.9	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
20	1.0	0.9	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
24	1.0	0.9	0.8	0.7	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4
30	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4
36	1.0	0.9	0.9	0.8	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4
38	1.0	0.9	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4
40	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.4	0.4	0.4	0.4

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5M** Angle of deviation = 45 degrees; I = 160 and 180

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	0.9	0.7	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
10	1.0	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
14	1.0	0.9	0.7	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
18	1.0	0.9	0.7	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4
20	1.0	0.9	0.8	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4
24	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4
30	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.4	0.4	0.4	0.4
36	1.0	0.9	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.4	0.4	0.4
38	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.4	0.4	0.4
40	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.4	0.4	0.4

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5N** Angle of deviation = 67.5 degrees; I = 160 and 180

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	0.9	0.7	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5
10	1.0	0.8	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5
14	1.0	0.9	0.7	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5
18	1.0	0.9	0.8	0.6	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5
20	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5
24	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5
30	1.0	0.9	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.5	0.5
36	1.0	1.0	0.9	0.8	0.7	0.6	0.6	0.5	0.5	0.5	0.5	0.5
38	1.0	1.0	0.9	0.8	0.7	0.6	0.6	0.5	0.5	0.5	0.5	0.5
40	1.0	1.0	0.9	0.8	0.7	0.6	0.6	0.5	0.5	0.5	0.5	0.5

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502–5O** Angle of deviation = 90 degrees; I = 160 and 180

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	1.0	0.8	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
10	1.0	0.9	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
14	1.0	0.9	0.8	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
18	1.0	0.9	0.8	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
20	1.0	0.9	0.8	0.7	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6
24	1.0	0.9	0.9	0.8	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6
30	1.0	1.0	0.9	0.8	0.7	0.7	0.6	0.6	0.6	0.6	0.6	0.6
36	1.0	1.0	0.9	0.8	0.8	0.7	0.6	0.6	0.6	0.6	0.6	0.6
38	1.0	1.0	0.9	0.8	0.8	0.7	0.7	0.6	0.6	0.6	0.6	0.6
40	1.0	1.0	0.9	0.9	0.8	0.7	0.7	0.6	0.6	0.6	0.6	0.6

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502–5P** Angle of deviation = 0 degrees; I = 220

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	1.0	0.8	0.6	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
10	1.0	0.9	0.7	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
14	1.0	0.9	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
18	1.0	1.0	0.9	0.7	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
20	1.0	1.0	0.9	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4
24	1.0	1.0	0.9	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4
30	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4
36	1.0	1.0	0.9	0.9	0.8	0.7	0.5	0.5	0.4	0.4	0.4	0.4
38	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4	0.4
40	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4	0.4

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.



**Table 502-5Q** Angle of deviation = 22.5 degrees; I = 220

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	1.0	0.8	0.6	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
10	1.0	0.9	0.7	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
14	1.0	0.9	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
18	1.0	1.0	0.9	0.7	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4
20	1.0	1.0	0.9	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4
24	1.0	1.0	0.9	0.8	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4
30	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4
36	1.0	1.0	0.9	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4	0.4
38	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4	0.4
40	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.4	0.4	0.4

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5R** Angle of deviation = 45 degrees; I = 220

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	1.0	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
10	1.0	0.9	0.7	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
14	1.0	0.9	0.8	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4	0.4
18	1.0	1.0	0.9	0.7	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4
20	1.0	1.0	0.9	0.7	0.6	0.5	0.5	0.4	0.4	0.4	0.4	0.4
24	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.4	0.4	0.4	0.4
30	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.4	0.4	0.4
36	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.4	0.4
38	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.4	0.4
40	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.4	0.4

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502–5S** Angle of deviation = 67.5 degrees; I = 220

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	1.0	0.9	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5
10	1.0	0.9	0.7	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5
14	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5
18	1.0	1.0	0.9	0.7	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5
20	1.0	1.0	0.9	0.8	0.6	0.6	0.5	0.5	0.5	0.5	0.5	0.5
24	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.5	0.5
30	1.0	1.0	0.9	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.5
36	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.6	0.5	0.5	0.5	0.5
38	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.6	0.5	0.5	0.5	0.5
40	1.0	1.0	1.0	0.9	0.8	0.7	0.7	0.6	0.5	0.5	0.5	0.5

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502–5T** Angle of deviation = 90 degrees; I = 220

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	1.0	0.9	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
10	1.0	0.9	0.8	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
14	1.0	1.0	0.9	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
18	1.0	1.0	0.9	0.8	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6
20	1.0	1.0	0.9	0.8	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6
24	1.0	1.0	0.9	0.9	0.8	0.7	0.6	0.6	0.6	0.6	0.6	0.6
30	1.0	1.0	1.0	0.9	0.8	0.7	0.7	0.6	0.6	0.6	0.6	0.6
36	1.0	1.0	1.0	0.9	0.8	0.8	0.7	0.6	0.6	0.6	0.6	0.6
38	1.0	1.0	1.0	0.9	0.9	0.8	0.7	0.7	0.6	0.6	0.6	0.6
40	1.0	1.0	1.0	0.9	0.9	0.8	0.7	0.7	0.6	0.6	0.6	0.6

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5U** Angle of deviation = 90 degrees; I = 250

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	1.0	0.9	0.7	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
10	1.0	1.0	0.8	0.6	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
14	1.0	1.0	0.9	0.7	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
18	1.0	1.0	0.9	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4
20	1.0	1.0	0.9	0.8	0.7	0.5	0.4	0.4	0.4	0.4	0.4	0.4
24	1.0	1.0	1.0	0.9	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4
30	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4	0.4
36	1.0	1.0	1.0	0.9	0.9	0.8	0.7	0.5	0.5	0.4	0.4	0.4
38	1.0	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4
40	1.0	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5V** Angle of deviation = 22.5 degrees; I = 250

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	1.0	0.9	0.7	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
10	1.0	1.0	0.8	0.6	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
14	1.0	1.0	0.9	0.7	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
18	1.0	1.0	0.9	0.8	0.7	0.5	0.4	0.4	0.4	0.4	0.4	0.4
20	1.0	1.0	0.9	0.8	0.7	0.5	0.4	0.4	0.4	0.4	0.4	0.4
24	1.0	1.0	1.0	0.9	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4
30	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4	0.4
36	1.0	1.0	1.0	0.9	0.9	0.8	0.7	0.5	0.5	0.4	0.4	0.4
38	1.0	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4
40	1.0	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.4	0.4	0.4

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5W** Angle of deviation = 45 degrees; I = 250

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	1.0	0.9	0.7	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
10	1.0	1.0	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
14	1.0	1.0	0.9	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4	0.4
18	1.0	1.0	0.9	0.8	0.7	0.5	0.5	0.4	0.4	0.4	0.4	0.4
20	1.0	1.0	0.9	0.9	0.7	0.6	0.5	0.4	0.4	0.4	0.4	0.4
24	1.0	1.0	1.0	0.9	0.8	0.6	0.5	0.5	0.4	0.4	0.4	0.4
30	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.4	0.4	0.4
36	1.0	1.0	1.0	0.9	0.9	0.8	0.7	0.6	0.5	0.5	0.4	0.4
38	1.0	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.4	0.4
40	1.0	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.4

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5X** Angle of deviation = 67.5 degrees; I = 250

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	1.0	0.9	0.7	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5
10	1.0	1.0	0.8	0.7	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5
14	1.0	1.0	0.9	0.8	0.6	0.5	0.5	0.5	0.5	0.5	0.5	0.5
18	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.5	0.5
20	1.0	1.0	1.0	0.9	0.7	0.6	0.5	0.5	0.5	0.5	0.5	0.5
24	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.5
30	1.0	1.0	1.0	0.9	0.9	0.8	0.6	0.6	0.5	0.5	0.5	0.5
36	1.0	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.6	0.5	0.5	0.5
38	1.0	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.6	0.5	0.5	0.5
40	1.0	1.0	1.0	1.0	0.9	0.8	0.8	0.7	0.6	0.5	0.5	0.5

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5Y** Angle of deviation = 90 degrees; **I** = 250

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	1.0	0.9	0.8	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
10	1.0	1.0	0.9	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
14	1.0	1.0	0.9	0.8	0.7	0.6	0.6	0.6	0.6	0.6	0.6	0.6
18	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.6	0.6	0.6	0.6	0.6
20	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.6	0.6	0.6	0.6	0.6
24	1.0	1.0	1.0	0.9	0.8	0.7	0.7	0.6	0.6	0.6	0.6	0.6
30	1.0	1.0	1.0	0.9	0.9	0.8	0.7	0.7	0.6	0.6	0.6	0.6
36	1.0	1.0	1.0	1.0	0.9	0.9	0.8	0.7	0.6	0.6	0.6	0.6
38	1.0	1.0	1.0	1.0	0.9	0.9	0.8	0.7	0.7	0.6	0.6	0.6
40	1.0	1.0	1.0	1.0	0.9	0.9	0.8	0.7	0.7	0.6	0.6	0.6

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5Z** Angle of deviation = 0 degrees; **I** = 310

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	1.0	1.0	0.9	0.7	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
10	1.0	1.0	1.0	0.9	0.6	0.4	0.4	0.4	0.4	0.4	0.4	0.4
14	1.0	1.0	1.0	0.9	0.8	0.6	0.4	0.4	0.4	0.4	0.4	0.4
18	1.0	1.0	1.0	1.0	0.9	0.8	0.6	0.4	0.4	0.4	0.4	0.4
20	1.0	1.0	1.0	1.0	0.9	0.8	0.6	0.5	0.4	0.4	0.4	0.4
24	1.0	1.0	1.0	1.0	1.0	0.9	0.8	0.6	0.5	0.4	0.4	0.4
30	1.0	1.0	1.0	1.0	1.0	0.9	0.9	0.7	0.6	0.5	0.4	0.4
36	1.0	1.0	1.0	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.4
38	1.0	1.0	1.0	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.4
40	1.0	1.0	1.0	1.0	1.0	1.0	0.9	0.9	0.8	0.6	0.5	0.4

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5AA** Angle of deviation = 22.5 degrees; I = 310

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	1.0	1.0	0.9	0.7	0.4	0.4	0.4	0.4	0.4	0.4	0.4	0.4
10	1.0	1.0	1.0	0.9	0.6	0.4	0.4	0.4	0.4	0.4	0.4	0.4
14	1.0	1.0	1.0	0.9	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4
18	1.0	1.0	1.0	1.0	0.9	0.8	0.6	0.4	0.4	0.4	0.4	0.4
20	1.0	1.0	1.0	1.0	0.9	0.8	0.6	0.5	0.4	0.4	0.4	0.4
24	1.0	1.0	1.0	1.0	1.0	0.9	0.8	0.6	0.5	0.4	0.4	0.4
30	1.0	1.0	1.0	1.0	1.0	0.9	0.9	0.7	0.6	0.5	0.4	0.4
36	1.0	1.0	1.0	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.4
38	1.0	1.0	1.0	1.0	1.0	1.0	0.9	0.9	0.7	0.6	0.5	0.4
40	1.0	1.0	1.0	1.0	1.0	1.0	0.9	0.9	0.8	0.6	0.5	0.4

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5BB** Angle of deviation = 45 degrees; I = 310

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	1.0	1.0	0.9	0.7	0.5	0.4	0.4	0.4	0.4	0.4	0.4	0.4
10	1.0	1.0	1.0	0.9	0.7	0.5	0.4	0.4	0.4	0.4	0.4	0.4
14	1.0	1.0	1.0	1.0	0.8	0.6	0.5	0.4	0.4	0.4	0.4	0.4
18	1.0	1.0	1.0	1.0	0.9	0.8	0.6	0.5	0.4	0.4	0.4	0.4
20	1.0	1.0	1.0	1.0	0.9	0.8	0.7	0.5	0.5	0.4	0.4	0.4
24	1.0	1.0	1.0	1.0	1.0	0.9	0.8	0.6	0.5	0.4	0.4	0.4
30	1.0	1.0	1.0	1.0	1.0	0.9	0.9	0.8	0.6	0.5	0.5	0.4
36	1.0	1.0	1.0	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.5
38	1.0	1.0	1.0	1.0	1.0	1.0	0.9	0.9	0.8	0.6	0.5	0.5
40	1.0	1.0	1.0	1.0	1.0	1.0	0.9	0.9	0.8	0.7	0.5	0.5

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5CC** Angle of deviation = 67.5 degrees; I = 310


Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	1.0	1.0	0.9	0.7	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5
10	1.0	1.0	1.0	0.9	0.7	0.5	0.5	0.5	0.5	0.5	0.5	0.5
14	1.0	1.0	1.0	1.0	0.9	0.7	0.5	0.5	0.5	0.5	0.5	0.5
18	1.0	1.0	1.0	1.0	0.9	0.8	0.6	0.5	0.5	0.5	0.5	0.5
20	1.0	1.0	1.0	1.0	0.9	0.9	0.7	0.6	0.5	0.5	0.5	0.5
24	1.0	1.0	1.0	1.0	1.0	0.9	0.8	0.7	0.5	0.5	0.5	0.5
30	1.0	1.0	1.0	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.5
36	1.0	1.0	1.0	1.0	1.0	1.0	0.9	0.9	0.8	0.6	0.6	0.5
38	1.0	1.0	1.0	1.0	1.0	1.0	0.9	0.9	0.8	0.7	0.6	0.5
40	1.0	1.0	1.0	1.0	1.0	1.0	0.9	0.9	0.8	0.7	0.6	0.5

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.

**Table 502-5DD** Angle of deviation = 90 degrees; I = 310

Ridge spacing (inches)	Ridge height (inches)											
	1	2	3	4	5	6	7	8	9	10	11	12
7	1.0	1.0	1.0	0.8	0.6	0.6	0.6	0.6	0.6	0.6	0.6	0.6
10	1.0	1.0	1.0	0.9	0.8	0.6	0.6	0.6	0.6	0.6	0.6	0.6
14	1.0	1.0	1.0	1.0	0.9	0.7	0.6	0.6	0.6	0.6	0.6	0.6
18	1.0	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.6	0.6	0.6	0.6
20	1.0	1.0	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.6	0.6	0.6
24	1.0	1.0	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.6	0.6	0.6
30	1.0	1.0	1.0	1.0	1.0	1.0	0.9	0.8	0.7	0.6	0.6	0.6
36	1.0	1.0	1.0	1.0	1.0	1.0	0.9	0.9	0.8	0.7	0.6	0.6
38	1.0	1.0	1.0	1.0	1.0	1.0	1.0	0.9	0.8	0.7	0.7	0.6
40	1.0	1.0	1.0	1.0	1.0	1.0	1.0	0.9	0.8	0.8	0.7	0.6

These values are based on conditions in which erosive wind energy is 60% parallel and 40% perpendicular to prevailing erosive wind.



Graph to convert random roughness heights (standard deviation in inches) to WEQ K-subfactors for random roughness. K subfactors vary by I factors assigned to soil groups.

Random roughness is defined as the standard deviation (in inches) of the soil surface elevations, measured at regular intervals from a fixed arbitrary plane above a tilled soil surface, after oriented roughness has been considered.

Random roughness photos and associated random roughness (standard deviation) values are in Predicting Soil Erosion by Water: A Guide to Conservation Planning With Revised Universal Soil Loss Equation (RUSLE), 1997, Agriculture Handbook 703, appendix C, or can be downloaded at

<http://www.nrcs.usda.gov/technical/ECS/agronomy/roughness.html>

**Table 502-6** Table converts random roughness heights (standard deviation in inches) to WEQ K subfactors ( $K_{rr}$ ) for random roughness.  $K_{rr}$  values vary by I factors assigned to soil Wind Erodibility Groups.

I Factors	Random roughness (standard deviation, inches)									
	0.2	0.4	0.6	0.8	1.0	1.2	1.4	1.6	1.8	2.0
>134	1.00	1.00	1.00	1.00	1.00	1.00	1.00	1.00	1.00	1.00
134	1.00	0.99	0.98	0.96	0.93	0.91	0.98	0.96	0.85	0.84
104	1.00	0.94	0.88	0.82	0.78	0.74	0.71	0.69	0.67	0.66
86	1.00	0.87	0.76	0.67	0.61	0.57	0.54	0.52	0.50	0.48
56 or less	1.00	0.71	0.50	0.38	0.31	0.27	0.25	0.23	0.23	0.22



**Table 502-7** Random roughness (standard deviation) core values

This information on core values is from Predicting Soil Erosion by Water: A Guide to Conservation Planning With the Revised Universal Soil Loss Equation (RUSLE), 1997, Agriculture Handbook 703.

Parameter values of *core* cropland field operations may be used in the Wind Erosion Equation for random roughness. However the use of the random roughness photos in Agriculture Handbook 703, in appendix C, may be preferable, especially where roughness is caused by residual sod material such as the crowns of plants that has attached roots and soil.

The following core values are typical and representative for field operations in medium textured soils tilled at optimum moisture conditions. Many of the machines may differ by cropping region, farming practice, soil texture, or other conditions. Refer to the random roughness photos in the handbook and adjust to values that seem most appropriate. The photos and associated random roughness (standard deviation) values in the Agriculture Handbook 703 can be downloaded at:

<http://www.nrcs.usda.gov/technical/ECS/agronomy/roughness.html>

State agronomists can reproduce and distribute copies of the photographs to Field Offices.

#### Field operations

#### Random roughness (standard deviation in inches)

Chisel, sweeps	1.20
Chisel, straight point	1.50
Chisel, twisted shovels	1.90
Cultivator, field	0.70
Cultivator, row	0.70
Cultivator, ridge till	0.70
Disk, 1-way	1.20
Disk, heavy plowing	1.90
Disk, tandem	0.80
Drill, double disk	0.40
Drill, deep furrow	0.50
Drill, no-till	0.40
Drill, no-till into sod	0.30
Fertilizer applicator, anhyd knife	0.60
Harrow, spike	0.40
Harrow, tine	0.40
Lister	0.80
Manure injector	1.50
Moldboard plow	1.90
Mulch treader	0.40
Planter, no-till	0.40
Planter, row	0.40
Rodweeder	0.40
Rotary hoe	0.40
Vee ripper	1.20

**Exhibit 502-7a** Example of erosive wind data available for specific locationsThis information is found at: <http://www.weru.ksu.edu/nrcs/windparm/>

KS CHANUTE	JAN	FEB	MAR	APR	MAY	JUN	JUL	AUG	SEP	OCT	NOV	DEC
PREV WIND EROS DIR	180	0	180	180	180	180	180	180	180	180	180	180
PREPONDERANCE	4.0	2.3	2.5	3.5	4.6	4.2	3.6	3.7	4.5	4.8	5.2	3.4
EROSIVITY (EWE)	7.9	7.3	17.5	30.2	17.9	2.5	.7	1.5	1.6	2.0	5.6	5.1
CUMULATIVE EWE	7.9	15.3	32.8	63.0	81.0	83.4	84.1	85.6	87.2	89.3	94.9	100.0
KS CONCORDIA	JAN	FEB	MAR	APR	MAY	JUN	JUL	AUG	SEP	OCT	NOV	DEC
PREV WIND EROS DIR	0	0	338	158	180	180	180	180	180	180	338	338
PREPONDERANCE	3.4	2.7	2.7	2.0	2.8	3.4	3.8	4.1	5.8	5.3	3.0	2.5
EROSIVITY (EWE)	8.9	9.5	19.8	18.4	7.4	5.4	3.7	3.3	3.8	6.2	5.9	7.6
CUMULATIVE EWE	8.9	18.4	38.2	56.6	64.0	69.5	73.1	76.5	80.3	86.5	92.4	100.0
KS DODGE_CITY	JAN	FEB	MAR	APR	MAY	JUN	JUL	AUG	SEP	OCT	NOV	DEC
PREV WIND EROS DIR	0	0	0	180	180	180	180	180	180	180	0	0
PREPONDERANCE	6.6	3.4	2.7	3.1	3.6	5.8	4.1	4.7	5.7	5.5	3.4	3.8
EROSIVITY (EWE)	7.3	8.5	17.3	16.5	9.1	7.7	4.5	3.2	5.6	6.5	6.5	7.4
CUMULATIVE EWE	7.3	15.8	33.1	49.6	58.7	66.4	70.9	74.1	79.6	86.2	92.6	100.0
KS FT.RILEY	JAN	FEB	MAR	APR	MAY	JUN	JUL	AUG	SEP	OCT	NOV	DEC
PREV WIND EROS DIR	180	180	180	180	180	180	180	180	202	180	180	202
PREPONDERANCE	5.2	3.6	3.9	3.0	6.0	7.9	5.4	4.1	4.8	4.9	3.6	1.9
EROSIVITY (EWE)	5.3	6.3	20.6	18.5	10.1	4.9	2.2	3.1	5.4	10.0	5.7	7.8
CUMULATIVE EWE	5.3	11.7	32.3	50.8	60.9	65.8	68.0	71.1	76.4	86.4	92.2	100.0
KS GOODLAND	JAN	FEB	MAR	APR	MAY	JUN	JUL	AUG	SEP	OCT	NOV	DEC
PREV WIND EROS DIR	338	338	338	338	158	180	158	158	180	338	337	337
PREPONDERANCE	3.3	3.8	3.4	3.6	2.3	2.4	2.1	2.9	3.2	3.6	3.6	4.4
EROSIVITY (EWE)	5.1	7.4	19.2	16.9	9.7	8.8	4.4	4.1	6.0	5.2	7.3	6.0
CUMULATIVE EWE	5.1	12.5	31.7	48.5	58.2	67.0	71.4	75.5	81.5	86.7	94.0	100.0
KS HUTCHINSON	JAN	FEB	MAR	APR	MAY	JUN	JUL	AUG	SEP	OCT	NOV	DEC
PREV WIND EROS DIR	0	0	0	180	180	180	180	180	180	180	0	0
PREPONDERANCE	4.5	3.4	3.2	2.9	3.8	5.1	4.9	3.5	4.5	5.1	4.1	4.3
EROSIVITY (EWE)	7.9	10.2	12.3	15.5	9.5	10.1	3.9	3.5	6.2	7.6	6.8	6.6
CUMULATIVE EWE	7.9	18.1	30.4	45.9	55.3	65.4	69.3	72.8	79.0	86.6	93.4	100.0
KS OLATHE	JAN	FEB	MAR	APR	MAY	JUN	JUL	AUG	SEP	OCT	NOV	DEC
PREV WIND EROS DIR	180	338	180	202	180	180	202	202	202	180	180	180
PREPONDERANCE	2.4	1.8	1.8	2.2	2.7	3.6	3.7	4.4	5.5	2.6	1.9	2.0
EROSIVITY (EWE)	8.3	7.4	27.9	26.7	7.7	1.9	.7	.6	1.0	4.9	4.9	7.9
CUMULATIVE EWE	8.3	15.7	43.6	70.4	78.1	80.0	80.7	81.3	82.3	87.2	92.1	100.0
KS RUSSELL	JAN	FEB	MAR	APR	MAY	JUN	JUL	AUG	SEP	OCT	NOV	DEC
PREV WIND EROS DIR	0	0	0	0	202	202	202	202	202	180	0	0
PREPONDERANCE	3.3	2.9	2.6	1.9	2.7	3.0	3.1	3.4	4.2	3.1	2.8	2.4
EROSIVITY (EWE)	6.9	8.9	14.8	14.5	8.4	5.9	4.8	6.2	7.3	7.2	8.2	6.9
CUMULATIVE EWE	6.9	15.8	30.7	45.1	53.5	59.4	64.2	70.4	77.6	84.8	93.1	100.0
KS SALINA	JAN	FEB	MAR	APR	MAY	JUN	JUL	AUG	SEP	OCT	NOV	DEC
PREV WIND EROS DIR	0	0	0	180	180	180	180	180	180	180	180	0
PREPONDERANCE	5.8	2.4	3.0	2.9	4.6	5.4	3.7	4.6	6.4	4.6	4.0	3.0
EROSIVITY (EWE)	7.4	8.8	19.6	19.8	11.5	4.2	2.2	5.2	6.5	4.9	5.8	4.2
CUMULATIVE EWE	7.4	16.2	35.8	55.6	67.1	71.3	73.4	78.6	85.1	90.0	95.8	100.0



















## NRCS - WEQ CALCULATIONS, Version 5

**Producer:** lam Windy      **Planner:** mas      **Location:** Mose Lake      **Tract:** 123      **Field:** 1  
**Crop Rotation:** Corn      **Climate Data Station:** WA, MOSES LAKE, old      **Site "C" Value:** 50  
**Tillage Direction (NS/EW):** ns      **Length/width ratio:** 1      **Field Direction (NS/EW):** ew      **Field Width (Ft.):** 2640  
**Irrigation (Y or N):** y      **Soil "I":** 134      **Wind Erodibility Group:** 2 (1-7)      **TWF:** 1 (see instr.)  
**Sum Period Erosion (t/ac):** 6.9      **No. Yrs in Rotation:** 1.0      **Av. Annual Wind Erosion:** 6.9 (t/ac/yr)

Mgt Periods		Irr.	Soil	Ridge Roughness				R Roug	Unsheltered Distance				SGe	Erosion			
Dates		No. of	"I"	Dev.	Ht.	Sp.	"Krd"	"Krr"	Dev.	Prep.	WED	"L"	"V"	"E"	EWE	"IF"	Loss
Begin	End	(#)	(t/ac)	(deg)	(in.)	(in.)	(factor)	(factor)	(deg)	(factor)	(factor)	(ft)	(lbs/ac)	(t/ac)	(%)	(%)	(t/ac)
1/1/99	1/2/99	0	104	90.0	0	0	1.0	0.99	0.0	2.5	1.02	2693	3422	0.0	0.3	1.00	0.00
1/2/99	3/15/99	0	104	90.0	0	0	1.00	1.00	0.0	2.5	1.02	2693	2703	0.0	24.9	1.00	0.00
3/15/99	3/15/99	0	104	45.0	0	0	1.00	0.98	45.0	1.3	1.03	2719	1437	4.0	0.0	1.00	0.00
3/15/99	4/1/99	0	104	45.0	0	0	1.0	1.00	45.0	1.3	1.03	2719	1361	5.3	8.5	1.00	0.45
4/1/99	4/1/99	0	104	45.0	0	0	1.0	0.88	45.0	1.1	1.03	2719	57	43.8	0.0	1.00	0.00
4/1/99	4/10/99	0	104	45.0	0	0	1.0	0.99	45.0	1.1	1.03	2719	54	49.8	4.3	1.00	2.12
4/10/99	4/15/99	0	104	45.0	3	30	0.7	0.98	45.0	1.1	1.03	2719	34	33.8	2.4	1.00	0.80
4/15/99	4/30/99	2	104	45.0	3	30	0.7	0.99	45.0	1.1	1.03	2719	33	34.5	7.1	0.87	2.12
4/30/99	5/15/99	6	104	45.0	3	30	0.7	1.00	45.0	1.1	1.03	2719	37	34.6	4.4	0.60	0.92
5/15/99	5/15/99	0	104	0.0	3	30	0.7	0.97	90.0	1.1	1.03	2719	26	33.2	0.0	1.00	0.00
5/15/99	5/30/99	12	104	0.0	3	30	0.7	1.00	90.0	1.1	1.03	2719	114	32.5	4.3	0.20	0.28
5/30/99	6/14/99	12	104	0.0	3	30	0.7	1.00	90.0	1.1	1.03	2719	448	23.7	4.5	0.20	0.21
6/14/99	6/29/99	12	104	45.0	3	30	0.7	1.00	45.0	1.2	1.03	2719	5291	0.0	4.6	0.20	0.00
6/29/99	10/15/99	38	104	45.0	3	30	0.7	1.00	45.0	1.2	1.03	2719	6999	0.0	17.2	0.65	0.00
10/15/99	11/1/99	0	104	90.0	0	0	1.0	1.00	0.0	1.6	1.03	2719	6999	0.0	3.7	1.00	0.00
11/1/99	11/1/99	0	104	90.0	0	0	1.0	0.98	0.0	1.6	1.03	2719	3613	0.0	0.0	1.00	0.00
11/1/99	12/31/99	0	104	90.0	0	0	1.0	1.00	0.0	1.6	1.03	2719	3422	0.0	13.7	1.00	0.00

**Exhibit 502–8** C factor map, United States

An interactive version of the C factor map is located at <http://data4.ftw.nrcs.usda.gov/website/>. On this page, click on the link for “C-Values”, and the map will load. The icons below will be displayed in the upper left hand corner of the screen. Following each one is a short description of what that icon allows you to do.

-  - Toggles between Layer list and the Map Legend (in upper right hand corner of screen).
-  - Toggles the overview map (in the upper right hand corner) on and off.
-  - After clicking this icon, you can zoom in on a specific area of the map.
-  - After clicking this icon, you can zoom out from a specific area of the map.
-  - Zooms the U.S. map so that it fills the entire viewing area.
-  - Zooms to the active layer
-  - Returns zoom level to the last one viewed.
-  - Cursor becomes cross-arrows. As you zoom in on the map, click and hold the left mouse button and move the map in the desired direction.
-  - Cursor becomes crosshairs. Click on an attribute to find its value. For example, when the “WEQ” layer is active, click on a C factor isoline to find its value. When the “County Boundaries” layer is active, click on a county to find its name and area in acres.
-  - Brings up a query box at the bottom of the screen. Allows you to query the data for the active layer for specific attribute values. Uses SQL (Structured Query Language)
-  - Brings up a query box that allows you to search for a specific value in the active data layer.
-  - Allows you to measure the distance between two points. The cursor becomes crosshairs; click on two different locations on the map, and the distance between them will be displayed.
-  - Brings up a box at the bottom of the screen that allows you to change the units of distance used on the map.
-  - After selecting a line or polygon, click on this icon to set a buffer of a given width around it.
-  - Cursor becomes crosshairs. Hold down the left mouse button and select a rectangular area. Displays values of attributes in and immediately adjacent to the area selected. Attributes displayed will vary with the active layer.
-  - Cursor becomes crosshairs. Allows you to describe a line or a polygon. Displays values of attributes touched by the line or polygon. Attributes displayed will vary with the active layer
-  - Clears the current selection
-  - Prints the current selection

**Exhibit 502–9** Procedures for developing local C factors

The Wind Erosion Research Unit, ARS, Manhattan, Kansas, published new wind erosion C factors in 1983. This information, based on 1941-80 recorded weather data, updated previously published maps.

Agriculture Research Service provided calculated values of C at benchmark locations—sites where available weather data included average monthly precipitation and temperature and average annual wind velocity. Data was obtained from the National Climatic Center at Asheville, North Carolina, from the Wind Energy Resource Atlas, and from other sources.

To supplement the benchmark C values provided by ARS, NRCS extended the estimation of C to many more local weather stations. Where recorded precipitation and temperature data were available, including 1951-80 NOAA weather data. An estimate of average annual wind velocity was used to calculate C. Wind velocity isoline maps were prepared from available data, and used as supporting information to estimate local wind velocities. The influence of topography on local climate was also considered.

Precipitation and temperature data was used to calculate the precipitation-effectiveness (PE) index at various locations, using the equation:

$$PE = \sum^{12} 115 \times \left[ \frac{P}{(T-10)} \right]^{\frac{10}{9}}$$

where:

PE = precipitation-effectiveness index

P = average monthly precipitation <sup>1/</sup> (inches)

T = average monthly temperature <sup>2/</sup> (°F)

1/ When the average monthly precipitation is less than 0.5 inches, use 0.5

2/ When average monthly temperature is less than 28.4 °F, use 28.4

The PE index was used to represent surface soil moisture, together with estimated local wind velocities, in the general equation to calculate C:

$$C = 34.48 \times \frac{V^3}{(PE)^2}$$

where:

C = annual climatic factor

V = average annual wind velocity

Estimated local C values, calculated as described above, were recorded on state and regional maps and used as a basis to locate C value isolines. The benchmark values provided by ARS were not changed unless there was reason to believe that station data was not reliable.

The mathematical formulas can be solved manually or by use of computer software available for wind erosion from the NRCS cooperating scientist and most State Offices. The following page shows an example of the calculations.

**Exhibit 502-9** Procedures for developing local C factors—continued

Constraints: Monthly P => 0.5 inches  
 Monthly T => 28.4 degrees F

LOCATION: Norton, Kansas

COUNTY: Norton

DATE: 09/26/97

Month	P	adj P	T	adj T	T - 10	PE
January	0.41	0.5	26.7	28.4	18.4	2.1
February	0.6	0.6	32.6	32.6	22.6	2.0
March	1.33	1.33	39.7	39.7	29.7	3.7
April	1.83	1.83	52.4	52.4	42.4	3.5
May	3.42	3.42	62.3	62.3	52.3	5.6
June	3.68	3.68	72.2	72.2	62.2	5.0
July	3.35	3.35	77.8	77.8	67.8	4.1
August	2.61	2.61	76.3	76.3	66.3	3.2
September	2.16	2.16	66.8	66.8	56.8	3.1
October	1.41	1.41	55.7	55.7	45.7	2.4
November	0.73	0.73	40.3	40.3	30.3	1.8
December	0.46	0.5	31.1	31.1	21.1	1.8
Average annual	21.99		52.8			38.3

Estimated V = 13

Estimated C = 51.8

**Table 502-8A** Wind erosion direction factor; angle of deviation  $\angle = 0$  degrees

Preon- dence	Field length/width ratio						
	1:1	2:1	4:1	8:1	10:1	12:1	16:1
1.0	1.03	1.46	1.70	1.85	1.88	1.90	1.95
1.2	1.03	1.30	1.45	1.53	1.56	1.58	1.62
1.4	1.03	1.20	1.28	1.32	1.35	1.37	1.40
1.6	1.03	1.14	1.18	1.20	1.22	1.23	1.25
1.8	1.03	1.10	1.11	1.12	1.13	1.14	1.15
2.0	1.02	1.07	1.07	1.07	1.08	1.08	1.08
2.2	1.02	1.05	1.05	1.05	1.05	1.05	1.05
2.4	1.02	1.04	1.04	1.04	1.04	1.04	1.04
2.6	1.01	1.03	1.03	1.03	1.03	1.03	1.03
2.8	1.01	1.02	1.02	1.02	1.02	1.02	1.02
3.0	1.01	1.02	1.02	1.02	1.02	1.02	1.02
3.2	1.01	1.01	1.01	1.01	1.01	1.01	1.01
3.4	1.01	1.01	1.01	1.01	1.01	1.01	1.01
3.6	1.00	1.01	1.01	1.01	1.01	1.01	1.01
3.8	1.00	1.01	1.01	1.01	1.01	1.01	1.01
4.0	1.00	1.01	1.01	1.01	1.01	1.01	1.01

See footnote at end of table.

**Table 502-8B** Wind erosion direction factor; angle of deviation  $\angle = 22.5$  degrees

Preon- dence	Field length/width ratio						
	1:1	2:1	4:1	8:1	10:1	12:1	16:1
1.0	1.03	1.46	1.70	1.85	1.88	1.90	1.95
1.2	1.03	1.37	1.50	1.61	1.64	1.66	1.70
1.4	1.03	1.27	1.36	1.44	1.46	1.47	1.50
1.6	1.03	1.22	1.26	1.30	1.32	1.33	1.35
1.8	1.03	1.18	1.20	1.21	1.22	1.23	1.24
2.0	1.04	1.16	1.16	1.16	1.16	1.16	1.17
2.2	1.05	1.14	1.14	1.14	1.14	1.14	1.14
2.4	1.06	1.13	1.13	1.13	1.13	1.13	1.13
2.6	1.06	1.13	1.13	1.13	1.13	1.13	1.13
2.8	1.07	1.12	1.12	1.12	1.12	1.12	1.12
3.0	1.07	1.12	1.12	1.12	1.12	1.12	1.12
3.2	1.07	1.12	1.12	1.12	1.12	1.12	1.12
3.4	1.08	1.12	1.12	1.12	1.12	1.12	1.12
3.6	1.08	1.11	1.11	1.11	1.11	1.11	1.11
3.8	1.08	1.11	1.11	1.11	1.11	1.11	1.11
4.0	1.08	1.11	1.11	1.11	1.11	1.11	1.11

See footnote at end of table

**Table 502-8C** Wind erosion direction factor; angle of deviation  $\frac{1}{2}$  = 45 degrees

Prepon- dence	Field length/width ratio						
	1:1	2:1	4:1	8:1	10:1	12:1	16:1
1.0	1.03	1.46	1.70	1.85	1.88	1.90	1.95
1.2	1.03	1.44	1.63	1.72	1.75	1.77	1.81
1.4	1.03	1.42	1.57	1.62	1.65	1.67	1.70
1.6	1.03	1.42	1.52	1.55	1.57	1.58	1.61
1.8	1.03	1.42	1.49	1.51	1.52	1.53	1.55
2.0	1.03	1.42	1.48	1.49	1.49	1.49	1.50
2.2	1.02	1.42	1.48	1.48	1.48	1.48	1.48
2.4	1.02	1.42	1.48	1.48	1.48	1.48	1.48
2.6	1.01	1.42	1.48	1.48	1.48	1.48	1.48
2.8	1.01	1.42	1.48	1.48	1.48	1.48	1.48
3.0	1.01	1.42	1.48	1.48	1.48	1.48	1.48
3.2	1.01	1.42	1.48	1.48	1.48	1.48	1.48
3.4	1.01	1.42	1.48	1.48	1.48	1.48	1.48
3.6	1.01	1.42	1.48	1.48	1.48	1.48	1.48
3.8	1.01	1.42	1.48	1.48	1.48	1.48	1.48
4.0	1.01	1.42	1.48	1.48	1.48	1.48	1.48

See footnote at end of table.

**Table 502-8D** Wind erosion direction factor; angle of deviation  $\frac{1}{2}$  = 67.5 degrees

Prepon- dence	Field length/width ratio						
	1:1	2:1	4:1	8:1	10:1	12:1	16:1
1.0	1.03	1.46	1.70	1.85	1.88	1.90	1.95
1.2	1.03	1.49	1.80	1.94	1.98	2.00	2.04
1.4	1.03	1.52	1.90	2.03	2.07	2.08	2.12
1.6	1.03	1.55	1.98	2.13	2.15	2.16	2.20
1.8	1.03	1.58	2.08	2.23	2.25	2.26	2.30
2.0	1.04	1.62	2.17	2.35	2.36	2.37	2.40
2.2	1.05	1.65	2.27	2.48	2.49	2.49	2.50
2.4	1.06	1.68	2.37	2.61	2.61	2.61	2.61
2.6	1.06	1.71	2.42	2.71	2.71	2.71	2.71
2.8	1.07	1.72	2.44	2.77	2.77	2.77	2.77
3.0	1.07	1.73	2.45	2.82	2.82	2.82	2.82
3.2	1.07	1.74	2.46	2.85	2.85	2.85	2.85
3.4	1.08	1.75	2.47	2.87	2.87	2.87	2.87
3.6	1.08	1.75	2.48	2.89	2.89	2.89	2.89
3.8	1.08	1.76	2.48	2.90	2.90	2.90	2.90
4.0	1.08	1.76	2.49	2.91	2.91	2.91	2.91

See footnote at end of table.



**Table 502-8E** Wind erosion direction factor; angle of deviation <sup>1/</sup> = 90 degrees


Preponderance	Field length/width ratio						
	1:1	2:1	4:1	8:1	10:1	12:1	16:1
1.0	1.03	1.46	1.70	1.85	1.88	1.90	1.95
1.2	1.03	1.50	1.90	2.10	2.16	2.23	2.32
1.4	1.03	1.55	2.10	2.40	2.50	2.60	2.75
1.6	1.03	1.66	2.30	2.70	2.87	3.00	3.25
1.8	1.03	1.80	2.55	3.10	3.32	3.50	3.85
2.0	1.02	1.96	2.78	3.50	3.84	4.08	4.56
2.2	1.02	2.00	3.06	4.05	4.47	4.80	5.40
2.4	1.02	2.00	3.35	4.63	5.12	5.60	6.40
2.6	1.01	2.00	3.56	5.30	5.93	6.50	7.60
2.8	1.01	2.00	3.74	5.85	6.64	7.50	8.90
3.0	1.01	2.00	3.92	6.51	7.60	8.80	10.6
3.2	1.01	2.00	4.00	6.89	8.20	9.30	11.5
3.4	1.01	2.00	4.00	7.08	8.40	9.60	11.8
3.6	1.00	2.00	4.00	7.26	8.60	9.90	12.3
3.8	1.00	2.00	4.00	7.45	8.91	10.3	12.8
4.0	1.00	2.00	4.00	7.64	9.20	10.6	13.3

<sup>1/</sup> Angle of deviation is the difference between prevailing wind erosion direction and a line perpendicular to the long side of the field or strip (0 degrees is perpendicular to the long side). Multiply the Wind Erosion Direction Factor times the width of the field to determine L distance. For circular fields L = .915 times the diameter regardless of direction or preponderance.

### Index to flat small grain equivalent charts

Vegetation	Figure	Vegetation	Figure
Alfalfa	b-1	Needleandthread	d-1, 4, 8
Barley	a-1, 2	Oats	a-1, 2
Beans, dry	b-2	Peanuts	b-12, 13, 14
Beets, sugar	b-15	Potato	b-15
Big bluestem	d-1, 3, 4, 5	Range grasses and mixtures	d-1-8
Blue grama	d-1, 3, 4, 6, 7, 8	Rape	b-16
Buckwheat	b-5	Rye	a-1, 2
Buffalograss	d-1, 2, 4, 5, 7, 8	Safflower	b-17
Corn	a-3, 4, 5, 6	Sesame	b-12
Cotton	b-6, 7, 8, c-1	Sideoats grama	d-1, 4
Dry beans	b-2	Sorghum	a-4, 5, 6, 8
Flax	b-9	Soybeans	b-2, 3, 4
Guar	b-12	Sudan	a-9
Lentils	b-2	Sugarbeets	b-15
Little bluestem	d-1, 3, 4, 6	Sunflower	b-18
Manure	c-2	Switchgrass	d-3, 6
Millet	a-7	Turnip	b-10
Mint	b-10	Western wheatgrass	d-1, 2, 4, 5, 8
Mustard	b-11	Wheat	a-1, 2
		Winter peas	b-2


Figure	Chart	Figure	Chart
a-1	Small grain residue (use for wheat, barley, rye, and oats)	b-11	Mustard residue
a-2	Growing small grain	b-12	Peanut, guar, and sesame residue
a-3	Corn residue	b-13	Growing peanuts
a-4	Corn and grain sorghum silage stubble	b-14	Growing peanuts; days after emergence
a-5	Growing corn and grain sorghum	b-15	Potato or sugar beet residue
a-6	Growing corn and grain sorghum; days after emergence	b-16	Rape residue
a-7	Millet stubble and residue	b-17	Safflower residue
a-8	Grain sorghum and residue	b-18	Sunflower residue
a-9	Sudangrass stubble and residue	c-1	Cotton burs
b-1	Alfalfa residue	c-2	Manure
b-2	Dry bean, lentil, soybean, and winter pea residue	d-1	Overgrazed range mixtures
b-3	Growing soybeans	d-2	Overgrazed big bluestem, western wheatgrass, and buffalograss
b-5	Buckwheat residue	d-3	Overgrazed little bluestem, switchgrass, and blue grama
b-6	Cotton residue	d-4	Properly grazed range grass mixtures
b-7	Growing cotton	d-5	Properly grazed big bluestem, etc
b-8	Growing cotton; days after emergence	d-6	Properly grazed little bluestem, etc
b-9	Flax residue	d-7	Ungrazed blue grama and buffalograss
b-10	Reserved for turnip and mint residue)	d-8	Undergrazed western wheatgrass, needleandthread, blue grama, and buffalograss mixtures

**Figure a-1** Flat small grain equivalents of small grain residue (use for wheat, barley, rye, oats)

Reference condition: Dry small grain stalks 10 inches long, lying flat on the soil surface in 10-inch rows, rows perpendicular to wind direction, stalks oriented to wind direction. Residue is washed, air dried, and placed as described for the wind tunnel tests.

Source: Lyles and Allison— Trans. ASAE 1981, 24 (2): 405-408.

**Figure a-2** Flat small grain equivalents of growing small grain



Reference condition: Dry small grain stalks 10 inches long, lying flat on the soil surface in 10-inch rows, rows perpendicular to wind direction, stalks oriented to wind direction.


1/ Siddway, F.H., W.S. Chepil, and D.V. Armburst 1965.

2/ Estimates by best judgment of SCS personnel.

3/ Air-dry weights of growing winter wheat from emergence to winter dormancy.


4/ Crop growth, in days after emergence, from Central SD, 1996.

**Figure a-3** Flat small grain equivalents of corn residue



Source: Lyles and Allison, Transcript ASAE 1981, 24 (2): 405-408.


1/ Flat to 2,000 lbs, standing to 3,500 lbs. Extended by NRCS.

**Figure a-4** Flat small grain equivalents of corn and grain sorghum silage stubble

Source: Lyles and Allison— Trans. ASAE 1981, 24 (2): 405-408. Residue weights are washed, air dried, and placed as described for the wind tunnel tests.

1/ Field experience in the Northern Plains indicates the ratio of residue to grain is higher when crops, such as forage sorghum, are grown in narrow row seedings. Research is not available at this time to confirm this observation. Until research is available, the residue production values may be increased 30 percent when crops are planted in rows less than 20 inches apart. The line for standing forage sorghum 6.25 inches high with 10 inch rows includes an increase of 30 percent over the values for 30 inch rows.


**Figure a-5** Flat small grain equivalents of growing corn and grain sorghum



Source: Armburst and Lyles, 1984—unpublished.


<sup>1/</sup> Natural Resources Conservation Service data from Central South Dakota, 1996.

**Figure a-6** Flat small grain equivalents of growing corn and grain sorghum; days after emergence



Source: Armburst and Lyles, 1984—unpublished.




**Figure a-7** Flat small grain equivalents of millet stubble and residue

Reference condition: Dry small grain stalks 10 inches long, lying flat on the soil surface in 10-inch rows, rows perpendicular to wind direction, stalks oriented to wind direction.


Source: Leon Lyles— ARS memorandum, January 25, 1985.

**Figure a-8** Flat small grain equivalents of grain sorghum and residue



Source: Lyles and Allison— Trans. ASAE 1981, 24 (2): 405-408.


1/ Leafy residue estimates by NRCS North Central agronomists. (Flat to 2,500 lbs. standing stalks to 3,500 lbs.) November 1984.

**Figure a-9** Flat small grain equivalents of sudangrass stubble and residue

Reference condition: Dry small grain stalks 10 inches long, lying flat on the soil surface in 10-inch rows, rows perpendicular to wind direction, stalks oriented to wind direction.

Source: Leon Lyles, ARS, Memorandum, January 25, 1985.


**Figure b-1** Flat small grain equivalents of alfalfa residue



Reference condition: Dry small grain stalks 10 inches long, lying flat on the soil surface in 10-inch rows, rows perpendicular to wind direction, stalks oriented to wind direction.

Source: Unpublished coefficients provided by Leon Lyles, ARS, Wind Erosion Research Unit, Manhattan, Kansas.

1/ Data from central South Dakota, 1996


**Figure b-2** Flat small grain equivalents of dry bean, lentil, soybean,<sup>1/</sup> and winter pea residue

Reference condition: Dry small grain stalks 10 inches long, lying flat on the soil surface in 10-inch rows, rows perpendicular to wind direction, stalks oriented to wind direction.


Source: Best Judgment Estimates by NRCS, North Central Agronomists, November 1984.

1/ Soybeans—Lyles and Allison, Trans. ASAE. 1981, 24(2) 405-408.

**Figure b-3** Flat small grain equivalents of growing soybeans




Source: Amburst and Lyles, 1984—unpublished.

**Figure b-5** Flat small grain equivalents of buckwheat residue

Reference condition: Dry small grain stalks 10 inches long, lying flat on the soil surface in 10-inch rows, rows perpendicular to wind direction, stalks oriented to wind direction.

Source: Best judgment estimates by NRCS, North Central agronomists, November 1984.

**Figure b-6** Flat small grain equivalents of cotton residue




Reference condition: Dry small grain stalks 10 inches long, lying flat on the soil surface in 10-inch rows, rows perpendicular to wind direction, stalks oriented to wind direction.

Source: Lyles and Allison, Trans ASAE, 1981, 24(2): 405-408.

Residue weights are washed and dried, placed as described for wind tunnel test.




**Figure b-7** Flat small grain equivalents of growing cotton



Reference condition: Dry small grain stalks 10 inches long, lying flat on the soil surface in 10-inch rows, rows perpendicular to wind direction, stalks oriented to wind direction.


Source: Armburst and Lyles, 1984 — unpublished.

**Figure b-8** Flat small grain equivalents of growing cotton; days after emergence



Source: Armburst and Lyles, ARS, 1984 —unpublished.

**Figure b-9** Flat small grain equivalents of flax residue




Reference condition: Dry small grain stalks 10 inches long, lying flat on the soil surface in 10-inch rows, rows perpendicular to wind direction, stalks oriented to wind direction.

Source: Best judgment estimates by NRCS, North Central agronomists. November 1984.

**Figure b-10** Turnip and mint residue


**(Reserved)**

**Figure b-11** Flat small grain equivalents of mustard residue




Source: Best judgment estimates by NRCS West agronomists, 1983.

**Figure b-12** Flat small grain equivalents of peanuts, guar, and sesame residue



Source: Best judgment estimates by NRCS.


**Figure b-13** Flat small grain equivalents of growing peanuts



Reference condition: Dry small grain stalks 10 inches long lying flat on the soil surface in 10-inch rows, rows perpendicular to wind direction, stalks oriented to wind direction.


Source: Armburst and Lyles, 1984 — unpublished.

**Figure b-14** Flat small grain equivalents of growing peanuts; days after emergence



Source: Armbrust and Lyles, 1984 — unpublished.




**Figure b-15** Flat small grain equivalents of potato or sugar beet residue

Reference condition: Dry small grain stalks 10 inches long, lying flat on the soil surface in 10-inch rows, rows perpendicular to wind direction, stalks oriented to wind direction.


Source: Best judgment estimates by NRCS, North Central agronomists, November 1984.

**Figure b-16** Flat small grain equivalents of rape residue



Source: Lyles and Allison— Trans. ASAE 1981, 24 (2): 405-408.


Residue weights are washed, air dried, and placed as described.

**Figure b-17** Flat small grain equivalents of safflower residue

Reference condition: Dry small grain stalks 10 inches long, lying flat on the soil surface in 10-inch rows, rows perpendicular to wind direction, stalks oriented to wind direction.


Source: Best judgment estimates by NRCS, North Central agronomists, November 1984.

**Figure b-18** Flat small grain equivalents of sunflower residue




Source: Lyles and Allison, Trans. ASAE 1981, 24(2): 405-408.  
Residue wts. are washed, air dried, and placed as described for wind tunnel test.

**Figure c-1** Flat small grain equivalents of cotton burs




Source: Research by D.W. Fryear, ARS, Big Spring, Texas.

**Figure c-2** Flat small grain equivalents of manure



Source: Woodruff, N.P., L. Lyles, J.D. Dickerson, and D.V. Armbrust. 1974 Journal Soil and Water Conservation 19(3), pages 127-129.


**Figure d-1** Flat small grain equivalents of overgrazed range mixtures—big bluestem, little bluestem, sideoats grama, western wheatgrass, needleandthread, blue grama, and buffalograss



Reference condition: Dry small grain stalks 10 inches long, lying flat on the soil surface in 10-inch rows, rows perpendicular to wind direction, stalks oriented to wind direction.

Source: Lyles and Allison— 1980 Journal Range Management, 33(2), pages 143–146.

**Figure d-2** Flat small grain equivalents of overgrazed big bluestem, western wheatgrass, and buffalograss




Reference condition: Dry small grain stalks 10 inches long, lying flat on the soil surface in 10-inch rows, rows perpendicular to wind direction, stalks oriented to wind direction.

Source: Lyles and Allison— 1980 Journal Range Management, 33(2), pages 143–146.




**Figure d-3** Flat small grain equivalents of overgrazed little bluestem, switchgrass, and blue grama



Reference condition: Dry small grain stalks 10 inches long, lying flat on the soils surface in 10 inch rows perpendicular to wind direction, stalks oriented to wind direction.

Source: Lyles and Allison – 1980 Journal Range Management, 33(2), pages 143–146.


**Figure d-4** Flat small grain equivalents of properly grazed range grass mixture



Reference condition: Dry small grain stalks 10 inches long, lying flat on the soils surface in 10-inch rows perpendicular to wind direction, stalks oriented to wind direction.

Source: Lyles and Allison – 1980 Journal Range Management, 33(2), pages 143–146.


**Figure d-5** Flat small grain equivalents of properly grazed big bluestem, western wheatgrass, and buffalograss



Reference condition: Dry small grain stalks 10 inches long, lying flat on the soils surface in 10 inch rows perpendicular to wind direction, stalks oriented to wind direction.


Source: Lyles and Allison, 1980, Journal Range Management, 33(2), pages 143-146.

**Figure d-6** Flat small grain equivalents of properly grazed little bluestem, blue grama, and switchgrass



Reference condition: Dry small grain stalks 10 inches long, lying flat on the soils surface in 10 inch rows perpendicular to wind direction, stalks oriented to wind direction.


Source: Lyles and Allison, 1980, Journal Range Management, 33(2), pages 143–146.

**Figure d-7** Flat small grain equivalents of ungrazed blue grama and buffalograss

Reference condition: Dry small grain stalks 10 inches long, lying flat on the soils surface in 10 inch rows perpendicular to wind direction, stalks oriented to wind direction.

Source: Lyles and Allison, 1980, *Journal Range Management*, 33(2), pages 143–146.

**Figure d-8** Flat small grain equivalents of ungrazed western wheatgrass, needleandthread, blue grama, and buffalograss mixtures



Reference condition: Dry small grain stalks 10 inches long, lying flat on the soils surface in 10 inch rows perpendicular to wind direction, stalks oriented to wind direction.

Source: Lyles and Allison, 1980, Journal Range Management, 33(2), pages 143-146.



## Background

*Small grain equivalents* (SGe) expresses the effectiveness of residue or growing crops in resisting wind erosion, as compared with a reference condition. Agricultural Research Service has established benchmark SGe values for several common crops by wind tunnel testing. The research indicates that effectiveness of vegetative material is the result of vegetative roughness and is a function of residue weight, average stalk diameter, specific weight of stalk, orientation relative to the ground surface (standing or flat), and spatial distribution. Spatial distribution relates to plant population, row spacing, and row direction relative to windflow.

Conservation planners frequently need to estimate the effectiveness of vegetation or residue for which small grain equivalence has not been determined. In the absence of wind tunnel tests or predictive equations, it may be desirable for NRCS to develop interim *best judgment* SGe curves based on judgment and field experience as a basis for consistent estimates. This can be done with confidence when the relationships are understood. The general principles are:

- Standing residue is more effective than an equal weight of flat residue.
- Fine residue is more effective, pound for pound, than coarse residue.
- Given equal diameter and equal pounds per acre, residue that has low specific weight (density) is more effective than residue with high density.
- Rows perpendicular to wind are more effective than rows parallel to wind.
- Dense stands are more effective than thin stands.

Several of the SGe curve charts in exhibit 502–10 were developed using the procedure described below. The footnotes with each figure identify which curves are *best judgments* by NRCS and which are from published sources resulting from wind tunnel research by ARS. Interim curves developed using similar procedures are to be submitted to the national agronomist or to an NRCS Cooperating Scientist located at an ARS Research Unit, for technical review and approval for trial use.

## Procedure

1. Use only the SGe curves developed and published by ARS in exhibits 502–10, figures a–1 through d–8 as benchmark values.
2. Select one or more benchmark crops having physical characteristics similar to the crop in question. For purposes of comparison, give preference to SGe curves from published sources and minimize use of curves based on *best judgment* estimates.
3. Array the selected crop and the benchmark crops in order of apparent effectiveness on a pound-for-pound basis. Use comparative physical characteristics such as stalk diameter and density for guidance. If possible, *bracket* the crop in question between two benchmark crops.
4. By interpolation from benchmark curves, estimate and plot a curve for the crop in question. Estimate at least two SGe values, representing low and high levels of residue, to establish the slope of the curve.

Example (This procedure was used to develop the SGe curve for standing flax, figure b-9.):



---

## Crop

### Flax, standing stubble

Benchmark crops with similar characteristics—winter wheat; other similar crops that have curves available for comparison—millet.

Comparative characteristics and effectiveness: flax stubble (6-inch height) is assumed to be finer and denser than small grains and millet. Standing flax is assumed less effective than standing millet (4-inch height) because of stubble height that relates to thinner stands (pound for pound).

### Estimated small grain equivalents SGe value (by interpolation):

---

Pounds residue	SGe, Winter wheat (figure a-1)	SGe, Flax (estimated)	SGe, Millet (figure a-7)
200	750	480	360
500	1,800	1,200	850
2,000	7,000	4,400	3,200

---

### Additional note

Some predictive equations have been developed to estimate the SGe of vegetative material. To use these equations, diameter and specific weight must be known, as well as the amount and orientation of the material. Contact the state or national agronomist for assistance in using these procedures.

**Background**

When the wind tunnel is used to determine small grain equivalents of vegetative cover, the material tested is usually uniform in size, density, and orientation. Vegetative cover found in the field, however, frequently includes two or more components that are not alike. Common combinations are (1) part standing and part flat, (2) part coarse and part fine, or (3) part growing and part dead.

SGe values for mixed cover can be determined in the wind tunnel. However, there are too many possible combinations for development of practical field guides. When SGe conversion curves represent uniform components, the reference values can be combined to estimate SGe for any mixture of vegetative cover.

The following procedure is recommended for estimating SGe of mixed vegetative cover.

**Procedure**

1. Describe each major type of vegetative cover and estimate the percentage of total air-dry weight made up of each component.
2. Using the appropriate conversion curve, and total air-dry weight of all the vegetative cover, determine the SGe value of each component cover type.
3. Multiply the SGe value of each component by that component's percentage of total air-dry weight.
4. Add the products. The sum of the products is the weighted SGe for the mixed cover.

**Example crop:**

Winter wheat, 2,500 lb residue (air-dry weight) after harvest. 1,500 lb (60 percent) is standing stubble and 1,000 lb (40 percent) is flat randomly distributed straw.

Calculation:

Standing winter wheat:

$$2,500 \text{ lb} = 8,500 \text{ lb SGe} \times 0.60 = 5,100 \text{ lb}$$

Flat winter wheat:

$$2,500 \text{ lb} = 3,300 \text{ lb SGe} \times 0.40 = 1,320 \text{ lb}$$

Weighted average:

$$\text{SGe} = 6,420 \text{ lb}$$

### **Exhibit 502–13      Crop yield — residue conversions**

(This section reserved, to be developed)

### **Exhibit 502–14      Residue reduction by tillage**

(This section reserved, to be developed)

### **Exhibit 502–15      E Tables: Soil loss from wind erosion in tons per acre per year**

(Insert appropriate E tables for local values of the climatic factor, C)

### **Exhibit 502–16      Wind physics**

(This section reserved, to be developed)

### **Exhibit 502–17      Wind erosion control exhibits**

(This section reserved, to be developed)

## Subpart 502G References

- Alcorn, K. and M.W. Dodd. 1984. Windbreaks for conservation: an annotated bibliography. Pub. No. WB 84-01, Calif. Dept. Cons., Div. Land Resource Protection.
- Armbrust, D.V. 1972. Recovery and nutrient content of sandblasted soybean seedlings. *Agron. Jour.* 64:707-708.
- Armbrust, D.V. 1977. A review of mulches to control wind erosion. *Trans. Amer. Soc. Agr. Engin.* 20(5):904-905, 910.
- Armbrust, D.V. 1979. Wind- and sandblast-damage to tobacco plants at various growth stages. *Tobacco Sci. XXIII*:117-119, and *Tobacco International* 181(20):63-65.
- Armbrust, D.V. 1982. Physiological responses to wind and sandblast damage by grain sorghum plants. *Agron. Jour.* 74:133-135.
- Armbrust, D.V., W.S. Chepil, and F.H. Siddoway. 1964. Effects of ridges on erosion of soil by wind. *Soil Sci. Soc. of America Proc.* 28(4):557-560.
- Armbrust, D.V., and L. Lyles. 1985. Equivalent wind erosion protection from selected growing crops. *Agron. Jour.* 77(5):703-707.
- Armbrust, D.V., G.M. Paulsen, and R. Ellis, Jr. 1974. Physiological responses to wind- and sandblast-damaged winter wheat plants. *Agron. Jour.* 66:421-423.
- Bagnold, R.A. 1941. *The physics of blown sand and desert dunes.* Landon, Chapman, and Hall, 265 pp.
- Bondy, Earl, Leon Lyles, and W.A. Hayes. 1980. Computing soil erosion by periods using wind energy distribution. *Jour. Soil and Water Conserv.* 35(4):173-176.
- Chepil, W.S. 1945. Dynamics of wind erosion: I. Nature of movement of soil by wind. *Soil Science* 60:305-320.
- Chepil, W.S. 1945. Dynamics of wind erosion: II. Initiation of soil movement. *Soil Science* 60:397-411.
- Chepil, W.S. 1945. Dynamics of wind erosion: III. The transport capacity of the wind. *Soil Science* 60:475-480.
- Chepil, W.S. 1945. Dynamics of wind erosion: IV. The translocating and abrasive action of the wind. *Soil Science* 61:167-177.
- Chepil, W.S. 1946. Dynamics of wind erosion: V. Cumulative intensity of soil drifting across eroding fields. *Soil Science* 61(3):257-263.
- Chepil, W.S. 1946. Dynamics of wind erosion: VI. Sorting of soil material by the wind. *Soil Science* 61(4):331-340.
- Chepil, W.S. 1956. Permanent methods of wind erosion control. *The Kansas Crop Improvement Association Certified Seed Directory*, pp. 66-67.
- Chepil, W.S. 1957. Erosion of soil by wind. *1957 Yearbook of Agriculture (USDA)* pp. 308-314.
- Chepil, W.S. 1957. Sedimentary characteristics of dust storms: II. Visibility and dust concentration. *Amer. Jour. Sci.* 255:104-114.
- Chepil, W.S. 1957. Width of field strips to control wind erosion. *Kans. Agr. Expt. Sta. Tech. Bul.* 92.
- Chepil, W.S. 1958. Soil conditions that influence wind erosion. *USDA Tech. Bul. No.* 1185.
- Chepil, W.S. 1959. Estimations of wind erodibility of farm fields. *USDA, ARS, Prod. Res. Rpt. No.* 25.
- Chepil, W.S. 1959. Stripcropping for wind erosion control. *Soil Conservation Magazine* 24:153-156.
- Chepil, W.S. 1959. Wind erodibility of farm fields. *Jour. Soil and Water Conserv.* 14(5):214-219.
- Chepil, W.S. 1960. Conversion of relative field erodibility to annual soil loss by wind. *Soil Sci. Soc. of America Proc.* 24(2):143-145.

- Chepil, W.S. 1960. How to determine required width of field strips to control wind erosion. *Jour. Soil and Water Conserv.* 15:72-75.
- Chepil, W.S. 1962. Stubble mulching to control erosion. *Proceedings of the Great Plains Council Workshop on Stubble Mulch Farming, Lincoln, Nebraska, February 8-9, 1962.*
- Chepil, W.S. 1963. Climatic index of wind erosion conditions in the Great Plains. *Soil Sci. Soc. Amer. Proc.* 27(4):449-452.
- Chepil, W.S. 1963. The physics of wind erosion and its control. *Adv. in Agronomy* 15:211-302
- Chepil, W.S. 1964. In the Great Plains, prevailing wind erosion direction. *Jour. of Soil and Water Conser.* 19(2):67-70.
- Chepil, W.S. 1964. Wind erodibility of knolly terrain. *Jour. Soil and Water Conserv.* 19(5):179-181.
- Chepil, W.S., F.H. Siddoway, and D.V. Armbrust. 1962. Climatic Factor for estimating wind erodibility of farm fields. *Jour. Soil and Water Conserv.* 17(4):162-165.
- Chepil, W.S. and N.P. Woodruff. 1954. Estimations of wind erodibility of field surfaces. *Jour. Soil and Water Conserv.* 9:257-265, 285.
- Chepil, W.S., N.P. Woodruff, F.H. Siddoway, D.W. Fryrear, and D.V. Armbrust. 1963. Vegetative and nonvegetative materials to control wind and water erosion. *Soil Sci. Soc. Amer. Proc.* 27(1):86-89.
- Chepil, W.S., N.P. Woodruff, and A.W. Zingg. 1955. Field study of wind erosion in western Texas. USDA, SCS-TP-125.
- Cole, George W. 1984. A stochastic formulation of soil erosion caused by wind. *Trans. Amer. Soc. Agr. Engin.* 27(5):1405-1410.
- Cole, George W., L. Lyles, and L.J. Hagen. 1983. A simulation model of daily wind erosion soil loss. *Trans. Amer. Soc. Agr. Engin.* 26(6):1758-1765.
- Durar, A.A. 1991. Simulation of soil-water dynamics for wind erosion modeling. Ph.D. diss. Kansas State Univ., Manhattan, KS (Diss. Abstr. 91-28491).
- Durar, A.A., J.L. Steiner, S.R. Evett, and E.L. Skidmore. 1995. Measured and Simulated Surface Soil Drying.
- Downes, J.D., D.W. Fryrear, R.L. Wilson, and C.M. Sabota. 1977. Influence of wind erosion on growing plants. *Trans. Amer. Soc. Agr. Engin.* 20:885-889.
- Fisher, P.S. and E.L. Skidmore. 1970. WEROS: A FORTRAN IV program to solve the wind erosion equation. USDA, ARS 41-174, 13 pp.
- Fryrear, D.W. 1969. Reducing wind erosion in the southern Great Plains. *Tex. Agr. Expt. Sta., Misc. Publ.* 929, pp. 1-10. (Technical Report)
- Fryrear, D.W. 1971. Survival and growth of cotton plants damaged by windblown sand. *Agron. Jour.* 63(4):638-642.
- Fryrear, D.W. 1981. Tillage influences monthly wind erodibility of dryland sandy soils. *In Crop production with conservation tillage. Amer. Soc. Agr. Engin. Publ. #7-81, pp. 153-163.*
- Fryrear, D.W., D.V. Armbrust, and J.D. Downes. 1975. Plant response to wind-erosion damage. *Proc. 30<sup>th</sup> Annual Meeting of Soil Conserv. Soc. Amer., Aug. 10-13, 1975, San Antonio, Texas, pp. 144-146.*
- Fryrear, D.W., and J.D. Downes. 1975. Consider the plant in planning wind erosion control systems. *Trans. Amer. Soc. Agr. Engin.* 18:1070-1072.
- Fryrear, D.W., and P.T. Koshi. 1971. Conservation of sandy soils with a surface mulch. *Trans. Amer. Soc. Agr. Engin.* 14(3):492-495, 499.
- Fryrear, D.W., C.A. Krammes, D.L. Williamson, and T.M. Zobeck. 1994. Computing the wind erodible fraction of soils. *Jour. Soil and Water Cons.* 49(2):183-188.
- Fryrear, D.W., J. Stubbendieck, and W.G. McCully. 1973. Grass seedling response to wind and windblown sand. *Crop Sci.* 13(6):622-625.

- Hagen, L.J. 1976. Windbreak design for optimum wind erosion control. *In Proc. of the Symposium "Shelterbelts on the Great Plains,"* Great Plains Agr. Council Publ. No. 78, pp. 31-36.
- Hagen, L.J. 1991. A wind erosion prediction system to meet user needs. *Jour. Soil and Water Conserv.* 46(2):105-111.
- Hagen, L.J. 1995. Erosion submodel. *In Wind erosion prediction system technical description. Proc. of WEPP/WEPS Symposium, Soil and Water Conservation Society, Ankeny, IA.*
- Hagen, L.J. 1995. Wind erosion: emission rates and transport capacities on rough surfaces. *Amer. Soc. Agric. Engin. Paper No. 91-2082, St. Joseph, Michigan. (Society Proceedings)*
- Hagen, L.J. and D.V. Armbrust. 1992. Aerodynamic roughness and saltation trapping efficiency of tillage ridges. *Trans. Amer. Soc. Agric. Engin.* 35(5):1179-1184.
- Hagen, L.J., E.L. Skidmore, and J.D. Dickerson. 1972. Designing narrow strip barrier systems to control wind erosion. *Jour. Soil and Water Conserv.* 27(6):269-272.
- Hagen, L.J., E.L. Skidmore, P.L. Miller, and J.E. Kipp. 1981. Simulation of effect of wind barriers on air-flow. *Trans. Amer. Soc. Agr. Engin.* 24(4):1002-1008.
- Hagen, L.J., and N.P. Woodruff. 1975. Particulate loads caused by wind erosion in the Great Plains. *APCA Jour.* 25(8):860-861.
- Lyles, L. 1980. The U.S. wind erosion problem. *Amer. Soc. Agr. Engin. Publication 7-81, Proc. of the ASAE Conf. on Crop Production with Conservation in the 80s, December 1-2, 1980, Chicago, Illinois, pp. 16-24.*
- Lyles, L. 1981. Equivalent wind-erosion protection from selected crop residues. *Trans. Amer. Soc. Agr. Engin.* 24(2):405-408.
- Lyles, L. 1983. Erosive wind energy distributions and climatic factors for the West. *Jour. Soil and Water Conserv.* 38(2):106-109.
- Lyles, L. 1983. Improved wind erosion prediction. Paper presented at 1984 ARS Erosion Workshop, Purdue University, West Lafayette, Indiana, November 1983.
- Lyles, L. 1985. Predicting and controlling wind erosion. *Agric. History* 59(2):205-214.
- Lyles, L. and Bruce E. Allison. 1980. Range grasses and their small grain equivalents for wind erosion control. *Jour. Range Mgmt.* 33(2):143-146.
- Lyles, L. and R.K. Krauss. 1971. Threshold velocities and initial particle motion as influenced by air turbulence. *Trans. Amer. Soc. Agr. Engin.* 14(3):563-566.
- Lyles, L. and N.P. Swanson. 1976. Advances in wind and water erosion control. *Proc. of Conservation Tillage Workshop, August 10-12, 1976, Fort Collins, Colorado. Great Plains Agr. Council Publ. No. 77, pp. 13-32.*
- Lyles, L., and J. Tatarko. 1982. Emergency tillage to control wind erosion: Influences on winter wheat yields. *Jour. Soil and Water Conserv.* 37(6):344-347.
- Lyles, L., and N.P. Woodruff. 1960. Abrasive action of windblown soil on plant seedlings. *Agron. Jour.* 52:533-536.
- Lyles, L., N.F. Schmeidler, and N.P. Woodruff. 1973. Stubble requirements in field strips to trap windblown soil. *Kans. Agr. Expt. Sta. Res. Pub.* 164, 22 pp.
- Mech, S.J., and N.P. Woodruff. 1967. Wind erosion on irrigated lands. *Agron. Monograph No. 11, Irrigation of Agricultural Lands, American Soc. of Agron., 964-973.*
- Niles, J.S. 1961. A universal equation for measuring wind erosion. *Agricultural Research Service Special Report* 22-69.
- Precheur, R., J.K. Greig, and D.V. Armbrust. 1978. The effects of wind and wind-plus-sand on tomato plants (*Lycopersicon esculentum* L.). *Jour. Amer. Soc. Hort. Sci.* 103(3):351-355.

- Renard, K.G., G.R. Foster, G.S. Weesies, D.K. McCool, and D.C. Yoder, coordinators. 1997. Predicting Soil Erosion by Water: A Guide To Conservation Planning With the Revised Universal Soil Loss Equation (RUSLE). U.S. Department of Agriculture, Agriculture Handbook 703, 404 pp.
- Siddoway, F.H., W.S. Chepil, and D.V. Armbrust. 1965. Effect of kind, amount, and placement of residue on wind erosion control. *Trans. Amer. Soc. Agr. Engin.* 8(3):327-331.
- Skidmore, E.L. 1965. Assessing wind erosion forces: directions and relative magnitudes. *Soil Sci. Soc. Amer. Proc.* 29(5):587-590.
- Skidmore, E.L. 1966. Wind and sandblast injury to seedling green beans. *Agron. Jour.* 58:311-315.
- Skidmore, E.L. 1976. A wind erosion equation: development, application, and limitations. *In ERDA Symposium Series 38, Atmosphere- Surface Exchange of Particulate and Gaseous Pollutants (1974)*, pp. 452-465.
- Skidmore, E.L. 1983. Wind erosion calculator: revision of residue table. *Jour. Soil and Water Conserv.* 38(2):110-112.
- Skidmore, E.L. 1984. Wind climatic erosivity. Paper presented at ASA meeting, Las Vegas, Nevada.
- Skidmore, E.L. 1987. Wind erosion direction factors as influenced by field shape and wind preponderance. *Soil Sci. Soc. of America Jour.* 51(1):198-202.
- Skidmore, E.L., and L. Dahl. 1978. Surface Soil Drying: Simulation Experiment. Abstracts for commission papers, 11<sup>th</sup> Congress. *Int. Soc. Soil Sci.*, Edmonton, AB. 19-27 June 1978.
- Skidmore, E.L., and L.J. Hagen. 1977. Reducing wind erosion with barriers. *Trans. Amer. Soc. Agr. Engin.* 20(5):911-915.
- Skidmore, E.L., and N.P. Woodruff. 1968. Wind erosion forces in the United States and their use in predicting soil loss. USDA, Agricultural Research Service, Agriculture Handbook No. 346 42 pp.
- Skidmore, E.L., P.S. Fisher, and N.P. Woodruff. 1970. Wind erosion equation: computer solution and application. *Soil Sci. Soc. Amer. Proc.* 34(5):931-935.
- Skidmore, E.L., M. Kumar, and W.E. Larson. 1979. Crop residue management for wind erosion control in the Great Plains. *Jour. Soil and Water Conserv.* 34(2):90-96.
- Stallings, J.H. 1951. Mechanics of wind erosion, USDA, Soil Conservation Service; SCS-TP-108.
- Stoeckeler, J.H. 1962. Shelterbelt influence on Great Plains field environment and crops: a guide for determining design and orientation. USDA, Forest Service, Production Research Report No. 62.
- Sweeney, Tim A. 1984. Wind erosion estimator for Colorado. USDA, Soil Conservation Service.
- Thorntwaite, C.W. 1931. Climates of North America according to a new classification. *Geog. Review* 21:633-655.
- van Eimern, J. 1961. Effects of windbreaks and shelterbelts. Report of Working Group of Commission for Agricultural Meteorology, World Meteorological Organization, Geneva, Switzerland.
- Wagner, L.E., and Hagen, L.J. 1992. Relationship between shelter angle and surface roughness and cumulative sheltered storage depth. *In J. Karacsony and G. Szalai (eds.) Proc. of the International Wind Erosion Workshop of CIGR Budapest, Hungary, v. Section I, 10 pp. (Conference Proceedings)*
- Williams, C.L. 1983. Procedure for adjusting the climatic factor for applying the wind erosion equation on irrigated land. USDA, Soil Conservation Service.
- Williams, J.R. and K.G. Renard. 1983. Assessments of soil erosion and crop productivity with process models (EPIC). Unpublished draft.
- Woodruff, N.P. 1975. Wind erosion research—past, present, and future. *Proc. of 30<sup>th</sup> Annual Meeting of Soil Conserv. Soc. Amer.*, August 10-13, 1975, San Antonio, Texas, pp. 147-152.

- 
- Woodruff, N.P., and D.V. Armbrust. 1968. A monthly climatic factor for the wind erosion equation. *Jour. Soil and Water Conserv.* 23(3):103-104.
- Woodruff, N.P., and F.H. Siddoway. 1965. A wind erosion equation. *Soil Sci. Soc. Amer. Proc.* 29(5):602-608.
- Woodruff, N.P., and F.H. Siddoway. 1973. Wind erosion control. *Proc. of the National Conservation Tillage Conference, Des Moines, Iowa, March 28-30, 1973*, pp. 156-162.
- Woodruff, N.P., and W.S. Chepil. 1956. Implements for wind erosion control. *Agr. Engin.* 37:751-754, 758.
- Woodruff, N.P., L. Lyles, J.D. Dickerson, and D.V. Armbrust. 1974. Using cattle feedlot manure to control wind erosion. *Jour. Soil and Water Conserv.* 29(3):127-129.
- Woodruff, N.P., L. Lyles, F.H. Siddoway, and D.W. Fryrear. 1972. How to control wind erosion. USDA, Agricultural Research Service, *Agr. Inf. Bul. No. 354*, 22 pp.
- Woodruff, N.P., J.D. Dickerson, E.E. Banbury, A.B. Erhart, and M.C. Lundquist. 1976. Selected trees and shrubs evaluated for single-row windbreaks in the Central Great Plains. USDA, ARS-NC-37, 15 pp.
- Zingg, A.W., and N.P. Woodruff. 1951. Calibration of a portable wind tunnel for the simple determination of roughness and drag on field surfaces. *Agron. Jour.* 43:191-193.



Contents:

<b>Subpart 503A</b>	<b>Crop rotation</b>	<b>503-1</b>
503.00	Definition .....	503-1
503.01	Benefits of crop rotations .....	503-1
<b>Subpart 503B</b>	<b>Tillage systems</b>	<b>503-2</b>
503.10	Introduction .....	503-2
503.11	Conservation tillage .....	503-2
<b>Subpart 503C</b>	<b>Nutrient management (Under development)</b>	<b>503-5</b>
<b>Subpart 503D</b>	<b>Pest management (Under development)</b>	<b>503-5</b>
<b>Subpart 503E</b>	<b>Crop residue</b>	<b>503-6</b>
503.40	Benefits of managing crop residue .....	503-6
503.41	Crop residue production (Under development) .....	503-6
503.42	Crop residue retention (Under development) .....	503-6
503.43	Estimating crop residue cover .....	503-6
503.44	Determining the weight of standing vegetative cover .....	503-7
<b>Subpart 503F</b>	<b>References</b>	<b>503-8</b>

<b>Figures</b>	<b>Figure 503-1</b>	Acceptable orientations for residue measurement lines	<b>503-6</b>
	<b>Figure 503-2</b>	Counting residue pieces along a line transect	<b>503-7</b>

<b>Exhibits</b>	<b>Exhibit 503-1</b>	Example worksheet for recording crop residue measurement	<b>503-8</b>
	<b>Exhibit 503-2</b>	Example worksheet for recording crop residue measurement	<b>503-9</b>



## Subpart 503A Crop rotation

### 503.00 Definition

A crop rotation is a sequence of different crops grown in a recurrent sequence over a given number of years. In some rotations a crop may occupy the land two years in succession. Crop rotations can vary in one or more of the following ways (Beck 1990):

- Plant family – grass vs. broadleaf
- Life cycle – annual vs. biennial vs. perennial
- Season of growth – winter annual vs. spring/summer annual
- Rooting depth – shallow vs. moderate vs. deep
- Residue production – light vs. heavy
- Residue type – fragile vs. non-fragile
- Water use efficiency – high vs. low

To realize the greatest benefits, a crop rotation should not have the same annual crop grown 2 years in succession and should alternate plant families. This minimizes the potential for build-up and carryover of insect and disease populations, and maintains some degree of diversity in the cropping system.

### 503.01 Benefits of crop rotations

Properly designed crop rotations provide many benefits, and give producers more management options for their cropping systems. Conservation planners, when working with producers to develop a conservation management system, should emphasize the importance of maintaining the planned sequence of crops in the rotation. The benefits that accrue from the rotation, such as erosion reduction and pest management, depend on the crops being grown in the designated order. Crop rotations can help address the following resource concerns:

**Pest management** — Rotations can reduce the incidence and severity of weeds, insects, and diseases in a cropping system. When a different crop is grown each year, a different host crop is present that is usually not compatible with pest problems that may have carried over from the previous year. Because of this, the levels of any given pest are kept at levels that make them easier to manage. A crop rotation allows the use of different management strategies for pest problems. Herbicides and insecticides with differing modes of action can be used, reducing the possibility that some

species will become resistant to chemical control. Different crops each year may allow tillage to be used to control pests, further reducing the need for chemical controls (Sprague and Triplett 1986).

**Erosion control** — Cropping systems that consist of continuous row crops and excessive tillage have a higher potential for wind or water erosion than rotations that include closely-spaced row crops or perennial crops. Different crops have different growth and development periods so that one crop may provide protection from erosive forces during a period of the year that another may not. Closely-spaced row crops, such as small grains or narrow-row soybeans, or perennial crops provide more canopy and surface cover than wide-row crops and reduce the potential for erosion.

**Surface residue** — Surface residue is one of the most effective erosion reduction measures available. High residue-producing crops following low residue-producing crops help maintain higher levels of crop residue on the soil surface. Residue management practices, such as mulch tillage or no-till, can help maximize the amount of crop residue on the soil surface during critical erosion periods.

**Soil quality** — Cropping sequences that include hay or pasture crops in rotation produce greater soil aggregate stability than systems that have continuous grain crops. In systems that have all grain crops, greater aggregate stability occurs with crops that produce higher amounts of residue. For example, rotations that alternate sorghum with soybeans result in greater organic carbon levels in the soil than with continuous soybeans (Unger 1994).

**Nutrient management** — Crop rotations that have forage legumes or legume cover crops preceding grain crops can reduce the need for nitrogen (N) fertilizer for the grain crop. Average corn yields of 160 bushels per acre have been obtained with corn following alfalfa (Triplett et al. 1979). Leguminous cover crops can provide an estimated 60 to 70 pounds of N per acre (Hargrove 1986). Small grain crops following legumes can scavenge the nitrogen fixed by the legume, reducing the potential for N losses by leaching.

**Water management** — Dryland cropping systems can take advantage of stored soil moisture by alternating shallow and deep-rooted crops. For example, many areas in the Great Plains alternate winter wheat, a shallow-rooted crop, with safflower, a deep-rooted crop.

***Livestock feed production*** – For livestock operations, crop rotations that include hay and pasture can provide a major portion, and in some cases, all of the livestock forage and feed. Additional information on planning crop rotations for livestock operations is in the National Range and Pasture Handbook, chapter 5, section 2.

## Subpart 503B Tillage systems

### 503.10 Introduction

The tillage system is an integral part of the cropping management system for a farm. The type, number, and timing of tillage operations have a profound effect on soil, water and air quality. Tillage systems vary widely depending on the crops, climate, and soils. The impacts of tillage on crop residue vary greatly depending on implements used, implement adjustments and the number of tillage trips. NRCS planners should be familiar with the tillage systems in their area, and how the application of these systems affects the resources.

### 503.11 Conservation tillage

Conservation tillage as defined by the Conservation Technology Information Center is any tillage and planting system with 30 percent or more residue cover remaining on the soil surface after planting to reduce soil erosion by water. Where soil erosion by wind is the primary concern, at least 1,000 pounds per acre of flat small-grain residue equivalent are left on the soil surface during the critical wind erosion period.

#### (a) Residue management practices

Residue management practices that typically meet the conservation tillage definition include:

***No-till and strip-till*** — No-till and strip-till systems manage the amount, orientation, and distribution of crop and other plant residues on the soil surface year-round, while growing crops in narrow slots, or tilled or residue-free strips in soil previously untilled by full-width inversion implements. The soil is left undisturbed from harvest to planting except for nutrient injection. Seeds are placed in a narrow seedbed or slot made by coulter(s), row cleaners, disk openers, in-row chisels, or rototillers, where no more than one third of the row width is disturbed. Weeds are controlled primarily with herbicides. Row cultivation for emergency weed control should utilize undercutting implements that minimize residue burial.

***Ridge-till*** — Managing the amount, orientation, and distribution of crop and other plant residues on the soil surface year-round, while growing crops on preformed ridges alternated with furrows protected by crop residue. The soil is

left undisturbed from harvest to planting except for nutrient injection. Planting is done in a seedbed prepared on ridges with sweeps, disk openers, coulters, or row cleaners. Residue is left on the surface between ridges. Weed control is done with herbicides or cultivation or both. Ridges are rebuilt during row cultivation.

**Mulch-till** — Managing the amount, orientation, and distribution of crop and other plant residue on the soil surface year-round, while growing crops where the entire field surface is tilled prior to planting. Tillage tools such as chisels, field cultivators, disks, sweeps, or blades are used. Weed control is done with herbicides or cultivation, or both.

## (b) Crop residue management

Despite considerable acceptance of these definitions there is still some confusion as to the meaning of conservation tillage. Crop residue management is defined as:

Any tillage and planting system that uses no-till, ridge-till, mulch-till, or other systems designed to retain all or a portion of the previous crop's residue on the soil surface. The amount required depends on other conservation practices applied to the field and the farmer's objectives.

Tillage systems, whether a conservation tillage system or some other system that retains little if any residue, is an important part of a crop production system. Crop response to various tillage systems is variable and the variability is often difficult to explain because so many aspects of crop production are influenced by tillage. In addition, weather variability is an additional factor which influences crop production from one year to the next. Items to consider in designing a conservation tillage system include the following:

**Soil temperature** — Crop residue insulates the soil surface from the sun's energy. This may be a plus at planting time or may delay planting and/or lead to poorer germination. If this is a concern, the use of planter attachments to remove residue from the row area will improve the situation. Later in the growing season crop residue on the soil surface may lower the soil temperature, resulting in increased crop growth and yield.

**Allelopathy** — This refers to toxic effects on a crop because of decaying residue from the same crop or closely related crop. Crop rotation can eliminate this problem. The use of planter attachments to remove the residue from the row area may reduce the problem.

Allelopathic effects can also be beneficial by reducing competition from some weeds.

**Moisture** — When crop residue is on the soil surface, evaporation is reduced and water infiltration is increased. Although this may be a disadvantage at planting time in some areas, the extra soil moisture may increase yields if a dry period is encountered later in the growing season. No-till systems often have more water than conventional systems available for transpiration later in the growing season, resulting in increased yields.

**Organic matter** — Soil organic matter tends to stabilize at a certain level for a specific tillage and cropping system. Each tillage pass aerates the soil, resulting in the oxidation of decaying residues and organic matter. Crop residue left on the soil surface, in no-till or ridge-till systems, decomposes slower, resulting in increased organic matter levels in the upper few inches.

**Soil density** — All tillage systems have some effect on soil density. Systems that disturb the plow layer by inversion tillage or mixing and stirring temporarily decrease soil density. However, after the soil is loosened by tillage, the density gradually increases due to wetting and drying, wheel traffic, and secondary tillage operations. By harvest the soil density has returned to almost the same density as before tillage operations started. Cropping management systems that use several tillage operations can create a compacted layer at the bottom of the plow layer. If the compaction is excessive, then drainage is impeded, plant root growth is restricted, there is reduced soil aeration, herbicide injury may increase, and nutrient uptake may be restricted.

No-till systems have a higher soil density at planting time than other systems because the plow layer is not disturbed to form a seedbed. This higher density seldom has any effect on germination, emergence and subsequent crop growth. Many times the crop will benefit from this because these soils retain more available moisture.

**Stand establishment** — Regardless of tillage system uniform planting depth, good seed to soil contact, and proper seed coverage is needed to obtain a good stand. Coulters and/or row cleaners may be needed to ensure a good stand in a no-till system. In addition, extra weight and heavy-duty down-pressure springs may be needed for the planter or drill to penetrate undisturbed soil, especially under less than ideal moisture conditions.

**Fertilizer placement** — Starter fertilizer (nitrogen and phosphorus) is generally recommended to help overcome the affects of lower soil temperatures at planting time. If fertility levels (P, K, and pH) are at maintenance levels before switching to a conservation tillage system, fertility should not be a problem. In a no-till system surface application of phosphorus and lime will result in stratification of these nutrients, but this has not shown to affect crop yield. It is generally recommended that nitrogen be knifed into the soil in a no-till system, or a nitrogen stabilizer be used. Surface-applied nitrogen may volatilize and be lost if a rain does not move the nitrogen into the soil profile shortly after application.

**Weed control** — Controlling weeds is essential for profitable production systems. With less tillage, herbicides and crop rotations become more important in obtaining adequate weed control. Weed identification, herbicide selection, application rate, and timing are important. A burn-down may be needed in no-till and ridge-till systems. A change in weed species can be expected in no-till and ridge-till systems. Perennials may become more evident but usually can be controlled with good management. The combination of post-applied herbicides and bioengineered crops has made weed control much easier, even in a no-till system.

**Insect management** — Regardless of tillage system, effective insect-management guidelines and tactics are available. Different tillage systems may affect *potential* insect pressure, but management addresses this.

**Disease control** — Residue on the soil surface offers the potential for increased disease problems. However, there are numerous strategies to overcome this problem. Crop rotation or the selection of disease-resistant hybrids may nullify this *potential* problem.

**Crop yields** — Weather has more affect on crop yields than the tillage system. Crop yields generally are better when a crop rotation is utilized, especially in no-till system.

**Production costs** — All of the related costs associated with various tillage systems must be analyzed to evaluate the profitability.

**Machinery and labor costs** — Total cost for machinery and labor per acre usually decrease as the amount of tillage is reduced. If the size of the power units can be decreased (no-till system) then the savings can be even more dramatic.

No-till equipment (planters, drills, nutrient injection equipment) may be more expensive than that needed for conventional equipment. No-till producers have been able to farm more acres than conventional tillage producers without additional labor because of the increased efficiency.

---

---

**Subpart 503C Nutrient  
management**

(Under development)

---

---

**Subpart 503D Pest management**

(Under development)

## Subpart 503E Crop residue

### 503.40 Benefits of managing crop residue

Crop residue management is paramount to improving soil health. Without residue left on or only partially incorporated in the soil surface, there will be continued degradation of soil organic matter levels and soil health will not be maximized. Lower soil organic matter leads to lower cation exchange capacity, lower pH, lower water holding capacity, greater susceptibility to soil erosion, and poorer soil structure. Poor soil structure results in less pore space, decreased infiltration, and increased surface runoff.

Soil organic matter is an extremely important component of a productive soil. Because organic matter has many exchange sites it is capable of buffering many soil reactions. For example, by holding hydrogen ions, their content is reduced in soil solution that results in less soil acidity. At a pH near neutral (pH 7.0), plant nutrients are most available. In addition, organic matter increases soil aggregate stability and thereby reduces detachment by falling raindrops and surface runoff. Declining levels of soil organic matter over time is a strong indicator of declining soil health.

Research in Morris, Minnesota, (Riecosky 1995) reported that as much carbon (C) was lost to the atmosphere as CO<sub>2</sub> in just 19 days after moldboard plowing wheat residue as was produced by the crop. Carbon is the key component of soil organic matter and serves as an energy source for microbial activity.

Tillage stirs the soil similar to *poking a fire* that results in more rapid loss of carbon. Therefore, the primary reason organic matter levels of continuous cultivated soils have declined to less than half of their original level is directly related to tillage and the resulting loss of carbon to the atmosphere. To increase organic matter levels of the soil, crops that produce large amounts of residue should be grown with a significant reduction in tillage. Undisturbed root systems are the main contributor to increased soil carbon levels.

### 503.41 Crop residue production

(Under development)

### 503.42 Crop residue retention

(Under development)

### 503.43 Estimating crop residue cover

**The line transect method** — The line transect method has been proven effective in estimating the percent of the ground surface covered by plant residue at any time during the year.


Estimates of percent cover are used for determining the impact of residue on sheet and rill erosion. They cannot be used directly for determining the impact of residue on wind erosion.

Estimates of percent cover obtained using the line transect method to evaluate the impact of residue on sheet and rill erosion are most accurate when the residue is lying flat on the soil surface and is evenly distributed across the field.

The following is the recommended procedure for using the line transect method:

1. Use a commercially available 50- or 100-foot long cable, tape measure, or any other line that has 100 equally spaced beads, knots, or other gradations (marks) at which to sight.
2. Select an area that is representative of the field as a whole and stretch the line out across the crop rows. The line may be oriented perpendicular to the rows, or in a direction that is at least 45 degrees off the row direction (fig. 503–1).

**Figure 503–1** Acceptable orientations for residue measurement lines





The locations in the field where the line is stretched out to make measurements should be selected randomly from among the areas of the field that are typical of the entire field. End rows, field borders, and parts of the field that appear different are probably not typical of the entire field and should be avoided.

- Walk along the line, stopping at each mark. Position the eye directly over the mark, and look down at it. When sighting, do not look at the entire mark. Rather look at a single point on each mark.

A point has an area about like the end of a needle. On commonly used equipment, the knots, beads, or gradations have much larger areas than the end of a needle. A measurement is not based on whether or not some portion of a mark is over the residue. It is based on whether or not a specific point associated with the mark is over residue.

If using a commercially available beaded line, one way to accomplish the above is to select as the point of reference the place along the line where a bead begins.

- Determine the percent residue cover by counting the number of points at each mark along the line under which residue is seen. Count only from one side of the line for the single, selected point count at each mark. Do not move the line while counting.

Count only that residue that is large enough to intercept raindrops. A rule of thumb is to count only residue that is 3/32 inch in diameter or larger (fig. 503-2). When using a line with 100 points, the percent residue cover is equal to the number of points under which residue is seen.

- Three to five transects should be done in each field, using the procedure described in steps 1 through 4. Five transects are recommended.

With five measurements, estimates of percent residue cover are accurate to within  $\pm 15$  percent of the mean. Three measurements will give estimates accurate to within  $\pm 32$  percent of the mean.

For example, if the mean of five measurements was 50 percent cover, you could be confident (at the 95% confidence level) that the true mean was between 42 percent and 57 percent cover. For a 30 percent cover average based on five measurements, you could be confident that the true value was between 25 percent and 34 percent cover.

- The documentation of individual transects and computations made to determine average percent residue amounts should be done in a professional manner.

Documentation should be done in a way that permits easy tracking from the field measurements to the final answer.


The development and use of a documentation worksheet is recommended. Example worksheet formats are illustrated at the end of this section.

**Converting pounds of residue to percent cover**—For some applications, the weight of the crop residue needs to be known rather than the percent cover. Figure 503-3 illustrates the relationship between residue weight and percent residue cover for various crops. It also illustrates the procedure for estimating the amount of surface cover provided by a known weight of residue.

#### 503.44 Determining the weight of standing vegetative cover

In many instances, the amount of above-ground biomass needs to be known. The procedures for estimating and measuring the weight of standing vegetation are given in the National Range and Pasture Handbook, Part 600.0401(c).


**Figure 503-2** Counting residue pieces along a line transect



## Subpart 503F References

- Beck, D.L., 1990. Rotational systems: The key to successful no-till. Unpublished paper.
- Hargrove, W.L. 1986. Winter legumes as a nitrogen source for no-till grain sorghum. *Agron. J.* 78: 70.
- Laflen, J.M., M. Amenlya, and E.A. Hintz, 1981. Measuring crop residue cover, *Jour. of Soil and Water Conservation*, Vol. 36, No. 6, pp. 341-343.
- Reicosky, D.C., and M.J. Lindstrom. 1995. Fall tillage method: Effect on short-term carbon dioxide flux from soil. *Agron. J.* 85(6) 1237-1243.
- Richards, B.K., M.F. Walter, and R.E. Muck, 1984. Variation in line transect measurements of crop residue cover, *Jour. of Soil and Water Conservation*, Vol. 39, No. 1, pp. 60-61.
- Sprague, Milton A., and G.B. Triplett, Eds. 1986. No-tillage and surface-tillage agriculture. John A. Wiley & Sons, New York.
- Triplett, G.B., Jr., F. Haghiri, and D.M. Van Doren., Jr. 1979. Plowing effects on corn yield response to nitrogen following alfalfa. *Agron. J.* 71:801 – 803.
- Unger, P.W., Ed., 1994. Managing agricultural residues. Lewis Publishers, Boca Raton, FL.
- U.S. Department of Agriculture. 1997. National Range and Pasture Handbook, Natural Resources Conservation Service.

**Figure 503-3** Relationship of residue weight to percent residue cover for various crops. Dashed lines with arrows illustrate the procedure to convert residue weight to percent residue cover.



<b>Crop residue measurement worksheet</b> (for use with the line transect method)			
State _____		County _____	
Land user _____		Opid _____	Tract _____
Field no. _____ Planned residue level _____ percent Residue type _____			
Transect number	Total number of points <sup>1/</sup>	Number of points with residue <sup>2/</sup>	Percent residue this transect
1			
2			
3			
4			
5			
Average percent residue for field			

<b>Crop residue measurement worksheet</b> (for use with the line transect method)			
Field no. _____		Planned residue level _____ percent Residue type _____	
Transect number	Total number of points <sup>1/</sup>	Number of points with residue <sup>2/</sup>	Percent residue this transect
1			
2			
3			
4			
5			
Average percent residue for field			

1/ To achieve the degree of accuracy quoted in the NAM-recommended procedure for using the line transect method, each transect must be based on looking at a total of at least 100 points.  
 2/ Attach a map or sketch showing the location of each line transect within the field. All measurements shall be made using the line transect procedure contained in the National Agronomy Manual.

\_\_\_\_\_

Data collectorTitleDate

**Exhibit 503-2**

**Example worksheet for recording crop residue measurement**

**Crop residue measurement worksheet**  
(for use with the line transect method)

State _____	County _____	
Land user _____	Opid _____	Tract _____

Field no. \_\_\_\_\_ Planned residue level \_\_\_\_\_ percent Residue type \_\_\_\_\_

Field no.	crop	Residue kind	Planned amount	Planned tillage system

Residue field measurements <sup>1/ 2/</sup>

Field no.	Transect number (record number of counts with residue)					Average residue for field
	1	2	3	4	5	

1/ To achieve the degree of accuracy quoted in the NAM-recommended procedure for using the line transect method, each transect must be based on looking at a total of at least 100 points.  
2/ Attach a map or sketch showing the location of each line transect within the field. All measurements shall be made using the line transect procedure contained in the National Agronomy Manual.

\_\_\_\_\_ Title \_\_\_\_\_ Date \_\_\_\_\_  
Data collector

---

<b>Contents:</b>	<b>Subpart 504A</b>	<b>Managing soil moisture on nonirrigated lands</b>	504-1
	504.00	Soil moisture management overview .....	504-1
	504.01	Soil characteristics .....	504-1
	504.02	Crop characteristics .....	504-6
	504.03	Methods for determining crop evapotranspiration .....	504-7
	504.04	Tillage systems effect on water conservation .....	504-11
	504.05	Saline seeps .....	504-17
	<b>Subpart 504B</b>	<b>References</b>	504-20

---

---

<b>Figures</b>	<b>Figure 504-1</b>	The USDA textural triangle describes the proportions of sand, silt, and clay in the basic textural classes	504-1
	<b>Figure 504-2</b>	Relationship of soil moisture content and water availability to crops	504-3

---

<b>Tables</b>	<b>Table 504-1</b> Available Water Capacity (AWC) by soil texture	504-4
	<b>Table 504-2</b> Available water capacity adjustments because of salinity 1/	504-6
	<b>Table 504-3</b> Critical periods for plant moisture stress	504-9
	<b>Table 504-4</b> Depth to which roots of mature crops will extract available water from a deep, uniform, well-drained soil under average unrestricted conditions (depths shown are for 80% of the roots)	504-11
	<b>Table 504-5</b> Maximum rooting depth of mature crops seeded on fallow from 1976 to 1979 at Fort Benton, MT	504-11
	<b>Table 504-6</b> Effect of tillage and corn residue on infiltration using simulated rainfall	504-13
	<b>Table 504-7</b> Net soil-water gain at the end of fallow as influenced by straw mulch rates at four Great Plains locations	504-14
	<b>Table 504-8</b> Water use efficiency of 3-year no-till cropping systems and continuous spring wheat as compared with no-till spring wheat and winter wheat-fallow systems at various locations across the Great Plains	504-16
	<b>Table 504-9</b> Salt tolerance of selected crops	504-18

## Subpart 504A Managing soil moisture on nonirrigated lands

### 504.00 Soil moisture management overview

Soil moisture management in dryland agriculture is an integral factor in producing a viable crop production system. Climatic factors, crop selection, rotational influences, tillage system as well as inherent soil characteristics all interrelate in assessing the availability of adequate water necessary for a selected crop rotation.

### 504.01 Soil characteristics

Physical soil characteristics have a major impact on the infiltration, movement, and storage of water within the soil profile. These characteristics include soil texture, bulk density, structure, pore space, organic matter content, salinity, and sodicity as well as other inherent soil characteristics.

#### (a) Water infiltration

Water infiltration is the process of water entering the soil from the soil surface. Infiltration rates are affected by tillage practices, amounts of surface residue, soil water content, surface sealing, soil organic matter, soil macropore development, salinity, and sodicity. Infiltration rates change during a rainfall event and typically become slower over time. They typically also decrease over the growing season because of cultivation and harvest equipment. This is especially true if operations are done at higher soil-water levels. Macropores, or preferential flow paths, such as cracks or wormholes, substantially influence infiltration, and the internal soil drainage. Infiltration rates are also affected by water quality; for example, suspended sediment, temperature, salinity, and sodicity all affect water surface tension.

#### (b) Soil texture

Soil texture refers to the weight proportion of the soil separates (sand, silt, and clay) for analysis. It defines the fineness or coarseness of a soil. Particle sizes larger than 2 mm are considered rock fragments, and those that are less than 2 mm are the fine earth fraction. The fine earth fraction is determined from a laboratory particle-size distribution. The fraction classed as rock or coarse fragments is determined by the proportion of the soil volume they occupy. Rock fragment classes are used to modify soil textures. Medium-textured soils with a high clay and silt content hold the most


water, while fine-textured soils generally hold more water than coarse-textured soils. Water in clay soils can be held at a greater tension that reduces its availability to plants.

Figure 504-1 displays what is commonly referred to as the USDA textural triangle. It describes the proportions of sand, silt, and clay in the basic textural classes. Texture determines the amount of surface area on the soil particles within the soil mass. Clay and humus both exist in colloidal state and have an extremely large surface area per unit weight. They carry surface electrical charges to which ions and water are attracted.

#### (c) Soil structure

Soil structure is the arrangement and organization of soil particles into natural units of aggregation. Weakness planes that persist through cycles of wetting and drying and cycles of freezing and thawing separate these units. Structure influences air and water movement, root development, and nutrient supply.

**Figure 504-1** The USDA textural triangle describes the proportions of sand, silt, and clay in the basic textural classes



Structure type refers to the particular kind of grouping that predominates in a soil horizon. Single-grained and massive soils are structureless. In single-grained soil, such as loose sand, water percolates rapidly. Water moves slowly through most clay soil. A more favorable water relationship occurs in soil that has prismatic, blocky, and granular structure. Platy structure in fine and medium soils impedes the downward movement of water.

Structure can be improved with cultural practices, such as reducing tillage, improving internal drainage, liming or adding sulfur to soil, using grasses or deep rooted crops in rotation, incorporating crop residue, and adding organic material or soil amendments. Structure can be destroyed by heavy tillage equipment or excess operations.

Texture, root activity, clay mineralogy, percent organic matter, microbial activity, and the freeze-thaw cycle all play a part in aggregate formation and stability. Some aggregates are quite stable upon wetting, and others disperse readily. Soil aggregation helps maintain stability when wet, resist dispersion caused by the impact from rain, maintain soil intake rate, and resist surface water and wind erosion.

#### **(d) Soil bulk density**

Bulk density is the weight per unit volume of dry soil, which includes the volume of solids and pore space. Units are expressed as the weight at oven-dry and volume at field capacity water content, expressed as grams per cubic centimeter (g/cc) or pounds per cubic foot (lb/ft<sup>3</sup>). Bulk density is used to convert water measurements from a weight basis to a volume basis. Other factors affecting soil bulk density include freeze/thaw process, plant root growth and decay, wormholes, and organic matter.

#### **(e) Organic matter**

Soil organic matter is the organic fraction of the soil. It includes plant and animal residue at various stages of decomposition, and cells and tissues of soil organisms. Organic matter directly influences soil structure, soil condition, soil bulk density, water infiltration, plant growth and root development, permeability, total water holding capacity, biological activity, oxygen availability, nutrient availability, and tillage, as well as many other factors that make the soil a healthy natural resource for plant growth. Organic matter has a high cation adsorption capacity, and its decomposition releases plant nutrients including nitrogen, phosphorus, and sulfur. Site specific organic matter values should always be used for planning and managing cropping systems. Published values often are from sites that were managed quite differently.

#### **(f) Soil water holding capacity**

The potential for a soil to hold water is an important factor in designing a crop production system. Total water held by a soil is called water-holding capacity. However, not all soil water is available for extraction by plant roots. The volume of water available to plants that a soil can store is referred to as available water capacity (AWC). Figure 504-2 is a general illustration of soil water content and availability for a loam soil.

**Available water capacity** is the traditional term used to express the amount of water held in the soil available for use by most plants. It is dependent on crop rooting depth and several soil characteristics. Units of measure are expressed in various terms:

- Volume unit as inches of water per inch or per foot of soil depth
- Gravimetric percent by weight
- Percent on a volume basis

In fine textured soils and soils affected by salinity, sodicity, or other chemicals, a considerable volume of soil water may not be available for plant use.

**Soil-water potential**, more correctly, defines water available to plants. It is the amount of work required per unit quantity of water to transport water in soil. The concept of soil-water potential replaces arbitrary terms such as gravitational, capillary, and hygroscopic water.

In the soil, water moves continuously in the direction of decreasing potential energy or from higher water content to lower water content. As a plant takes up water from the soil, the concentration of water in the soil immediately adjacent to its roots is reduced. Water from the surrounding soil then moves into the soil around the roots.

For practical reasons, the terms and concepts of field capacity and permanent wilting point are normally used. Units of megapascals [MPa (metric units)] or bars or atmospheres (English units) are generally used to express soil water potential. One megapascal is equal to ten bars or atmospheres.

**Field capacity**—The field capacity of a well-drained soil is the amount of water held by that soil after free water has drained because of gravity. For coarse textured soil, drainage occurs soon after a rain event because of relatively large pores and low soil particle surface tension. In fine textured soil, drainage takes much longer because of smaller pores and their horizontal shape. Major soil properties that affect field capacity are texture, organic matter content,



structure, bulk density, and strata within the profile that restrict water movement. Generally, fine textured soil holds more water than coarse textured soil. Some soils, such as some volcanic and organic soils, are unique in that they can retain significant volumes of water at tensions less than one-tenth bar, thereby giving them a larger available water capacity.


An approximation of field capacity soil-water content level can be identified in the laboratory. It is the water retained in a soil when subjected to a tension of  $-0.01$  mPa [ $-0.1$  atmosphere (bar)] for sandy soils and  $-0.03$  mPa for other finer textured soils.

Field capacity water content level can be estimated in the field immediately following a rain, after free water has drained through the soil profile. Some judgment is necessary to determine when free water has drained and field capacity has been reached. Free water in coarse textured soil (sandy) can drain in a few hours. Medium textured (loamy) soil takes about 24 hours, and fine textured (clayey) soil may take several days.

**Permanent wilting point**—This is the soil-water content at which most plants cannot obtain sufficient water to prevent permanent tissue damage. The lower limit to the available water capacity has been reached for a given plant when it has so exhausted the soil moisture around its roots as to have irrecoverable tissue damage, thus yield and biomass are severely and permanently affected. The water content in the soil is then said to be the permanent wilting percentage for the plant concerned.

Experimental evidence shows that this water content point does not correspond to a unique tension of 1.5 megapascals (MPa) for all plants and soils. The quantity of water a plant can extract at tensions greater than this figure appears to vary considerably with plant species, root distribution, and soil characteristics. Some plants show temporary plant moisture stress during hot daytime periods and yet have adequate soil moisture. In the laboratory, permanent wilting point is determined at 1.5 MPa tension. Unless plant specific data are known, any water remaining in a soil at greater than 1.5 MPa tension is considered unavailable for plant use.

**Figure 504-2** Relationship of soil moisture content and water availability to crops.



Major soil characteristics affecting the available water capacity are texture, structure, bulk density, salinity, sodicity, mineralogy, soil chemistry, and organic matter content. Of these, texture is the predominant factor in mineral soil. Because of the particle configuration in certain volcanic ash soil, the soil can contain very high water content at field capacity levels. This provides a high available water capacity value. Table 504–1 displays average available water capacity based on soil texture.

The available water capacity value shown in soil survey reports, the Field Office Technical Guide, or the National Soil Survey Information System account for the estimated volume of coarse fragments for the specific soil series. However, in an onsite investigation any additional coarse fragments found in the soil profile must be accounted for. Coarse fragments of volcanic material, such as pumice and cinders, can contain water within the fragments themselves,

but this water may not be available for plant use because of the restricted root penetration and limited capillary water movement. Adjustment to the available water capacity based upon this additional field information should be made.

Different soils hold and release water differently. When soil-water content is high, very little effort is required by plant roots to extract moisture. As each unit of moisture is extracted, the next unit requires more energy. This relationship is referred to as a soil moisture release characteristic. The tension in the plant root must be greater than that in the soil at any water content to extract the soil water. Typically with most field crops, soil moisture is not the limiting factor for crop yield when water is available at less than -0.5 MPa (-5 atmospheres) in medium or fine textured soils. At soil-water tensions of more than about 0.5 MPa, plant yield or biomass is reduced in medium to fine textured soils.

**Table 504-1** Available Water Capacity (AWC) by soil texture

Texture symbol	Texture	AWC range (in/in)	AWC range (in/ft)	Estimated typical AWC (in/ft)
COS	Coarse sand	0.01 - 0.03	0.1 - 0.4	0.25
S	Sand	0.01 - 0.03	0.1 - 0.4	0.25
FS	Fine sand	0.05 - 0.07	0.6 - 0.8	0.75
VFS	Very fine sand	0.05 - 0.07	0.6 - 0.8	0.75
LCOS	Loamy coarse sand	0.06 - 0.08	0.7 - 1.0	0.85
LS	Loamy sand	0.06 - 0.08	0.7 - 1.0	0.85
LFS	Loamy fine sand	0.09 - 0.11	1.1 - 1.3	1.25
LVFS	Loamy very fine sand	0.10 - 0.12	1.0 - 1.4	1.25
COSL	Coarse sandy loam	0.10 - 0.12	1.2 - 1.4	1.3
SL	Sandy loam	0.11 - 0.13	1.3 - 1.6	1.45
FSL	Fine sandy loam	0.13 - 0.15	1.6 - 1.8	1.7
VFSL	Very fine sandy loam	0.15 - 0.17	1.8 - 2.0	1.9
L	Loam	0.16 - 0.18	1.9 - 2.2	2.0
SIL	Silt loam	0.19 - 0.22	2.3 - 2.6	2.45
SI	Silt	0.16 - 0.18	1.9 - 2.2	2.0
SCL	Sandy clay loam	0.14 - 0.16	1.7 - 1.9	1.8
CL	Clay loam	0.15 - 0.17	1.8 - 2.0	1.9
SICL	Silty clay loam	0.17 - 0.19	2.0 - 2.3	2.15
SC	Sandy clay	0.15 - 0.17	1.8 - 2.0	1.9
SIC	Silty clay	0.15 - 0.17	1.8 - 2.0	1.9
C	Clay	0.14 - 0.16	1.7 - 1.9	1.8

**(g) Soil pore space**

Soil is composed of soil particles, organic matter, water, and air. Pore space allows the movement of water, air, and roots. Dense soil has a low AWC because of decreased pore space. Density can make AWC differences of -50 percent to +30 percent compared to average densities. Sandy soils generally have bulk densities greater than soils with high clay content. Sandy soils have less total pore space than silt and clay soils. Gravitational water flows through sandy soils much faster because the pores are much larger. Clayey soils hold more water than sandy soils because clay soils have a larger volume of small, flat-shaped pore spaces that hold more capillary water. Clay soil particles are flattened or plate-like in shape, thus, soil-water tension is also higher for a given volume of water. When the percent clay in a soil increases over about 40 percent, AWC is reduced even though total soil-water content may be greater. Permeability and drainability of soil are directly related to the volume, size and shape of pore space.

Uniform plant root development and water movement in soil occurs when the soil profile bulk density is uniform, a condition that seldom exists in the field. Generally, soil compaction occurs in all soils where tillage implements and wheel traffic are used. Compaction decreases pore space, decreasing root development, oxygen content, water movement and availability.

**(h) Soil depth**

Soil depth is the dimension from the soil surface to bedrock, hardpan, or water table; to a specified soil depth; or to a root growth restrictive layer. The deeper the soil and plant roots, the more soil-water storage is available for plant use. Crop rooting depth and the resulting total AWC control the length of time plants can go between rainfall events before reaching moisture stress. Equipment compaction layers or naturally-occurring impervious layers restrict the downward movement of water and root penetration.

An abrupt change in soil texture with depth can restrict downward water movement. For example, coarse sand underlying medium or fine textured soil requires saturation at the textural interface before substantial amounts of water will move into the coarser soil below. When a coarse textured soil abruptly changes to a medium or fine textured soil, a temporary perched water table develops above the less permeable soil. Stratified soils or shallow soils over hardpans or bedrock can also hold excess gravitational wa-

ter at the interface. The excess water can move upward because of the increased soil particle surface tension as the soil water in the upper profile is used by plants or capillary action resulting from surface evaporation. Thus, an otherwise shallow soil with low total AWC can have characteristics of a deeper soil.

**(i) Water tables**

Water tables can be a barrier for root development because of restricted oxygen availability. Providing artificial drainage of poorly drained soils increases soil depth for potential root development. Adequate soil drainage must be present for sustained growth of most plants.

In other situations, where water tables are not a barrier to root development, planned water table control and management of shallow ground water can supply all or part of the seasonal crop water needs. The water must be high quality, salt free, and held at or near a constant elevation. The water table level should be controlled to provide water according to crop needs.

**(j) Chemical properties**

The physical and chemical weathering of materials on the Earth's surface form soil. These materials may have been rock, or they may have been other materials that were transported from somewhere else and deposited over rock. Exposure of the surface to water, oxygen, organic matter, and carbon dioxide brings about chemical alterations to the material. Oxidation, reduction, hydration, hydrolysis, and carbonation contribute to chemical and physical changes in the surface material. If it is rock, the material gradually breaks down into smaller particles, forming a mineral soil. If it is a transported material, such as glacial till or loess, weathering can affect soil chemistry and mineralogy. The chemical and mineralogical composition of the soil varies with respect to depth or horizon. Weathering intensity decreases with depth from the surface. The longer the weathering has proceeded, the thicker the weathered layer and the greater the dissimilarity from the original material. In mineral soils, organic matter content generally decreases with depth.

The colloidal fraction (diameter less than 0.001 mm) of the soil plays an important part in the chemistry of the soil. Microbiological activity is greatest near the surface where oxygen, organic matter content, and temperature are the highest.

Cation exchange capacity (CEC) is the total amount of cations held in a soil in such a way that they can be removed by exchanging with another cation in the natural soil solution, expressed in milliequivalents per 100 grams of oven-dry soil (meq/100 gm). The cation exchange capacity is a measure of the ability of a soil to retain cations, some of which are plant nutrients. It is affected primarily by the kind and amount of clay and organic matter. Soils that have low CEC hold fewer cations and may require more frequent applications of fertilizers than soils with high CEC. See Soil survey reports, the Field Office Technical Guide, or the National Soil Survey Information System for CEC estimates for specific soil series.

### (k) Saline soil effects

Salt-affected soils are generally classified as follows, using electrical conductivity of the soil-water extract,  $EC_e$ , as the basis:

Salinity	$EC_e$
Nonsaline	0–2 dS/m
Very Slight	2 - 4 dS/m
Slight	4 - 8 dS/m
Moderate	8 - 16 dS/m
Strong	> 16 dS/m

Salts in the soil-water solution decrease the amount of water available for plant uptake. Table 504–2 displays AWC values adjusting for effect of salinity versus texture.  $EC_e$  is defined as the electrical conductivity of the soil-water extract corrected to 77 °F (25 °C). Units are expressed in millimhos per centimeter (mmho/cm) or decisiemens per meter (dS/m); 1 mmho/cm = 1 dS/m. As water is evaporated from the soil surface or used by plants, salt within the soil-water solution are left behind either on the ground surface or within the soil profile. Leaching with excess water through the soil profile can reduce accumulated saline salts.

## 504.02 Crop characteristics

### (a) Response to water, crop yield, and quality

Crop response to available water is dependent not only on the genetic characteristics and requirements of the plant but also on the environmental constraints to which it is subjected. Soil moisture is only one component needed to achieve desired crop yield and quality. Soil water within a desirable depletion range (preferably less than 5 bars tension) generally provides the expected yield and quality. The

**Table 504-2** Available water capacity adjustments because of salinity <sup>1/</sup>

Soil texture	----- Electrical conductivity ( $EC_e \times 10^3$ ) -----								
	0	2	4	6	8	10	12	14	
	----- Available water capacity (in/in) <sup>2/</sup> -----								
Clay	.14 - .16	.13 - .15	.12 - .14	.11 - .13	.10 - .12	.09 - .11	.07 - .08	.04 - .05	
Silty clay	.15 - .17	.14 - .16	.13 - .15	.12 - .14	.11 - .12	.09 - .11	.07 - .08	.04 - .05	
Sandy clay	.15 - .17	.14 - .16	.13 - .15	.12 - .14	.11 - .12	.09 - .11	.07 - .08	.04 - .05	
Silty clay loam	.19 - .21	.18 - .20	.17 - .18	.15 - .17	.14 - .15	.12 - .13	.09 - .10	.06 - .07	
Clay loam	.19 - .21	.18 - .20	.17 - .18	.15 - .17	.14 - .15	.12 - .13	.09 - .10	.06 - .07	
Sandy clay loam	.14 - .16	.13 - .15	.12 - .14	.11 - .13	.10 - .12	.09 - .11	.07 - .08	.04 - .05	
Silt loam	.19 - .21	.18 - .20	.17 - .18	.15 - .17	.14 - .15	.12 - .13	.09 - .10	.06 - .07	
Loam	.16 - .18	.15 - .17	.14 - .16	.13 - .15	.12 - .13	.10 - .11	.08 - .09	.05 - .06	
Very fine sandy loam	.15 - .17	.14 - .16	.13 - .15	.12 - .14	.11 - .12	.09 - .11	.07 - .08	.04 - .05	
Fine sandy loam	.13 - .15	.12 - .14	.11 - .13	.11 - .12	.09 - .11	.08 - .09	.06 - .07	.04 - .05	
Sandy loam	.11 - .13	.10 - .12	.10 - .11	.09 - .11	.08 - .09	.07 - .08	.05 - .06	.03 - .04	
Loamy very fine sand	.10 - .12	.10 - .11	.09 - .11	.08 - .09	.07 - .08	.06 - .07	.04 - .05	.02 - .03	
Loamy fine sand	.09 - .11	.09 - .10	.08 - .10	.07 - .09	.06 - .08	.06 - .07	.04 - .05	.03 - .04	
Loamy sand	.06 - .08	.06 - .08	.06 - .07	.05 - .06	.04 - .06	.04 - .05	.03 - .04	.02 - .03	
Fine sand	.05 - .07	.05 - .07	.05 - .06	.04 - .06	.04 - .05	.03 - .04	.02 - .03	.02	

<sup>1/</sup> Compiled by NRCS, National Soil Survey Laboratory, Lincoln, NE

<sup>2/</sup> 15 mmhos conductivity results in a 75-95% reduction in available water capacity

effect on yield and quality depends on how severe and during which period of crop growth water deficit occurs. In addition, some crops require less water to initially produce a minimum yield, are more efficient at utilizing available water, or go through their growth cycle during periods of reduced environmental stress. Brown and Carlson (1990) relate that barley was more productive, under the same environmental conditions as winter wheat, spring wheat, oats, and safflower. Barley was more efficient than other crops at converting plant available water to grain because of its water to grain conversion efficiency, its lower water requirements to initially produce the first unit of yield, and its early season maturity, avoiding environmental stresses that reduce yield potential.

Other management factors that limit maximum productivity are crop selection, previous crop, weed problems, soil fertility, and planting date also limit the crops ability to use available water.

#### **(b) Crop water requirements**

Crop evapotranspiration ( $ET_c$ ), sometimes called crop consumptive use, is the amount of water that plants use in transpiration and building cell tissue plus water evaporated from an adjacent soil surface. Crop evapotranspiration is influenced by several major factors: plant temperature, ambient air temperature, solar radiation (sunshine duration/intensity), wind speed/movement, relative humidity/vapor pressure, and soil-water availability. Seasonal local crop water use requirements are essential for planning crop production systems.

## **504.03 Methods for determining crop evapotranspiration**

### **(a) Direct measurement of crop evapotranspiration**

Direct measurement methods for  $ET_c$  include

- aerodynamic method,
- detailed soil moisture monitoring,
- lysimetry,
- plant porometers, and
- regional inflow-outflow measurements.

All these methods require localized and detailed measurements of plant water use. Detailed soil moisture monitoring in controlled and self-contained devices (lysimeters) is probably the most commonly used. Little long-term historical data outside of a few ARS and university research stations are available.

### **(b) Estimated crop evapotranspiration ( $ET_c$ )**

More than 20 methods have been developed to estimate the rate of crop ET based on local climate factors. The simplest methods are equations that generally use only mean air temperature. The more complex methods are described as energy equations. They require real time measurements of solar radiation, ambient air temperature, wind speed/movement, and relative humidity/vapor pressure. These equations have been adjusted for reference crop ET with lysimeter data. Selection of the method used for determining local crop ET depends on

- location, type, reliability, timeliness, and duration of climatic data;
- natural pattern of evapotranspiration during the year; and
- intended use intensity of crop evapotranspiration estimates.

Although any crop can be used as the reference crop, clipped grass is the reference crop of choice. Some earlier reference crop research, mainly in the West, used 2-year-old alfalfa ( $ET_p$ ). With grass reference crop ( $ET_o$ ) known, ET estimates for any crop at any stage of growth can be calculated by multiplying  $ET_o$  by the appropriate crop growth stage coefficient ( $k_c$ ), usually displayed as a curve or table. The resulting value is called crop evapotranspiration ( $ET_c$ ). The following methods and equations used to estimate reference crop evapotranspiration ( $ET_o$ ).  $ET_o$  methods and

equations are described in detail in the Engineering Field Handbook, Part 623, Chapter 2, Irrigation Water Requirements (1990). The reference crop used is clipped grass. Crop coefficients are based on local or regional growth characteristics. The Natural Resources Conservation Service (NRCS) recommends the following methods:

#### Temperature method

- FAO Modified Blaney-Criddle (FAO Paper 24)
- Modified Blaney-Criddle (SCS Technical Release No. 21)

#### Energy method

- Penman-Monteith method

#### Radiation method

- FAO Radiation method (FAO Paper 24)

### Evaporation pan method

The FAO Modified Blaney-Criddle, Penman-Monteith, and FAO Radiation equations represent the most accurate equations for these specific methods. They are most accurately transferable over a wide range of climate conditions.

The intended use, reliability, and availability of local climatic data may be the deciding factor as to which equation or method is used.

For estimation of monthly and seasonal crop water needs, a temperature-based method generally proves to be quite satisfactory. The FAO Modified Blaney-Criddle equation uses long-term mean temperature data with input of estimates of relative humidity, wind movement, and sunlight duration. This method also includes an adjustment for elevation. The FAO Radiation method uses locally measured solar radiation and air temperature.

Crop ET and related tables and maps can be included to replace or simplify crop ET calculations. These maps and tables would be locally developed, as needed.

### (c) Critical growth periods

Plants must have ample moisture throughout the growing season for optimum production and the most efficient use of water. This is most important during critical periods of growth and development. Most crops are sensitive to water stress during one or more critical growth periods in their growing season. Moisture stress during a critical period can cause an irreversible loss of yield or product quality. Critical periods must be considered with caution because they depend on plant species as well as variety. Some crops can be moderately stressed during noncritical periods with no adverse effect on yields. Other plants require mild stress to set and develop fruit for optimum harvest time (weather or market). Critical water periods for most crops are displayed in table 504-3.

**Table 504-3** Critical periods for plant moisture stress

Crop	Critical period	Comments
Alfalfa	At seedling stage for new seedlings, just after cutting for hay, and at start of flowering stage for seed production.	Any moisture stress during growth period reduces yield. Soil moisture is generally reduced immediately before and during cutting, drying, and hay collecting.
Beans, dry	Flowering through pod formation.	
Broccoli	During head formation and enlargement.	
Cabbage	During head formation and enlargement.	
Cauliflower	During entire growing season.	
Cane berries	Blossom through harvest.	
Citrus	During entire growing season.	Blossom and next season fruit set occurs during harvest of the previous crop.
Corn, grain	From tasseling through silk stage and nels become firm.	Needs adequate moisture from germination until kernel dent stage for maximum production. Depletion of 80% or more of AWC can occur during final ripening period without impacting yield.
Corn, silage	From tasseling through silk stage and nels become firm.	Needs adequate moisture from germination until kernel dent stage for maximum production.
Corn, sweet	From tasseling through silk stage and until kernels become firm.	
Cotton	First blossom through boll maturing stage.	Any moisture stress, even temporary, ceases blossom formation and boll set for at least 15 days after moisture again becomes available.
Cranberries	Blossom through fruit sizing.	
Fruit trees	During the initiation and early development period of flower buds, the flowering and fruit setting period (may be the previous year), the fruit growing and enlarging period, and the pre-harvest period.	Stone fruits are especially sensitive to moisture stress during last two weeks before harvest.
Grain, small	During boot, bloom, milk stage, early head development and early ripening stages.	Critical period for malting barley is at soft dough stage to maintain a quality kernel.
Grapes	All growth periods, especially during fruit filling.	See vine crops.
Peanuts	Full season.	
Lettuce	Head enlargement to harvest.	Water shortage results in a sour and strong lettuce.



**Table 504-3** Critical periods for plant moisture stress—Continued

Crop	Critical period	Comments
Melons	Blossom through harvest.	
Milo	Secondary rooting and tillering to boot stage, heading, flowering, and grain formation through filling.	
Onions, dry	During bulb formation, near harvest.	
Onions, green	Blossom through harvest stress.	Strong and hot onions can result from moisture.
Nut trees	During flower initiation period, fruit set, and mid-season growth.	Pre-harvest period is not critical because nuts form during mid-season period.
Pasture	During establishment and boot stage to head formation.	
Peas, dry	At start of flowering and when pods are swelling.	
Peas, green	Blossom through harvest.	
Peppers	At flowering stage and when peppers are swelling.	
Potato	Flowering and tuber formation to harvest.	Low-quality tubers result if moisture stress during tuber development and growth.
Radish	During period of root enlargement.	Hot radishes can be the result of moisture stress.
Sunflower	Flowering to seed development.	
Sorghum, grain	Secondary rooting and tillering to boot stage, heading, flowering, and grain formation through filling.	
Soybeans	Flowering and fruiting stage.	
Strawberries	Fruit development through harvest.	
Sugar beets	At time of plant emergence, following thinning, and 1 month after emergence.	Temporary leaf wilt on hot days is common even with adequate soil water content.
Sugarcane	During period of maximum vegetative growth.	
Tobacco	Knee high to blossoming.	
Tomatoes	When flowers are forming, fruit is setting, and fruits are rapidly enlarging.	
Turnips	When size of edible root increases rapidly up to harvest.	Strong tasting turnips can be the result of moisture stress.
Vine crops	Blossom through harvest.	
Watermelon	Blossom through harvest.	



**(d) Rooting depth**

The soil is a storehouse for plant nutrients, an environment for biological activity, an anchorage for plants, and a reservoir for water to sustain plant growth. The amount of water a soil can hold available for plant use is determined by its physical and chemical properties.

The type of root system a plant has is fixed by genetic factors. Some plants have taproots that penetrate deeply into the soil, while others develop many shallow lateral roots. The depth of the soil reservoir that holds water available to a plant is determined by that plant's rooting characteristics and soil characteristics including compaction layers and water management. The distribution of the plant roots determines its moisture extraction pattern. Typical rooting depths for various crops grown on a deep, well drained soil with good water and soil management are listed in table 504-4. With good soil management and growing conditions, crops can root much deeper (table 504-5).

**Table 504-4** Depth to which roots of mature crops will extract available water from a deep, uniform, well-drained soil under average unrestricted conditions (depths shown are for 80% of the roots)

Crop	Depth (ft)	Crop	Depth (ft)
Alfalfa	5	Milo	2 - 4
Asparagus	5	Mustard	2
Bananas	5	Onions	1 - 2
Beans, dry	2 - 3	Parsnips	2 - 3
Beans, green	2 - 3	Peanuts	2 - 3
Beets, table	2 - 3	Peas	2 - 3
Broccoli	2	Peppers	1 - 2
Berries, blue	4 - 5	Potatoes, Irish	2 - 3
Berries, cane	4 - 5	Potatoes, sweet	2 - 3
Brussels sprouts	2	Pumpkins	3 - 4
Cabbage	2	Radishes	1
Cantaloupes	3	Safflower	4
Carrots	2	Sorghum	4
Cauliflower	2	Spinach	1 - 2
Celery	1 - 2	Squash	3 - 4
Chard	1 - 2	Strawberries	1 - 2
Clover, Ladino	2 - 3	Sudan grass	3 - 4
Cranberries	1	Sugar beets	4 - 5
Corn, sweet	2 - 3	Sugarcane	4 - 5
Corn, grain	3 - 4	Sunflower	4 - 5
Corn, seed	3 - 4	Tobacco	3 - 4
Corn, silage	3 - 4	Tomato	3
Cotton	4 - 5	Turnips	2 - 3
Cucumber	1 - 2	Watermelon	3 - 4
Eggplant	2	Wheat	4
Garlic	1 - 2		
Grains & flax	3 - 4	<b>Trees</b>	
Grapes	5	Fruit	4 - 5
Grass pasture/hay	2 - 4	Citrus	3 - 4
Grass seed	3 - 4	Nut	4 - 5
Lettuce	1 - 2		
Melons	2 - 3		

For annual crops, rooting depths vary by stage of growth and should be considered in determining the amount of soil water available.

For most plants, the concentration of moisture absorbing roots is greatest in the upper part of the root zone (usually in the top quarter). Extraction is most rapid in the zone of greatest root concentration and where the most favorable conditions of aeration, biological activity, temperature, and nutrient availability occur. Water also evaporates from the upper few inches of the soil; therefore, water is diminished most rapidly from the upper part of the soil. This creates a high soil-water potential gradient.

**Table 504-5** Maximum rooting depth of mature crops seeded on fallow from 1976 to 1979 at Fort Benton, MT

Crop	Root depth (Feet)
Alfalfa, vernal	20
Argentine rape	4
Barley	5
Flax	5
Mustard, yellow	4
Safflower	7
Sunflower	6
Wheat, winter	6
Wheatgrass	9

In uniform soils that are at field capacity, plants use water rapidly from the upper part of the root zone and more slowly from the lower parts. About 70 percent of available soil water comes from the upper half of a uniform soil profile. Any layer or area within the root zone that has a low AWC or increased bulk density affects root development and may be the controlling factor for soil moisture availability.

Variations and inclusions are in most soil map units, thus uniformity should not be assumed. Field investigation is required to confirm or determine onsite soil characteristics including surface texture, depth, slope, and potential and actual plant root zone depths.

Soil texture, structure, and condition help determine the available supply of water in the soil for plant use and root development. Unlike texture, structure and condition of the surface soil can be changed with management.

Very thin tillage pans can restrict root development in an otherwise homogenous soil. Never assume a plant root zone. Observe root development of present or former crops.

Numerous soil factors may limit the plant's genetic capabilities for root development. The most important factors are:

- soil density and pore size or configuration,
- depth to restrictive or confining layers,
- soil-water status,
- soil aeration,
- nutrient availability,
- water table,
- salt concentrations, and
- soil-borne organisms that damage or destroy plant root system.

Root penetration can be extremely limited into dry soil, a water table, bedrock, high salt concentration zones, equipment and tillage compaction layers, dense fine texture soils, and hardpans. When root development is restricted, it reduces plant available soil-water use and consequent storage, which in turn limits crop production.

High soil densities that can result from tillage and farm equipment seriously affect root penetration. Severe compacted layers can result from heavy farm equipment, tillage during higher soil moisture level periods, and from the total number of operations during the crop growing season. In many medium to fine textured soils, a compacted layer at a uniform tillage depth causes roots to be confined above the

compacted layer at depths usually less than 6 to 10 inches from the surface. Roots seek the path of least resistance, thus do not penetrate a compacted dense layer except through cracks. Every tillage operation causes some compaction. Even very thin tillage pans restrict root development and can confine roots to a shallow depth, thereby limiting the depth for water extraction. This is probably most common with row crops where many field operations occur and with hayland when soils are at high moisture levels during harvest.

Subsoiling when the soil is dry can fracture compacted layers. However, unless the cause of compaction (typically tillage equipment itself), the number of operations, and the method and timing of the equipment's use are changed, compaction layers will again develop. Only those field operations essential to successfully growing a crop should be used. Extra field operations require extra energy (tractor fuel), labor, and cost because of the additional wear and tear on equipment. Necessary tillage operations should only be performed when the soil surface from 0 to 2 inches or 0 to 3 inches in depth is dry enough not to cause soil smearing or compaction. The lightest equipment with the fewest operations necessary to do the job should be used.

For site specific planning and design, never assume a plant root zone depth. Use a shovel or auger to observe actual root development pattern and depth with cultural practices and management used. The previous crops or even weeds will generally show root development pattern restrictions.

## 504.04 Tillage systems effect on water conservation

### (a) Comparisons of water conservation under different residue management systems

Tillage practices influence soil moisture throughout the growing season. Reduced-tillage or no-till systems decrease evaporation losses, if the residue remains on the soil surface. Both surface roughness and residue slow water runoff, allowing more time for infiltration. In addition, surface residue prevents soil surface sealing, thus increasing infiltration and soil water stored. The net effect of tillage systems that leave surface residue is less variation in soil water during the summer months and more plant available water.

**Evaporation**—a primary source of water loss during the first half of the growing season before the crop canopy closes. Crop residue on the soil surface shades the soil surface and reduces the amount of solar energy absorbed, thereby reducing soil temperatures and evaporation. Residue also reduce air velocity at the soil surface, slowing the rate at which evaporation occurs. Residue cover offers the greatest reduction in evaporation when the soil is moist and not yet shaded by the crop. Unger and Parker (1968) reported that the cumulative evaporation after 16 weeks was 57 percent less when wheat residue remained on the surface rather than mixed into the soil.

The difference in cumulative evaporation between bare soil and soil with a residue cover is related to the frequency and amount of rainfall. For small, infrequent rainfall events, the two soil surfaces show little difference in cumulative evaporation. However, with larger more frequent rains, less evaporation occurs from soil protected by surface residue than from bare soil. In stubble covered wheat field, evaporation ranges from 60-75 percent of that occurring from bare soil. Evaporation from the soil depends on water rising to the surface by capillary action as the soil dries. Shallow incorporation of residue reduces this capillary action however; leaving residue on the soil surface generally reduces evaporation more than shallow incorporation.

**Water infiltration**—the process of water entering the soil at the soil/air interface. Crop residue affects soil infiltration by intercepting raindrop energy and the associated soil sealing or ponding that occurs thereby increasing infiltration and reducing the amount of runoff. Simulated rainfall studies in Ohio show that infiltration increases with surface residue (table 504-6). Although the infiltration rate was initially greater on the plowed field than the bare no-till field, the residue in the no-till field enabled faster water infiltration.

**Runoff**—tillage systems that leave crop residue on the soil surface generally reduce runoff. The factors that influence the differences in runoff are soil characteristics, weather patterns, the presence of macropores, management, and the amount and kind of residue. The residue characteristics that affect water infiltration also affect runoff by increasing the time to initiation of runoff and lowering runoff rates. Residue on the soil surface increases the surface roughness of the soil, reduces runoff velocities, and causes ponding that further delays runoff. In addition, surface residue obstructs and diverts runoff, increasing the length of time in the downslope flow path allowing more time for infiltration.

Another important point is the effect of having both standing and flat residues present. The presence of standing and flat residues reduces the likelihood that small localized flow areas will combine into larger networks, and decreases the velocity and overall transport of runoff from the field. If the climate and soil conditions exclude macropore development and traffic causes unrelieved reductions in infiltration, runoff rates can increase even with high residue crop production systems such as no-till, particularly in the early years of the systems before surface organic matter has time to accumulate.

**Table 504-6** Effect of tillage and corn residue on infiltration using simulated rainfall (Triplett et al. 1968)

Treatment	Initial run	Wet run <sup>1/</sup>
Plowed, bare	0.71	0.41
No-tillage, bare <sup>2/</sup>	0.48	0.25
No-tillage, 40% cover	0.92	0.53
No-tillage, 80% cover	1.73	1.37

<sup>1</sup> Wet run took place 24 hr after initial run.

<sup>2</sup> Residue cover was removed for research purposes.

Gilley (1986, 1987) and co-workers conducted a series of studies evaluating the effect of different types and amounts of residue on runoff rates. Five rates of corn residue were spread on the soil surface at 0, 10, 31, 51, and 83 percent ground cover (0, 1, 1.12, 3.36, 6.73, and 13.45 mg/ha). Rainfall was applied at a rate of 28 millimeters per hour on days 1, 2, and 3 of the study. Average runoff rates were 15.6, 10.7, 6.0, 1.8, and 0 millimeters per hour for the 0, 10, 31, 51, and 83 percent residue covers, respectively. Runoff rates were also studied for sorghum and soybean residues at a rainfall rate of 48 millimeters per hour. The runoff rate for soybean decreased by 68 percent as residue cover increased from 0 to 56 percent; the runoff rate for sorghum decreased by 73 percent as residue cover increased from 0 to 44 percent.

**Snow catch**—Maximizing snow catch is a vital conservation measure in the northern Great Plains, since snow constitutes 20 to 25 percent of the annual precipitation. Stubble height management is a tool used to maximize snow catch. Taller stubble retains more snow, increasing soil water content. Bauer and Black (1990) in a 12 year study reported that increasing small grain stubble height from 2 to 15 inches increased soil water content to a depth of 5 feet by 1.6 inches. Increasing the snow catch on a field can also increase spring melt runoff depending on the early spring soil infiltration characteristics. However, in soils on which annual crops are grown, infiltration of snowmelt occurs 80 to 90 percent of the time because the soil is usually frozen while dry or not frozen as deeply due to the snow coverage to permit infiltration. Greb (1979) reported that the efficiency of storing meltwater is often double that of storing water received as rain.

**Water storage**—Soil moisture savings is of great importance in regions of low rain fall and high evapotranspiration, on soil low in water holding capacity, and in years with below normal rainfall. In the Corn Belt, excessive soil moisture in the spring months often has a negative effect on crop growth since it slows soil warming and delays planting. However, on soils where drought stress often occurs during the summer months, having more available water during crop pollination and seed filling usually offsets these early season negative effects. Seed zone soil moisture also aids in plant establishment and growth in dry areas of the United States. For a high percentage of the farmland, moisture savings should be a primary reason for producers to consider reduced tillage systems.

Research on the effects of reducing tillage and increasing surface residue have indicated that high amounts of surface residue results in increased soil water stored. Unger (1978) reported that high wheat residue levels resulted in increased water storage during the fallow period and the increased subsequent grain sorghum the following year. Similar results of water storage under high residue conditions, shown in table 504-7, summarized by Greb (1983) for 20 crop-years from four locations.

Management changes in the Great Plains since 1916 have improved soil water storage, fallow efficiency (percentage of the precipitation received during the fallow period and stored as soil water), and small grain yields. However, fallow efficiencies up to 40 percent were reported in the 1970's and have not improved beyond this value. Furthermore, subsequent research in the Great Plains with modern no-till wheat-fallow systems indicates that most of the moisture received is stored early in the year, after crop harvest, and very little soil water is stored beyond the first of July. This information indicates that reducing or eliminating fallow from the rotation, intensifying the cropping pattern, and utilizing the soil moisture stored through the rotation is a means of taking advantage of our increased capability to store water earlier in the cropping cycle with high residue crop production systems.

**Excessive soil water**—Soil properties that affect water infiltration, permeability, and drainage must always be properly assessed when making residue management decisions. Research in the Corn Belt has shown that no-till management systems on some poorly drained soils has resulted in lower yields compared to the yields of conventionally tilled systems. Continued research has shown, however after 18 years of continued no-till that yields are now equal or

**Table 504-7** Net soil-water gain at the end of fallow as influenced by straw mulch rates at four Great Plains locations

Location	Years reported	Mulch rate (mg/ha)			
		0	2.2	4.4	6.6
Bushland, TX	3	7.1	9.9	9.9	10.7
Akron, CO	6	13.4	15.0	16.5	18.5
North Platte, NE	7	16.5	19.3	21.6	23.4
Sidney, MT	4	5.3	6.9	9.4	10.2
Mean		10.7	12.7	14.5	15.7
Gain with mulch			2.0	3.8	5.0

Note: Soil water gain units = centimeter.

greater than conventionally tilled systems. The initial yield reductions on these poorly drained soils may have been attributed to a number of factors. The positive yield response after continuous no-till on these soils may be attributed to the development of internal drainage characteristics such as macropores, increases in organic matter, better surface soil structure, and the use of disease resistant cultivars.

When dealing with heavier residue amounts from the preceding crop it may be necessary in no-till situations to use residue managers that move the residue to the side of the seed trench. Poorly drained soils are not easily adapted to high residue systems and may need to be managed with limited till systems such as ridge-till or fall and spring strip-till methods. Some warm-season species such as corn or sunflower respond to warm, clean seedbed conditions. This may also be accomplished including crops in the rotation that produce lower amounts of dark colored residue or the inclusion of cover crop. (Refer to Subpart 506B, Suitability for crop production systems.)

#### **(b) Cropping system intensity**

Improving the relative efficiency of water use in crop production systems has been a major goal in achieving more productive modern crop production systems. Reducing water losses in cropping systems by changes in tillage systems, residue management, crop selection and sequence has achieved more intense rotations and greater water use efficiency (WUE).

Water use efficiency can be defined as the dry matter produced divided by the growing season evapotranspiration (ET) and expressed in units of dry matter per unit of water for a given crop in that system. Since water losses in a system such as runoff and drainage are often unknowns, ET is replaced by a value comprised of soil water used during the growing season plus growing season precipitation. This relationship can be shown in the equation below.

The result of the calculation is not exactly identical to situations where true ET is known because not all the precipitation received during the growing season does enter or stay in the soil. This overestimate of water available to the plant, however is valuable to quantify the efficiency of crops grown on a systems basis for a given climate.

Changes in cropping systems by decreasing tillage, increasing surface residues, making conscious decisions on residue orientation, as well as, strategically placing crops in rotations have produced these changes in water use efficiency. Cropping system intensification has improved the WUE, and has increased the productivity of crop production systems in the Great Plains. Three-year systems increased WUE in every climate regime in Texas, Kansas, and Colorado (table 504-8). The WUE for the 3-year rotation winter wheat-corn-fallow averaged 196 pounds per acre per inch, compared with an average WUE of 140 pounds per acre per inch for winter wheat-fallow.

Continuous cropping may be a viable option for producers in areas where fallow has traditionally been a part of a cropping sequence. With high residue management the inclusion of annual forages, such as sorghums, millet, field peas, or small grains, would increase the producers flexibility to maximize WUE. Crop choice affects WUE of the crop production system because each species has a different potential for production. Optimizing WUE in a particular crop production system requires choosing crops with the highest potential WUE for your particular environment.

Several predictive tools (water-use-production functions) have been developed to assist producers in crop selection in several environments across the Great Plains. Black et al. (1981) suggested that a flexible cropping strategy would provide efficient water use to control saline seeps in the northern Great Plains. Flexible cropping is defined as seeding a crop when stored soil water and rainfall probabilities are favorable for satisfactory yield, or fallowing when prospects are unfavorable. Available soil water can be estimated by measuring moist soil depth with a soil moisture probe or other soil sampling equipment. Brown et al. (1981) have developed soil water guidelines and precipitation probabilities for barley and spring wheat for flexible cropping systems in Montana and North Dakota.

When considering a flexible cropping system a producer should evaluate the amount of plant-available soil water at seeding time, the precipitation probabilities for the seasonal needs of a given crop, and management factors such as variety, crop rotation, weed and insect problems, soil fertility, and planting date. Current information in the Great Plains at

$$WUE = \frac{\text{Dry matter yield}}{\left( (\text{Soil water at planting} - \text{Soil water at harvest}) + \text{growing season precipitation} \right)}$$

various locations includes yield water-use-production functions for winter wheat, spring wheat, barley, oats, millet, corn, sunflower, dry beans, canola, crambe, soybean, and safflower given soil moisture and rainfall-probability information (Brown and Carlson 1990; Vigil et al. 1995; Nielson 1995). This information can assist a producer in crop selection in a given year, however users of these water use/yield relationships need to understand that the final crop yield is influenced by the timing of precipitation as well as the amount of water used.

**Table 504-8** Water use efficiency of 3-year no-till cropping systems and continuous spring wheat as compared with no-till spring wheat and winter wheat-fallow systems at various locations across the Great Plains (Peterson et al. 1996)

System	WUE, lb/acre per in	Location
Spring wheat/Fallow	130	Minot, ND
Cont. spring wheat	119	Do.
Spring wheat/Fallow	78	Williston, ND
Cont. spring wheat	125	Do.
Winter wheat/ Fallow	155	Sterling and Stratton, CO
Winter wheat/ Corn/ Fallow	202	Do.
Winter wheat/ Fallow	156	Akron, CO
Winter wheat/ Corn/ Fallow	250	Do.
Winter wheat/Fallow	144	Tribune, KS
Winter wheat/Sorghum/ Fallow	201	Do.
Winter wheat/ Fallow	128	Walsh, CO
Winter wheat/ Sorghum/ Fallow	148	Do.
Winter wheat/Fallow	87	Bushland, TX
Winter wheat/Sorghum/Fallow	156	Do.
Spring wheat/Fallow	104	Average
Winter wheat/Fallow	140	Average
Cont. spring wheat	122	Average
Winter wheat/Corn/Fallow	196	Average
Wheat/Sorghum/Fallow	181	Average



## 504.05 Saline seeps

### (a) Development of saline seeps

Saline seep describes a salinization process accelerated by dryland farming practices. Saline seep is an intermittent or continuous saline water discharge at or near the soil surface downslope from a recharge area under dryland farming conditions that reduces or eliminates crop growth in the affected area because of increased soluble salt concentration in the root zone. Saline seeps are differentiated from other saline soil conditions by their recent and local origin, saturated root zone in the soil profile, shallow perched water table, and sensitivity to precipitation and cropping systems. In the recharge area, water percolates to zones of low hydrologic conductivity at depths of 2 to 60 feet below the soil surface and flows internally downslope to emerge at the point where the transport layer approaches the soil surface or soil permeability is reduced.

The saline-seep problem stems from surface geology, above-normal precipitation periods, and farming practices that allow water to move beyond the root zone.

Under native vegetation, grasses and forbs used most of the water before it had a chance to percolate below the root zone to the water table. With sod plow-up, subsoils became wetter and fallow kept the land relatively free of vegetation for months at a time. Beginning in the forties, soil water storage efficiency during fallow improved with the advent of large tractors, good tillage equipment, effective herbicides, and timely tillage operations. This extra water filled the root zone to field capacity and allowed some water to move to the water table and downslope to emerge as a saline seep.

Several factors that may individually or in combination contribute water to shallow water tables include: fallow, high precipitation periods, poor surface drainage, gravelly and sandy soils, drainageways, constructed ponds and dugouts, snow accumulation, roadways across natural drainageways, artesian water, and crop failures resulting in low use of stored soil water. Saline-seep formation begins with a root zone filled to its water-holding capacity. Some of this water runs off the surface, some evaporates, and the rest moves into the soil. Once the soil is filled to field capacity, any additional water that moves through the root zone may contribute to saline seepage.

Water percolating through salt-laden strata dissolves salts and eventually forms a saline water table above an impermeable or slowly permeable layer. The underground saline water migrates downslope and dissolves more salts, adding to the perched water table at the site of the seep. Whenever, the water table rises to within 3 feet of the surface the water plus dissolved salts then move to the soil surface by capillary action where the discharge water evaporates, concentrating salt on or near the soil surface. As a result, crop growth in the affected area is reduced or eliminated and the soil is too wet to be farmed.

### (b) Identification of saline seeps

Early detection and diagnosis of a saline-seep problem are important in designing and implementing control and reclamation practices to prevent further damage. By early detection, a producer may be able to change his or her cropping system to minimize the damage. Detection of discharge areas may be accomplished by visual or by electrical conductivity detection. Visual symptoms of an impending saline seep may include

- vigorous growth of kochia or foxtail barley in small areas where the soil would normally be too dry to support weed growth,
- scattered salt crystals on the soil surface,
- prolonged periods of soil surface wetness in small areas,
- poor seed germination or rank wheat or barley growth accompanied by lodging in localized areas,
- stunted trees in a shelterbelt accompanied by leaf chlorosis, or
- a sloughed hillside in native vegetation adjacent to a cultivated field.

Soil electrical conductivity (EC), which is proportional to soil salinity, can be determined in the field using resistivity. This technique can be used to identify and confirm an encroaching or developing saline seep. Soil salinity in the discharge area may be low near the soil surface, but increases considerably with depth. Once the discharge area is identified, the next step is to locate the recharge area. Most remedial treatments for controlling the seep must be applied to the recharge area, which is always at a higher elevation than the discharge area. The approximate size of the recharge area must be determined to be successful. Most recharge areas are within 2,000 feet and many are within 100 to 600 feet of the discharge area, depending on the geology involved.

Several procedures for identifying the recharge area include: visual, soil probing, soil surveys, drilling, soil resistivity, and electromagnetic techniques. Even if the previously mentioned equipment is not available, a visual approximation of the recharge area can be made, and strategies implemented to correct the saline-seep problem. Some facts to remember are that the recharge areas are higher in elevation than the seep or discharge area, the recharge areas are generally within 2,000 feet of the discharge areas, and that seeps in glacial till areas expand downslope, laterally, and upslope toward the recharge area. Saline seeps in non-glaciated areas tend to expand downslope, away from the discharge area. After the recharge area has been located, a management plan should be designed to control the saline-seep problem.

### (c) Effects of salinity on yields

Saline soil is a term used to characterize soil containing sufficient salts to adversely affect the growth of most crop plants. One or more of the following may cause these adverse effects:

- Direct physical effects of salts in preventing soil water uptake by the plant roots because of increased osmotic tension.
- Direct chemical effects of salt in disrupting the nutritional and metabolic processes of the plant.
- Indirect effect of salt in altering soil structure, permeability, and aeration.

Agricultural crops differ significantly in their response to excessive concentrations of soluble salts in the root zone. This ability of the plant to produce economic yields in a saline environment is termed salt tolerance. Crop selection is one of the primary options available to growers to maximize productivity under saline conditions. Table 504-9 lists the salinity threshold and yield decrease of several selected agricultural crops. The threshold salinity level is the maximum allowable salinity that does not reduce yield below that of non-saline conditions. The yield decrease is reported as a percent yield reduction for every whole unit increase in salinity measured as electrical conductivity (EC) mmho/cm. For example, alfalfa yields decrease about 7.3 percent per unit of salinity increase above 2.0 mmho/cm. Therefore, at a soil salinity of 5.4 mmho/cm, alfalfa yield would be 25 percent lower than at soil salinity levels less than 2.0 mmho/cm.

Crop production has been reduced on approximately 2 million dryland acres in the northern Great Plains of the United States and Canada. Brown (1982) reported that this production loss on 2 million acres in the northern Great Plains could be translated into \$120 million in lost annual farm income.

### (d) Management practices for control of saline seeps

Saline-seeps are caused by water moving below the root zone in the recharge area. Because of this movement of water through the recharge area, there will be no permanent solution to the saline-seep problem unless control measures

**Table 504-9** Salt tolerance of selected crops <sup>1/</sup>

Common name	Botanical name	Salt tolerance threshold (mmhos/cm)	Yield decline (% per mmhos/cm)
Alfalfa	<i>Medicago sativa</i>	2.0	7.3
Barley	<i>Hordeum vulgare</i>	8.0	5.0
Sorghum	<i>Sorghum bicolor</i>	6.8	16.0
Soybean	<i>Glycine max</i>	5.0	20.0
Wheat	<i>Triticum aestivum</i>	6.0	7.1
Wheatgrass, tall	<i>Agropyron elongatum</i>	7.5	4.2
Wildrye, beardless	<i>Leymus triticoides</i>	2.7	6.0

<sup>1/</sup> Maas and Hoffman (1977) and Maas (1990)



are applied to the recharge area. These measures vary according to the soil texture and underlying geologic material, water table fluctuations, depth to the low hydraulic conductivity zone, occurrences of potholes and poorly drained areas, and annual precipitation and frequency of high precipitation periods.

Two general procedures are available for managing saline-seeps: either make agronomic use of the water for crop production before it percolates below the root zone; or mechanically drain either surface or subsurface water before it reaches the discharge area. Mechanical drainage is generally not performed either because of current farm bill legislation or because of constraint that subsurface water is excessively contaminated with salts and downstream disposal is difficult because of physical or legal limitations. However, before any control measures are implemented an evaluation of the land capability class should be determined. All control measures should be compatible with the land capability class involved.

The most effective solution to the saline-seep problem is to use as much of the current precipitation as possible for crop or forage production before it percolates beyond the root zone. Forage crops, such as alfalfa, use more water than cereal grains and oil crops because they have deep root systems, are perennial, and have longer growing seasons. Planting alfalfa in the recharge area of a saline seep is often the most effective way to draw down stored subsoil moisture and stop water flow to a saline-seep. Alfalfa can use all current precipitation plus a substantial amount of water from the deep subsoil. Halvorson and Reule (1976), (1980) found that alfalfa growing on approximately 80 percent of the recharge area effectively controlled several saline seeps. They also found that a narrow buffer strip of alfalfa (occupying less than 20 percent of the recharge area) on the immediate upslope side of a seep did not effectively control the water in the discharge area. Grasses may also effectively draw down subsurface water if the depth to the low hydraulic conductivity zone is less than 15 feet. After terminating alfalfa or grass production, the recharge area should be farmed using a flexible cropping system.

Flexible cropping is defined as seeding a crop when stored soil water and rainfall probabilities are favorable for satisfactory yield or fallowing when prospects are unfavorable. Available soil water can be estimated by measuring moist soil depth with a soil moisture probe or other soil sampling equipment. Black et al. (1981) suggested that this cropping strategy would provide efficient water use to control saline seeps in the northern Great Plains. Brown et al. (1981) have developed soil water guidelines and precipitation probabilities for barley and spring wheat for flexible cropping systems in Montana and North Dakota.

When considering a flexible cropping system a producer should evaluate the amount of plant-available soil water at seeding time, the precipitation probabilities for the seasonal need of a given crop, and management factors such as variety, crop rotation, weed and insect problems, soil fertility, and planting date. Current information in the northern Great Plains at various locations includes yield water-use-production functions for winter wheat, spring wheat, barley, oats, millet, corn, sunflower, dry beans, canola, crambe, soybean, and safflower, given soil moisture and precipitation information. Oilseeds such as safflower or sunflower included in the rotation utilize residual subsoil moisture below the normal rooting depth of small grains while disrupting disease and pest cycles associated with cereal grain production. After successful application of control measures to the recharge area, the seep area and surrounding area can then be seeded to a grass or grass/legume mixture tolerant to the saline conditions present in the discharge area. A return to a cropping system that does not adequately utilize stored soil water in the recharge area may reactivate the seep.

Once the water flow from the recharge area to the seep has been stopped or controlled and the water table in the seep has dropped enough to permit cultivation, cropping in the seep area can begin. Crop selection is important when initiating crop production on the discharge area. In the northern Great Plains, six-row barley is the most salinity-tolerant cereal available, and it is normally the first crop seeded. As the reclamation processes continues, comparing yields in and outside the seep area can be used to monitor progress. The water table depth should be closely monitored during the reclamation period.

Another approach that can be used on discharge areas is to manage salt-tolerant grasses seeded on the area. If the water table is above 4 feet the grasses should be mowed and completely removed to prevent excess snow accumulation and the subsequent rise in the water table. If the water table is below 4 feet, the grass can be left to catch snow. The resulting snowmelt will leach the salt downward into the soil and improve subsequent grass growth. Snow trapping using grass strips or crop stubble will enhance water movement through the profile in the discharge area and hasten the reclamation process. These practices will not be effective until hydrologic control is achieved in the recharge area and the water table is significantly lowered in the discharge area. Research and farmer experience have shown that yields will generally return to normal in 3 to 5 years.

In saline-seep areas, observation wells are useful for monitoring water table levels during the control, reclamation, and post-reclamation periods. Water tables fluctuate seasonally and annually. Reclaimed saline seeps may be reactivated by a significant rise in the water table, which persists for several weeks or months. If a saline water table is less than 3 feet below the soil surface, saline water can move to the surface by capillary rise and create a salt problem. To alleviate this problem, monitoring wells at least 10 feet in depth should be installed in discharge areas, along drainage-ways, and in recharge areas. Ideally, the water table should be at least 6 feet in depth. Water table levels should be monitored monthly, especially during and after snowmelt, and rainy seasons. A rising water table that persists into the summer months indicates that cropping practices should be intensified to increase soil water use.

## Subpart 504B References

- Arshad, M.A., K.S. Gill, and G.R. Coy. 1995. Barley, canola, and weed growth with decreasing tillage in a cold, semiarid climate. *Agron. Jour.* 87:49-55.
- Bauer, A. and A.L. Black. 1990. Effects of annual vegetative barriers on water storage and agronomic characteristics of spring wheat. *North Dakota Agric. Exp. Stn. Res. Rpt. No. 112.* 16 p.
- Black, A.L. 1973. Crop residue, soil water, and soil fertility related to spring wheat production and quality after fallow. *Soil Sci. Soc. Amer. Proc.*, Vol. 37.
- Black, A.L. 1994. Managing seed zone soil water. Crop residue management to reduce erosion and improve soil quality. (Northern Great Plains) W.C. Moldenhauer, Managing Editor A.L. Black, Regional Editor. USDA-ARS Conservation Research Report Number 38.
- Black, A.L., P.L. Brown, A.D. Halvorson, and F.H. Siddoway. 1981. Dryland cropping strategies for efficient water-use to control saline seeps in the Northern Great Plains, U.S.A. *Agric. Water Manage.*, (4):295-311.
- Brown, P.L., A.D. Halvorson, F.H. Siddoway, H.F. Mayland, and M.R. Miller. 1982. Saline-seep diagnosis, control, and reclamation. U.S. Department of Agriculture, Conservation Research Report No. 30, 22 p., illus.
- Brown, T.A., A.L. Black, C.M. Smith, and others. 1981. Soil water guidelines and precipitation probabilities for barley and spring wheat in flexible cropping systems in Montana and North Dakota. *Montana Cooperative Extension Service Bulletin No. 356*, 30 p.
- Brown, T.A., and Carlson, G.R. 1990. Grain yields related to stored soil water and growing season rainfall. *Montana State University Agricultural Experiment Station Special Report 35*, 22 p.

- Gilley, J.E., S.C. Finker, R.G. Spomer, and L.N. Mielke. 1986. Runoff and erosion as affected by corn residue. I. Total losses. *Trans. Am. Soc. Agric. Eng.*, 29, 157.
- Gilley, J.E., S.C. Finker, R.G. Spomer, and L.N. Mielke. 1986. Runoff and erosion as affected by corn residue. II. Rill and interrill components. *Trans. Am. Soc. Agric. Eng.*, 29, 161.
- Gilley, J.E., S.C. Finker, and G.E. Varvel. 1986. Runoff and erosion as affected by sorghum and soybean residue. *Trans. Am. Soc. Agric. Eng.*, 29, 1605.
- Gilley, J.E., S.C. Finker, and G.E. Varvel. 1987. Slope length and surface residue influences on runoff and erosion. *Trans. Am. Soc. Agric. Eng.*, 30, 148.
- Greb, B.W. 1979. Reducing drought effects on croplands in the west-central Great Plains. U.S. Department of Agriculture, Agriculture Information Bulletin No. 420.
- Greb, B.W. 1983. Water Conservation: Central Great Plains. *In* *Dryland Agriculture*, Dregne, H.E., and Willis, W.O., Eds/ Agronomy Monogr. 23, Amer. Soc. of Agron., Madison, Wis.
- Lyon, D.J., F. Boa, and T.J. Arkebauer. 1995. Water-yield relations of several spring-planted dryland crops following winter wheat. *Jour. Prod. Agric.*, Vol. 8, no. 2.
- Maas, E.V. 1990. Crop salt tolerance. Agricultural salinity assessment and management, Amer. Soc. Civil Eng. Man. and Rep. No. 71, pp. 262-304.
- Maas, E.V., and G.J. Hoffman. 1977. Crop salt tolerance—Current assessment. *Jour. Irrig. and Drain. Div.*, Amer. Soc. Civil Eng., 103(IR2):115-134.
- Nielson, D.C. 1995. Water use/yield relationships for Central Great Plains Crops. Conservation Tillage Fact Sheet no. 2-95. U.S. Dept. Agric., ARS and NRCS; and Colorado Conservation Tillage Association.
- Nielson, D.C. 1996. Estimating corn yields from precipitation records. Conservation Tillage Fact Sheet 2-96. U.S. Dept. Agric., ARS and NRCS; and Colorado Conservation Tillage Association.
- Nielson, D.C. 1997. Water use and yield of Canola under dryland conditions in the Central Great Plains. *Jour. Prod. Agric.*, Vol. 10, no. 2.
- Peterson, G.A. 1994. Interactions of surface residues with soil and climate. Crop residue management to reduce erosion and improve soil quality. (Northern Great Plains) W.C. Moldenhauer, Managing Editor A.L. Black, Regional Editor. U.S. Dept. Agric., ARS, Conservation Research Report Number 38.
- Peterson, G.A., A.J. Schlegel, D.L. Tanaka, and O.R. Jones. 1996. Precipitation use efficiency as affected by cropping and tillage system. *Jour. Prod. Agric.*, Vol. 9, no. 2.
- Pikul, Jr., J.L., and J.F. Zuzel. 1994. Soil crusting and water infiltration affected by long-term tillage and residue management. *Soil Sci. Soc. Am. Jour.* 58:1524-1530.
- Richards, L.A. 1954. Diagnosis and improvement of saline soils. USDA, United States Salinity Laboratory Staff. *Agric. Handbook* 60.
- Steiner, J.L. 1989. Tillage and surface residue effects on evaporation from soils. *Soil Sci. Soc. Am. Jour.* 53:911-916.
- Steiner, J.L. 1994. Crop residue effect on water conservation. *Managing agricultural residues*. Ed. P.W. Unger
- Tanaka, D.L. 1989. Spring wheat plant parameters as affected by fallow methods in the northern great plains. *Soil Sci. Soc. Am. Jour.* 53:1506-1511.
- Triplett, Jr., G.B., D.M. Van Doren, Jr., and B.L. Schmidt. 1968. Effect of corn stover mulch on no-tillage corn yield and water infiltration. *Agronomy Jour.* 60:236-239.
- Unger, P.W. and J.J. Parker, Jr. 1968. Residue placement effects on decomposition, evaporation, and soil moisture distribution. *Agron. Jour.* 60:469-472.
- Unger, P.W. 1978. Straw-mulch rate effect on soil water storage and sorghum yield. *Soil Sci. Soc. Am. Jour.* 42:486.

- Unger, P.W., and A. F. Wiese. 1979. Managing irrigated winter wheat residues for water storage and subsequent dryland grain sorghum production. *Soil Sci. Soc. Am. Jour.*, Vol. 43.
- Unger, P.W. 1986. Wheat residue management effects on soil water storage and corn production. *Soil Sci. Soc. Am. Jour.*, Vol. 50.
- Unger, P.W. 1994. Residue management for winter wheat and grain sorghum production with limited irrigation. *Soil Sci. Soc. Am. Jour.* 58:537-542.
- Vigil, M.F., D.C. Nielson, R. Anderson, and R. Bowman. 1995. Taking advantage of the benefits of no-till with rainfall probability distributions. *Conservation Tillage Fact Sheet 4-95*. U.S. Dept. Agric., ARS and NRCS.

---

<b>Contents:</b>	<b>Subpart 506A</b>	<b>Vegetative stabilization</b>	506-1
	506.00	Structures .....	506-1
	506.01	General considerations .....	506-1
	506.02	Seeding and planting process .....	506-2
	506.03	Seed, plant, and amendment application rates .....	506-2
	506.04	Disturbed land .....	506-5
	<b>Subpart 506B</b>	<b>Suitability for crop production systems</b>	506-6
	506.20	Suitability for crop production .....	506-6

---

---

<b>Table</b>	<b>Table 506-1</b>	Common mulch material	506-4
--------------	--------------------	-----------------------	-------

---



---

## Subpart 506A Vegetative stabilization

### 506.00 Structures

Structures are engineered earthen water retention, conveyance, or other conservation practice components. This section deals with establishing vegetation on typical erosion control structures such as Public Law 566 dams, diversions, waterways, emergency watershed program structures, and others. These structures are designed and constructed for soil and slope stability with vegetative treatment to protect and maintain the integrity of the structure.

#### 506.01 General considerations

**Plants**—Protecting structures is typically accomplished with grasses enhanced by a legume component for some nitrogen generation. Landscaping with shrubs and trees blend structures into surrounding landforms. Species and cultivar selection and effective planting techniques are key to successful establishment. Select plants to meet the existing site conditions including internal soil drainage, soil texture and percent fine particles present, organic matter, density, pH and nutrients available from the soil, exposure and aspect, temperature zone, and plant hardiness factors. Recommended plant lists are available in each state.

Proper plant selection to meet the existing and future site use will minimize future maintenance. Cultivars that have been released through the NRCS Plant Materials program should receive first consideration. Consider using native plants if they are known to be effective. Avoid using plants known to be invasive, such as kudzu, multiflora rose, or phragmites.

**Soil**—Soil is the medium in which seeds germinate and roots grow. The condition of the soil may well determine the success or failure of seedings or plantings. Soil texture, structure, tilth, organic matter, drainage, and chemical composition need to be reviewed to be certain that compatible plants have been selected. Soil amendments should be specified to meet site and plant needs.

If topsoil is salvaged onsite, use it on the most sensitive area(s) of the structure, such as emergency spillways or faces of dams. Blend the topsoil into the surface of the structure to avoid a sharp contrast between compacted fill material and the topsoil.

**Water and wind management**—Potential erosion problems need to be considered when selecting appropriate species and establishment techniques. Water as rainfall or snowmelt, spring ice flows in streams, surface runoff, or seepage areas may require special attention. Diversions and waterways may need to be established to manage excess surface water, or subsurface drains may need to be installed to dry out seeps. Exposed areas subject to wind should be treated with adequate protection to insure establishment of the planting. This may include mulch anchoring, temporary windbreaks or using wind barrier plants.

Combinations of geotextiles, soil bioengineering (live fascines, brush mattresses) and biotechnical stabilization may be desirable to handle special conditions of erosive water velocities or areas of temporary high flows.

**Land use**—Land use surrounding the structure(s) should be evaluated to blend the disturbed area into as natural setting as possible. Plantings should be planned based on anticipated growth and appearance of the species. Blending structures with the environment will enhance the visual appearance and present a positive effect to the public.

**Geology**—Geologic investigations include the overburden material and the underlying parent material. Bedrock, changes of soil texture at various depths, and saline areas can be addressed early in the planning process when identified from the geologic review.

**Existing vegetation**—Existing vegetation can be a source of potential species that should be included in the seeding of constructed structures. It may be desirable to select species from several successional stages to include in the revegetation plan. Using species that grow on surrounding areas will help blend the structure into the landscape. Caution is needed when doing this, because local species may not tolerate transplanting or may not perform well on disturbed sites. Local ecotypes, where available commercially, would be preferred sources of plant material.

**Present and proposed use**—Consideration of the proposed future use of the structure is important in species selection. If people and vehicles will be using the area, traffic patterns should be planned. Paths should be designed to minimize erosion potential. Plants that impede recreational activities, such as vines or dense, tangled growth, should be avoided. Select vegetation that will enhance the long-term use of the area as well as provide erosion control cover needed. For example, if fishing will be allowed after a large dam is constructed, leave some grass areas without shrubs at the water's edge. Where recreational abuse of the site causes soil erosion, select plant species that will discourage the use of these areas.

**Climate—Select species for the local climate** — Rainfall and temperature vary greatly within a state. Exposure to wind may create a sandblasting problem on the plants or may result in desiccation of the plants. Site aspect (north facing slopes) may result in several degrees difference in temperature. The USDA Plant Hardiness Zone Map, Misc. Pub. No. 1475, 1990, can serve as a general guide for selecting plants. The Plant Zone map may be viewed on-line at

<http://www.usna.usda.gov/Hardzone/>

However, local conditions may offer protection or may create exposure that will influence the plant performance.

**Shade tolerance**—Where structures will be shaded for part or all day, be sure the species are tolerant for the anticipated condition. If canopy cover closure is anticipated in the future, then include appropriate ground cover species to meet the future site condition.

**Site preparation**—The area before construction should be reviewed to select and preserve any highly desirable plants or section of plants near the perimeter or edge of the construction zone. Endangered, threatened, or declining species considerations must be met before construction. Install any temporary wind or water control measures. If topsoil or other organic matter is available onsite, salvage as much as is economically feasible. Do not waste it by burial or other loss.

## 506.02 Seeding and planting process

Seeding should be done as construction is completed or at intervals during construction. Daily or regular time interval seedings may be mandatory where site location or local laws require this. Frequently, daily seedings are planned for temporary erosion control until the work for the entire project is completed. Then the areas will be reseeded to permanent vegetation at an appropriate planting date.

**Seedbed preparation**—The objective in seedbed preparation is to create a condition where seed can be planted, emerging seedlings will have a favorable microenvironment, and the surface area will be such as to allow the type of maintenance required to support protective vegetative cover.

During this operation, soil amendments such as lime, gypsum, or fertilizer should be applied. Also, remove large stones (generally greater than 1 to 2 inches in diameter for areas that will be lawns or parks, and greater than 4 to 6 inches in diameter for other areas) and debris that will hinder seeding or planting and future operations and maintenance.

Seedbed scarification may be required unless seeding is accomplished within 24 hours of final grading. Sand and gravel (sites with less than 20% fines passing a 200 mesh) do not require scarification as long as moisture is adequate. When the surface soil is powdery, the soil is too dry for seeding. If clumps of mud stick to the planting equipment, the soil is too wet unless a hydroseeder or other suitable equipment is used.

Areas of compaction should be identified and ripped or scarified to a depth of at least 9 to 12 inches to create a more favorable rooting zone. Topsoil (if available) should be applied and blended with the surface of the structure. All tillage operations should be performed on or as close to the contour as possible. The balance of the area should be scarified or loosened to a minimum of 3 inches to allow good soil to seed contact. Scarification may be waived if the seeding is accomplished immediately after the final grading is finished and site conditions warrant this approach.



### 506.03 Seed, plant, and amendment application rates

**Seed and plant rates**—General seeding rates and planting quantities of adapted species or mixtures are available in the NRCS Field Office Technical Guide (FOTG), Section IV, Critical Area Planting Standard 342.

**Seed or plant specifications, or both**—To insure the quality all planting material, specify genus, species, cultivar (if applicable), specific inoculant, and percent pure live seed or minimum seed germination. All seeds should meet Federal and state seed laws for proper labeling and noxious weed content. Criteria for shrub and tree quality, size and type of plant material should be based on standards in the publication *American Standards for Nursery Stock*, developed by the American Association of Nurserymen.

**Time of seeding or planting**—Specify appropriate planting dates. Spring seedings may be adequate where normal rainfall is available. However, the effect of annual weeds and midsummer droughts should be considered. Fall seedings in many parts of the country have the advantage of more reliable precipitation and favorable temperatures. In addition, in the northern states, the annual weeds are generally winter killed.

Cool-season grasses generally do best when seeded in the fall. However, construction will often be completed during periods of the year when seedings should not be made. In these cases, temporary seeding or mulching should be done and the permanent seeding made at the optimum time of year for the species used.

Warm-season grasses are normally seeded in the spring. Some fall seedings are successful providing weather conditions remain cold and the seed remains dormant. In general, warm-season grasses should have about 100 days of growing season remaining after planting.

Where soil or site conditions limit available moisture, such as sandy or rocky soils, a temporary irrigation systems can help insure adequate establishment of vegetative cover. Irrigation can be used on earth-fill structures if care is taken to apply only amounts necessary. If the system is not operated properly, irrigation water induced erosion can occur. Steep slopes (3:1 or steeper) are generally too hazardous on which to set irrigation pipe, plus the erosion potential is too great.

**Soil amendments**—The desired soil pH will depend on the plant species selected and long-term goal of species composition. Acid soil should generally have the pH adjusted to 5.5 or higher for grasses and 6.0 if legumes are to be used. This will allow the rhizobium bacteria associated with legume roots to function. Ground agricultural limestone, either calcitic (high Ca) or dolomitic (high Mg) is used. The most desirable ratio is a Ca:Mg ratio of 10:1; however wider ratios are acceptable. High pH or saline soil may require gypsum ( $\text{CaSO}_4 \cdot 2\text{H}_2\text{O}$ ) application. A detailed soil analysis should be used to determine the type and amount of nutrients needed. Usually high levels of some elements may be toxic, and special steps may be needed to amend these areas. Add only the amount of nutrients required to produce adequate vegetative cover.

**Method of seeding or planting**—Many techniques are available that have proven successful. Site conditions will dictate options.

Steep slopes on which regular seeding equipment cannot be safely operated must be seeded by broadcasting the seed, blowing it on, or by hydroseeding (applying seed, and sometimes soil amendments and mulch, in a water slurry or suspension). For hydroseeders, coverage is limited by the size of equipment, wind conditions, and stream load. Centrifugal seeding equipment requires dry weather conditions and limited wind interference. High-velocity blowers are normally used for sites where it is difficult to hold seed in place, or sites that are inaccessible by large equipment. These blowers will force some of the seed into the soil and crevices for germination. For this method to work properly, the soil must be moist. Some delicate seeded species may experience seed damage.

Calibration of hydroseeders or blowers is difficult. Experienced operators usually will be able to uniformly apply seed by estimating the land area and applying tank loads at acceptable rates. Hydroseeders frequently add colored mulch to mark the area covered.

Another technique for steep slopes is to use a track type bulldozer to incorporate seed and amendments. Operate the bulldozer up and down the slope. The cleat tracks create areas in which seed may be trapped. Soil migrating down the slope will cover the seed and the indentations in the bank hold additional moisture. This works well on sands and gravel.

On flatter areas, additional equipment is available to better place the seed into the soil and in arid regions, to better take advantage of soil moisture.

Imprinting works well to allow for deep placement of seed. This allows for access to moisture and affords the germinating seedling some wind protection.

Special grass drills with packing wheels and other special features are available. Warm season grass boxes are available to handle the fluffy prairie grass seed. These units have devices within the boxes to prevent the *bridging* of seed, resulting in even seed flow.

Broadcast seeding with an airflow spreader is an acceptable seeding method for some species and purposes.

Herbaceous planting material, such as bermudagrass sprigs, American beachgrass cuttings or trees requires special knowledge and handling. Internal heating of this material frequently occurs during shipping and storage. The damage to the growing points may go undetected by an untrained

person until the plants do not grow. During delivery and planting, every effort should be made to keep the plants cool and moist to insure good survival and growth.

**Mulching** — Mulching is an important process in establishing vegetation (especially cool-season grasses) on structures or other critical areas. Mulch cover will help maintain favorable moisture conditions, prevent soil erosion by water or wind, hold seed in place, and maintain cooler, more constant soil temperatures. Mulch should be applied immediately after seeding (within a few hours or less). It should be uniformly applied at the specified rate.

Mulch material (table 506–1) is not all equal in providing the optimum conditions for germinating seeds. Small grain straw is the preferred material for most sites. This material generally has few weed seeds and provides the best results of any tested material. Grass or mixed legume and grass hay is good but frequently has weed and hay seeds that may also grow and compete with the desired seeded species for moisture, nutrients, and light. This is a problem with warm-season grass plantings. It does not make much sense to use cer-

**Table 506-1** Common mulch material

Mulch material	Quality standard	Application rate	Remarks
Hay, small grain straw	Air-dried; free of mold; free of noxious weeds.	2 tons per acre.	Subject to wind blowing unless anchored; cover about 90% of soil surface.
Wood excelsior	Green or air-dried burred wood fiber.	2 tons per acre.	Decomposes slowly; subject to blowing unless anchored; pack aged in 80-90 lb bales.
Wood fiber cellulose	Partially digested wood fiber; usually with green dye and a dispersing agent.	2,000 lb per acre.	Apply with hydroseeder; used as an anchoring material for mulches subject to blowing.
Jute mat - twisted yarn	Undyed, unbleached plain weave; warp 78 ends/yd; weft 41 ends/yd; 60–90 lb rolls.	48 in x 50 yd or 48 in x 75 yd.	Use without additional mulch; secure as per manufacturers' specification.
Excelsior wood fiber mats	Interlocking web of excelsior fibers with photodegradable plastic netting.	48- x 100-inch 2-sided plastic or 48- x 180-inch 1-sided plastic.	Use without additional mulch; secure as per manufacturers' specification.
Straw or coconut or combined mats	Photodegradable plastic net on one or two sides.	6.5 x 83.5 ft, 81 rolls per acre.	Designed to withstand fiber individually specific water velocities.

tified seed and then throw weedy mulch over the seeding. Other fibrous material such as coconut fiber, excelsior fiber and wood fiber all may be used. Economics will sometimes dictate which mulch material is used. Many latex compounds and commercial products will control erosion and hold seed in place under some moisture and temperature regimes.

Competition is a problem with warm-season grass plantings. Consider alternatives to mulching when warm-season grasses are seeded in northern regions. An oat cover crop, seeded in the fall, will grow enough to protect the soil. Because it will winter kill, the residue will be present in the spring to prevent erosion, but not compete with the warm-season grass seedlings.

Mulch material can be selected from the list below. Use appropriate materials for the location. The optimum mulch material for cool season grasses and legumes is small grain straw at 4,000 pounds per acre, anchored with 500 to 750 pounds wood fiber hydromulch. This will provide optimum conditions for rapid germination and establishment.

**Mulch anchoring**—Once mulch is applied, it must remain in place. Few if any of the seeded species will establish in bare areas from which the mulch has moved. On critical sites that are droughty and wind swept, mulch anchoring must be performed to obtain uniform establishment. The cost of establishing erosion control cover is frequently justified, and reducing the area needing reseeding offsets this cost. Mulch anchoring material selection and application rate is important to establish some species.

Material for anchoring fibrous material ranges from wood fiber hydromulch to latex compounds to asphalt emulsion, to mesh netting, to mulch blankets. All are excellent for specific situations. Follow manufactures recommendations for use. Selection is dependent on the intended use, cost, and available labor or equipment.

A wide assortment of implements is available to anchor mulch by incorporating some of the mulch into the soil surface.

Ultimately, the local growing conditions will dictate the outcome of the seeding. If a short-term drought occurs as the seed is germinating, allowing the mulch to be blown around or removed from the site during this time may result in a seeding failure. This is especially critical on droughty soils and for spring seedings.

## 506.04 Disturbed land

### (a) Planning principles

Vegetative treatment of disturbed land areas requires some planning to overcome many potential problems. These include water and wind management concerns, sedimentation, potential limiting or excess elements on site, intended land use, length of time the area or partial area must be exposed for continued construction, existing slope and planned slope and slope length, and presence or absence of vegetation. The kind of soil and drainage class will influence the type of plant desired.

Water and wind erosion concerns must be dealt with before establishing vegetation. Plants tolerant to wind may be used to protect areas before establishing more permanent and desirable species, or temporary wind breaks (wind fence) may be used. Plants tolerant of inundation or wetness may be required along with regrading or shaping portions of the site to divert or retain water. If the site requires grading and leveling, salvage as much topsoil and existing as possible. Shape and grade for intended future use. Areas planned for sports or other types of recreation require considerably more attention and detail than an area being reclaimed for wildlife habitat.

If a site is barren of vegetation, or nearly so, the cause needs to be determined before trying to establish vegetation. Past use or history of industry may provide clues to the lack of vegetation. Old garage areas or motor pool areas may have petroleum contamination or battery acid spills. Mining operations or industrial sites may have dumps associated with them, in which chemicals associated with the industry were disposed. By asking questions about the past use, the planner can then begin piecing the puzzle together. Testing for residual material or chemicals is the only way to confirm what is present.

Soil physical barriers such as restrictive or compacted layers in the rooting zone need to be identified and corrected. Soil sample analysis for particle size distribution may be required. Several plants may be available for use on soil that has 40 percent fines but fewer are suitable if the fines are less than 15 percent. Select plants for the long term, not ones that will grow well for 1 or 2 years. For example, use of ryegrass and cool season grasses on sand and gravel areas will grow and provide temporary cover. However, when the fertilizer is depleted and moisture becomes deficient, the cool-season plants will die off. If switchgrass and other warm-season grasses are used, they will persist for more than 20 years while natural succession occurs.

Fertility levels need to be assessed before selecting the appropriate plants. Percent organic matter, potentially toxic levels of elements, and pH are interrelated, and they need to be quantified before treatment.

The natural plant succession for the area should be considered, especially when selecting species to use. It may be desirable to select species from several successional stages to include in the revegetation plan. Use plants that blend to the surrounding areas. Avoid selecting invasive species. Biotechnical or soil bioengineering options should be evaluated for unstable slopes. The use of live fascines or brush layering techniques should be considered in lieu of more expensive stone gabion baskets and riprap. Chapters 16 and 18 of the Engineering Field Handbook detail these techniques.

**(b) Unique critical areas**

**Strip-mined areas**—Strip mining is the removal of overburden to gain access to some mineral or fuel. The spreading or dumping of this overburden material frequently exposes contaminants. Coal mining in the Appalachian Mountains frequently exposes sulfur and iron, the oxidation of which results in the formation of acid materials. The best solution is to cover this acid-forming material during the mining process. If left exposed, the soil pH can become extremely low, causing any aluminum in the soil to become available for plant uptake. When this occurs, the plants selected must be tolerant to potential aluminum toxicity. Because of exposure, slope, and rock, these sites are frequently very droughty.

The sequence of mining operations can be the best management practice and provide for minimizing future toxic areas through proper closing of mined areas. This requires saving the overburden and replacing it on the surface in proper sequence before vegetating the area.

**Mine tailings**—Areas covered with waste material from mining operations may be high in heavy metals, or have other chemical or physical conditions that make vegetative establishment difficult or impossible. Covering this material with a minimum of six inches of borrow material from surrounding areas may be necessary to establish vegetation, stabilize the site and help insure the long-term survival of desirable vegetation.

**Coastal and inland sands and sand dunes**—Areas of blowing sand need wind erosion control measures. This may be accomplished using plants such as American beachgrass or with windbreaks or other physical structures. On inland sands, planting single or double rows of American beachgrass or other appropriate plants, perpendicular to the prevailing wind erosion direction, will provide protection for establishing more permanent vegetation. Spacing between rows should be ten times the anticipated height of the plants after one growing season. Wait one year before seeding the permanent vegetation.

## Subpart 506B Suitability for crop production systems

### 506.20 Suitability for crop production

Crop selection in a properly designed rotation is critical to maximize rotational benefits. A properly designed crop rotation provides an excellent tool in breaking insect, weed and disease cycles (Refer to Part 503, Subpart A, Crop rotation).

In the past 10 years there has been a major shift in agriculture toward crop production systems using higher amounts of surface residue. In the United States between 1989 and 1997, there has been a 13.5 percent increase in cropland acres involved in some form of residue management. During this same time period the acres in no-till crop production systems have increased 10.1 percent. One of the consequences of this change in crop production systems is that less seedbed modification though tillage is occurring while placing greater reliance on crop selection and variety or hybrid characteristics. Conservation tillage or no-till methods require changes in machinery, fertility programs, and pesticide use. In addition, crop and seed selection must also be reevaluated. Selecting a more desirable variety or hybrid should not be a substitution for properly designed crop rotation.

After a proper rotation has been designed, two primary areas of crop selection need to be evaluated in depth: variety or hybrid performance and after-harvest seedbed characteristics for the next crop in the rotation.

#### (a) Variety or hybrid performance characteristics

In crop production systems using higher amounts of surface residue, the importance of desirable variety or hybrid characteristics varies among crops. Some important common characteristics to consider are high-quality seed, the right maturity for the geographic area, good early season emergence, good early season seedling vigor, consistent performance across soil types, vigorous root development and disease and insect resistance.

Of these characteristics, choosing high-quality seed, those with the right maturity for the geographic area, and that consistent performance are not just characteristics for high residue situations but are universal among tillage systems.

However, because of the cooler and wetter seedbeds normally encountered in high residue situations, these characteristics are not only important but may also need to be modified. An example would be a warm-season grass such as corn. Selecting hybrids 5 to 10 days earlier in maturity may be necessary when planting into heavy residues. In addition, consistent performance across various soil types is important, because it is a sign that the hybrid can withstand stress under varied environmental conditions.

Early season emergence and seedling vigor become of greater importance specifically with warm-season crop species when cooler, wetter soil conditions are the rule. Selecting varieties or hybrids with good early emergence and early seedling vigor is necessary where soil conditions that have more stored soil moisture and will be cooler and wetter. Crops under these conditions must germinate quickly and have good early season growth potential to provide the necessary competitive edge required against early weed competition. Treating crop seeds with fungicides can help offset these potential negative effects of planting in high residue conditions.

The selection of varieties or hybrids that can develop vigorous root systems without the help from conventional cultivation is also a very important characteristic for reduce till or no-till system. Some hybrids or varieties also produce a stronger stem or stalk that translates into consistent performance and may contribute to a more durable residue cover following harvest. When selecting varieties and hybrids for superior root and stem characteristics, inquire whether these characteristics have been evaluated under reduced tillage or no-till conditions.

Tolerance to common insect and disease can be important depending on the area and crop rotation. This can be especially true when the crop to be planted is closely related to the preceding crop in the rotation, such a cool-season grass planted into a cool-season grass. Another example might be planting soybeans in field with heavy surface residues and poorly drained soils. Selecting soybean varieties for phytophthora root rot resistance may be a major advantage in these fields. An important point to mention again is that the selection of varieties with insect or disease tolerance is not a substitution for rotation.



**(b) After harvest seedbed characteristics for the next crop in the rotation**

Previously, modifying the seedbed in preparation for the next crop was done with tillage, either conventional (plow, disk, arrow), or in recent years, by building ridges (ridge till), or fall and spring strip till methods. In high-residue cropping systems, residue characteristics such as the amount, color, resistance to decay, and stubble height of residue left after harvest can affect the seedbed characteristics for the next crop. These characteristics can be an advantage if properly managed, or they can be an obstacle to good production advantage or can be an obstacle if not properly incorporated into a cropping system.

Residue levels and residue color affect soil temperatures. High levels of residue keep the soil cool longer because the residue absorbs or reflects the sun's energy. After crops such as corn or grain sorghum, which can produce high levels of surface cover, the soil will warm up slower. When dealing with heavier amounts of residue from the preceding crop, it may be necessary in no-till situations to use residue managers that move the residue off to the side of the seed slot. Dark-colored residue, such as that produced by oilseed and legume crops, absorbs the sun's energy and transfers it to the soil, causing it to warm up faster than if the residue was lighter colored.

Warm-season species such as corn or sunflower respond to warm, clean seedbed conditions. These conditions can be obtained by managing the type and amount of residue from the preceding crop. For example, soybeans produce relatively low amounts of residue that is dark colored. After soybeans, the seedbed for subsequent crops will be mellow, warm, and very conducive to fast, uniform emergence.

Other crop species may benefit from the micro-environmental conditions produced by high amounts of surface residue. Cool soil conditions are not a concern when seeding winter wheat. However surface moisture and sufficient standing stubble to catch snow are important factors to consider. Surface residue helps prevent the soil from drying out or cooling down too rapidly, extending the fall growing period for winter wheat. For another example, soybeans are sensitive to heat, drought, and high soil temperatures. Heavier surface residue levels improve soybean performance under these conditions.

When higher amounts of surface residues are desirable for crop production, the inclusion of a crop with more durable residue characteristics may be necessary. As surface residues increase, microbial populations in the upper one or two inches of soil also increase, which increases the rate of decay of these residues. Including a crop residue is more resistant to decay, such as corn, sorghum, or sunflowers, will help increase surface residue levels.

Stubble height of previous crop residues can be very beneficial in increasing soil moisture and can increase the survival of fall-planted crops. In the northern Great Plains, increasing stubble height traps more snow on the field, increasing the available water for crop production. Stubble height can be increased by setting the combine header higher, or by using stripper headers to harvest grain.

Taller stubble heights can also moderate air and soil temperatures, improving the survival of winter wheat and increasing the effective range of the crop further north. The maximum winter wheat hardiness is obtained with winter wheat planted into standing small grain stubble. However, when winter wheat is planted following another small grain, varieties with tolerance to leaf spotting diseases should be considered in some environments. Managing stubble height coupled with selecting disease-tolerant varieties allows higher yielding varieties with less winter hardiness to be planted further north than was previously possible.

---

## **Subpart 506C    References**

American Nursery and Landscape Association. American Standard for Nursery Stock. 1997.57pp.





---

<b>Contents:</b>	<b>Subpart 507A</b>	<b>Major cropland practices</b>	507-1
		507.00 Cropland conservation management systems .....	507-1
		507.10 Cropland conservation management systems—humid east .....	507-1
		507.11 Typical cropland resource concerns .....	507-1
		507.12 Purposes, effects, and impacts of the major cropland conservation .....	507-1
		management systems	
		507.13 Economics of the major agronomic practices/treatments .....	507-2
		507.20 Resource concerns and effects-dryland regions of the Great Plains .....	507-4
		and western United States	
		507.21 Defining and describing dryland regions .....	507-5
		507.22 Regional resource settings of dryland cropping areas of the United States ....	507-5
		507.23 Principles and guidelines of dryland conservation Management systems .....	507-5
		507.24 Factors in planning dryland cropping systems .....	507-8
		507.25 Major cropping systems and technologies for the dryland regions .....	507-8
		of the United States	
	<b>Subpart 507B</b>	<b>References</b>	507-10

---

<b>Table</b>	<b>Table 507-1</b>	Example of major purposes and expected effects of commonly used conservation practices/treatments on cropland	507-3
	<b>Table 507-2</b>	Climatic zone delineation	507-5
	<b>Table 507-3</b>	Major cropping systems and water and soil conservation management technologies for U.S. dryland agricultural regions	507-9



## Subpart 507A Major cropland practices

### 507.00 Cropland conservation management systems

The development of sustainable cropland conservation management systems involves effective conservation planning. This conservation planning process views the agro-ecosystem as an integration of complex natural physical, chemical, and biological functions. Our look back at history should convince us that undertakings to *manage* agro-ecosystems as a natural resource must consider the entire system rather than just the parts. Nothing less than managing for the *whole* or health of the agro-ecosystem is acceptable. Managing for the health of the agro-ecosystem requires acceptance of a holistic approach to conservation planning to achieve some degree of sustainability.

The same general principles that Hugh Hammond Bennett set forth in 1947 are still applicable in the development of effective conservation management systems on cropland. The principles are summarized as follows:

- Consideration and focus on the producer's goals. As a part of this goal setting process, an evaluation is made of the producer's farm and livestock facilities, machinery, and economic situation. The product of this principle results in the establishment of three action statements that further define the goal. The statements are
  - the quality of life that the producer wants derived from the agro-ecosystem;
  - the forms of production and management tools required to deliver the quality of life; and,
  - a description as to what the farm's landscape or the desired future condition is to look like (Savory 1988).

Also, the description includes the producer's expectation of the farm's production ability to be sustained.

- Evaluation of the needs and capability of each cropland acre.
- Incorporate the producer's willingness to implement and adapt new technology and practices.
- Consideration of the landscapes relationship and function to the entire farm and watershed.
- Continued presence of the conservationists with the producer. In any holistic approach to management of the agro-ecosystem there is a requisite for monitoring and assessment of the function of the system.

In addition, there will be assessment indicators and events that will demand re-planning. In many cases the specific management tools will need to be altered, or in some cases a current tool is abandoned and a different one implemented.

### 507.10 Cropland conservation management systems—humid east

#### 507.11 Typical cropland resource concerns

One or more of the resource problems listed are a concern on cropland in the humid east of the United States.

- Erosion from water or wind, or both
- Soil condition
- Soil compaction
- Available water (too much, too little)
- Pests (weeds, insects, diseases)
- Soil/plant nutrient management
- Quality of runoff or ground water, or both
- Pesticide management, selection, drift, leaching, runoff, and resistance
- Economics
- Compliance with USDA programs and other Federal, State, and local laws

### 507.12 Purposes, effects, and impacts of the major cropland conservation management systems

Practices/treatments used to address the resource concerns about cropland situations often have complimentary effects on the resource concerns. For example, by selecting a rotation of different crops (conservation crop rotation practice) to meet soil erosion, soil condition, and producer needs; the practice also has complimentary effects on reducing weed, disease, and insect pressures (pest management practice). Likewise, a practice/treatment selected to treat one concern may have an adverse effect on another resource concern. For example, the use of the no-till practice may be effective to reduce erosion, improve soil condition, and reduce nutrient and pesticide runoff; but no-till may have an adverse effect on the production system if a proper crop rotation and nutrient and pest management are not implemented at the same time. Therefore, as a cropland management system is planned, it is critical to understand all the effects of the practices/treatments being considered on the total production system.

Table 507-1 has examples of some of the major purposes and expected effects of the most commonly used practices/treatments on cropland. The purposes identified are expressed in the National Practice Standards as well as additional purposes/effects for local consideration.

Conservation management systems for cropland include a combination of practices/treatments necessary to address existing and anticipated soil, water, air, plant, animal, and human resource concerns, and treat all the concerns to a minimum acceptable level. Cropland involves the growing of annual or a mixture of annual and perennial crops. To produce crops requires the continued management of soil, water, air, plants, and their associated components to meet the objectives of the producer and to maintain a sustainable production base.

A large number of potential practices/treatments can be used on cropland. However, there are few major practices/treatments that form the foundation (or core) of most cropland conservation management systems. The major practices/treatments that form the core of cropland management systems involve those that relate to the

- selection and rotation of crops,
- tillage or planting system (crop establishment),
- residue management,
- fertility management, and
- pest management.

Other major practices/treatments include irrigation management, surface and subsurface water management, contouring, buffer strips, and filter strips.

To successfully produce crops in an economical and sustainable manner requires an accurate assessment of the resources' (soil, water, air, plants, animals, human) capabilities and limitations. The core practices of crop rotation, timing and type of tillage, how the residue is managed, nutrient management, and pest management are almost always involved to address the capabilities and limitations (resource concerns) of any cropland management system.

Other common practices/treatments used in cropland management systems include

- cover crops,
- cross wind strips,
- waste utilization,
- subsoiling,
- terraces,
- subsurface drainage,
- surface drainage,

- grassed waterways, and
- water and sediment control basins (control concentrated flow/gully erosion).

Cropland management systems must address the following:

- Crop(s) to be grown within the resource capabilities and limitations.
- Producer's needs and concerns.
- Crop(s) establishment.
- Residue management.
- Nutrient management.
- Pest management.
- Soil water management.
- Sustainability of the management system.

The first step in developing a cropland management system is to fully assess the resource capabilities and limitations (a resource assessment) and determine the producer's capabilities, limitations, and objectives. This will establish the baseline to begin to build an effective conservation management system for cropland. One must also keep in mind that although different cropland systems may have the same practices planned, the treatment within those practices may be different to meet different purposes. In addition, cropland systems with the same combination of practices but planned for different purposes may have different effects on the resources and concerns.

### 507.13 Economics of the major agronomic practices/treatments

To assess the economics of the agronomic practices is often difficult. The traditional method used to assess the economics of various agronomic practices is to compare different methods to achieve a given treatment or purpose. For example, a seedbed must be prepared for planting. One method would be to use mulch-till and compare that cost to using no-till. It is critical that the costs involved in agronomic practices/treatments be carefully analyzed. For example, in the mulch-till vs. no-till scenario mentioned previously, if the producer owns both mulch-till tools and no-till tools, one can only evaluate operation and maintenance costs of the equipment because the costs of the equipment are already incurred regardless of the system used.

Most agronomic type practices/treatments do not require a direct outlay of cash. Many of the practices and treatments are often more of a change in management techniques rather than a formal installation.

**Table 507-1** Example of major purposes and expected effects of commonly used conservation practices/treatments on cropland

Practice/treatments and National Practice Standard code	Purposes and effects
Conservation crop rotation Code 328	Reduce sheet, rill, and wind erosion Produce needed feed for livestock Produce needed residue for soil organic matter Manage soil nutrient levels Improve soil condition, tilth, health Manage or break pest cycles, or both Improve wildlife food and cover
Residue management Code 329 series No-till and strip-till (A) Mulch till (B) Ridge-till (C)	Reduce sheet, rill, and wind erosion Improve air quality (reduced dust and soil particulate in the air) Improve soil condition, tilth, health Improve soil available water content Reduce nutrient and pesticide runoff Reduce sedimentation Reduce trips across the field (compaction potential) Reduce time demands for seedbed preparation Reduce cost of equipment and field operations Improve wildlife cover
Residue management, Code 344 Seasonal	Reduce sheet, rill, and wind erosion Provide residue for livestock grazing Provide food and cover for wildlife Manage available soil water Reduce runoff during selected times of the year
Contour farming Code 330	Reduce sheet and rill erosion Reduce power requirements Improve soil available water content Reduce surface runoff Reduce nutrient and pesticide runoff Safety during field operations
Contour buffer strips Code 332 Contour stripcropping Code 585 Field stripcropping Code 586	Reduce sheet, rill, and wind erosion Improve soil condition, tilth, health Improve soil available water content Reduce surface runoff Reduce nutrient and pesticide runoff Reduce sedimentation Reduce power requirements

To select the most cost-effective cropland management system, first develop two or more alternative management systems that adequately treat the resources and meet the producer's objectives. Then evaluate each system, comparing the total costs to implement each system to the expected impacts and returns of that system.

### 507.20 Resource concerns and effects-dryland regions of the Great Plains and western United States

In discussing major cropland management practices within the Great Plains and western regions of the United States, a distinction must be made between the term's *dryland* and *rain fed*. Rain-fed agricultural systems can be used to describe agricultural systems that exclude irrigation as a water source and generally fall into two categories. The first category of rain-fed agricultural systems are those that emphasize maximum crop yields, significant production inputs, and disposal of excess water, while the second category of rain-fed agricultural systems characterize the *dryland* systems (Stewart 1988; Stewart and Burnett 1987).

Several investigators have proposed various definitions of *dryland* or dry farming (Duley and Coyle 1955; Hargreaves 1957; Higbee 1958). Common to all definitions, these "dryland" systems are those which describe production techniques under limited precipitation and usually severe resource concern constraints. The resource constraints include soil erosion by both wind and water; periods of water stress of significant duration; and limited production inputs. Another distinction is that the *dryland* systems focus on crop yield sustainability and water conservation/water harvesting techniques. To further define *dryland* Oram (1980) has suggested six criteria to be used in describing dryland regions and systems:

1. Occurrence of very high intensity rainstorms.
2. Potential evapotranspiration exceeds the precipitation for a minimum of 7 months during the year.
3. Decreased reliability and increased precipitation variability as annual precipitation decreases.
4. Low total annual precipitation accompanied with at least one pronounced dry season.
5. Large annual precipitation variations from year-to-year.
6. Large monthly variations in precipitation.

**Table 507-1** Example of major purposes and expected effects of commonly used conservation practices/treatments on cropland—Continued

Practice/treatments and National Practice Standard code	Purposes and effects
Nutrient management Code 590	Provide the necessary nutrients for plant growth Manage soil fertility at desirable and economic levels Reduce nutrient leaching and runoff
Pest management Code 595	Manage weeds, insects, and diseases within established threshold levels Reduce Pesticide runoff and leaching Reduce pest tolerance and resistance to cultural, biological, and chemical treatments
Filter strips Code 393	Reduce offsite sedimentation Reduce nutrient and pesticide runoff Biologically treat runoff Improve infiltration and treatment of runoff Provide food and cover for wildlife

### 507.21 Defining and describing dryland regions

A number of attempts have been made to quantitatively describe and categorize dryland regions. The older accepted approaches generally included some form of the Thornthwaite precipitation effectiveness index (P-E) are presented and reviewed elsewhere (Bregle 1982).

Stewart (1988) reviews two methods hereby referred to as the FAO method and the UNESCO (United Nations Educational, Scientific and Cultural Organization) method. Based on the length of growing season the FAO method delineates dryland climatic regions as dry, arid, and semiarid. The UNESCO method delineates four dryland zones (hyperarid, arid, semiarid, subhumid) based on an index, called the climatic aridity index. Both methods use daily values of precipitation (P) and potential evapotranspiration (ETp). Since daily values are evaluated, an appropriate energy balance method for estimating ETp for short time steps should be used. This would include the Penman method or one of its several variations based on local conditions and available data.

**FAO Method.** The length of the growing period in the FAO method is the number of days that have a mean daily temperature greater than 44 degrees Fahrenheit (6.5 °C) during the year when P is greater than 50 percent of ETp (0.5 ETp), plus the number of days required to use about 4 inches (10 cm) of stored soil profile water. Regions classified as dry are those where P never exceeds 0.5 ETp; arid where the length of the growing period is between 1 and 74 days; and, semiarid where the growing period is between 75 and 119 days.

**UNESCO Method.** The UNESCO method uses the climatic aridity index. The climatic aridity index (CAI) is the ratio of the precipitation (P) to the potential evapotranspiration (ETp) ( $CAI=P/ETp$ ). The four climatic zones are delineated in table 507-2.

### 507.22 Regional resource settings of dryland cropping areas of the United States

In the United States and Canada, six distinct dryland-farming regions can be identified. The six regions are the Southern Great Plains, Central Great Plains, Northern Great Plains, Canadian Prairies, Pacific Northwest, and the Pacific Southwest (fig. 507-1). Also shown are the five specific areas of dryland production.

Common to all of the regions is the non-beneficial use of soil water through evaporation and the practice of summer fallow. There are, however, a number of general distinctions other than crop adaptability that can be made between the regions. The distribution and types (snow versus rainfall) of precipitation differ greatly. Snow management can be used effectively to increase soil water storage in the northern regions. Detailed descriptions of these regions are in Cannell and Dregne (1983).

### 507.23 Principles and guidelines of dryland conservation Management systems

#### (a) Basic principles

In natural ecosystems the successional process advances until something limits it. Moreover, as succession continues, the complexity, diversity, and stability increases (Savory 1988). The result of a complex, diverse, and stable ecosystem is increased productivity. Secondly, everything that occurs within an ecosystem can be described in terms of the effectiveness, or lack of effectiveness in the water cycle, nutrient cycle, succession itself, and the flow of carbon (energy) through the ecosystem.

The same concepts can certainly be applied to dryland agroecosystems. The successional process in a natural system is analogous to the sequence of crops in rotation. Like natural systems, the successional process of dryland systems can advance until something limits it. In most cases, this limiting factor is climate. The holistic approach, though, teaches us that there may be additional limitations. The most common of these include economics and market forces.

**Table 507-2** Climatic zone delineation

Zone	CAI
Hyperarid	$CAI < 0.03$
Arid	$0.03 < CAI < 0.20$
Semiarid	$0.20 < CAI < 0.50$
Subhumid	$0.50 < CAI < 0.75$



The underlying principles directed at the development of a sustainable dryland cropping system include three elements. These elements are:

- rotation intensity,
- rotation diversity, and
- management.

First, any given crop rotation must have a crop succession of sufficient intensity to assure maximum use of effective precipitation.

Secondly, the crop rotation must have sufficient diversity, which is central to the whole-system management philosophy. Agroecosystem diversity is more than the interaction and manifestation of physical and biochemical processes. It includes all of the concepts related to not only the promotion of effective nutrient cycling and expansion of disease and weed control strategies. Diversity also considers human and economic factors, in that the crop rotation must have sufficient diversity for distributing workloads and economic risks. Gleissman (1998) outlines six specific benefits and characteristics of diverse agroeco-systems. The following can be identified and applied to the dryland areas:

- Greater stability and diminished external input requirements. Stability not only includes the lack of fluctuating crop yields; but also includes the ability to spread out workload and fixed costs; and the reduction in weather and price risks.
- Greater harvestable biomass production potential.
- Larger soil carbon pool resulting from increased total biomass.
- Diminished need for external nutrient inputs resulting from efficient nutrient cycling.
- Reduced risk of economic crop loss resulting from greater species diversity.
- Increased opportunity to break insect and disease cycles; and potential for effective application biological control strategies.

Thirdly, the crop rotation that has sufficient intensity and diversity must be managed properly. The proper management levels include using tillage and planting methods that reduce soil disturbance and renewing dependence on cultural practices that will reduce reliance on costly technology.

### (b) Intensity

The intensity of crop rotations in the dryland areas of the United States can be based on the water use patterns of the

various crops (Beck and Doerr 1992; Beck 1997). The higher the water use the greater the intensity. Crops can be divided into high water use crops and low water use crops. High water use crops are those full-season summer-grown crops such as corn, sunflower, soybean, and cotton. Low water use crops are those classified as short-season and cool-season crops. Examples include small grains, flax, millet, and lentils.

The application of the method gives arbitrary increasing values with increasing crop water use; respectively. That is,

- fallow (no crop water use) has a zero (0) value;
- low water use crops has a value of one (1); and
- high water use crops has a value of two (2).

The intensity is equal to the sum of all of the crop water-use values, divided by the number of crops and fallow in the rotation. For example, a winter wheat-fallow rotation has an intensity of only 0.50 ( $0+1=1$  divided by 2); and a spring wheat-winter wheat-corn-sunflower rotation has an intensity of 1.50 ( $1+1+2+2=6$  divided by 4).

### (c) Diversity

Ecologists have developed several measures of diversity. The most widely used procedures are the Shannon, Simpson, and Margalef diversity indices (Gleissman, 1998). The Natural Resources Conservation Service, formerly Soil Conservation Service, has made several attempts at describing the influence of crops and tillage on productivity and sustainability (Soil Conservation Service 1976; King 1977). A much simplified and holistic approach to describing diversity has been proposed by Beck (1996). The diversity index accounts for the different crop types and their intervals within the rotation. The crop types considered are as follows:

- Cool-season grasses (winter wheat, spring barley)
- Warm-season grasses (corn, millet, sorghum)
- Cool-season broadleaf (flax, lentils, canola)
- Warm-season broadleaf (soybean, cotton, dry bean, sunflower)

In addition, the index accounts for ecological considerations such as those relating to weed and disease pressures, as well as workload distribution and the conflicts between operational interferences. These include planting interference of one crop with the harvest of another crop in the rotation. Diversity values generally range from -0.50 (winter wheat-fallow) to nearly 4.0 for highly diverse rotations such as spring wheat-winter wheat-soybean-corn.



**Figure 507-1** Major dryland regions and production areas of the United States and Canada. (Cannel and Dregne 1988)



Both the intensity and diversity indices, as defined, offer tools that can be used to evaluate rotations. The utility of these tools is particularly useful during the initial planning phases.

### 507.24 Factors in planning dryland cropping systems

The following factors need to be considered in planning dryland-cropping systems:

- Historic precipitation patterns and rainfall probabilities.
- Crop marketability and potential profitability.
- Insect cycles and potential disease organisms.
- Crop water use patterns.
- Snow management.
- Weed control options and evaluation of ability to rotate herbicide types.
- Optimum row widths.
- Potential phytotoxicity.
- Equipment needs.

### 507.25 Major cropping systems and technologies for the dryland regions of the United States

As previously mentioned, the resource constraints of the dryland regions of the United States are three-fold:

- soil erosion by both wind and water;
- periods of water stress of significant duration; and,
- limited production inputs.

Probably the most important factor affecting the constraint associated with limited production inputs is soil fertility. The inability to make precise fertilizer recommendations under diverse and variable precipitation patterns comprises efforts in obtaining maximum economic returns.

The focus of dryland systems is on crop yield sustainability and water conservation/water harvesting techniques. Thus, the sequence of crops and the characteristics of each crop control every other aspect of the cropping system.

Briefly, table 507-3 identifies the major crops, crop rotations, and management technologies.

**Table 507–3** Major cropping systems and water and soil conservation management technologies for U.S. dryland agricultural regions

U.S. dryland agricultural regions	----- Cropping systems ----- Crops	----- Crop rotations	Water and soil conservation management technologies	
Southern Great Plains	Winter Wheat (WW)	con't OC	<ul style="list-style-type: none"> <li>• No-tillage</li> <li>• Weed Control</li> <li>• Summer fallow</li> <li>• Vertical mulching</li> <li>• Terrace</li> <li>• Contouring</li> <li>• Furrow diking</li> <li>• Furrow blocking</li> </ul>	<ul style="list-style-type: none"> <li>• Bench terraces</li> <li>• Mulch-tillage</li> <li>• Alternate irrigation/dryland</li> <li>• Variable rate planting</li> <li>• Delayed planting dates</li> <li>• Nutrient management</li> <li>• Pest management</li> </ul>
	Grain Sorghum (SO)	con't WW		
	Cotton (OC)	WW-fallow		
	Sunflower (SF)	WW-SO/SD-fallow		
	Forage Sorghum (SD)	WW-OC-fallow		
	Alfalfa (AL)	con't SO/SD		
	Guar (GU)	WW(3)-OC(3)-fallow		
OC-SF				
Central Great Plains	Winter Wheat (WW)	WW-fallow	<ul style="list-style-type: none"> <li>• No-tillage</li> <li>• Mulch-tillage</li> <li>• Terrace</li> <li>• Contouring</li> <li>• Weed control</li> <li>• Summer fallow</li> </ul>	<ul style="list-style-type: none"> <li>• Snow management</li> <li>–tall wheatgrass barriers</li> <li>–annual crop barriers</li> <li>• Nutrient management</li> <li>• Stripcropping</li> <li>• Pest management</li> </ul>
	Grain Sorghum (SO)	WW-SO/SD-fallow		
	Sunflower (SF)	WW-CG-fallow		
	Forage Sorghum (SD)	WW-SF-fallow		
	Grain Corn (CG)	con't SO/SD		
	Millet (MO)	WW-MO-fallow		
	Dry bean (BD)	SF/SG-BD con't BD		
Northern Great Plains	Barley (BA)	WW/WS-fallow	<ul style="list-style-type: none"> <li>• No-tillage</li> <li>• Mulch-tillage</li> <li>• Summer fallow</li> <li>• Weed control</li> </ul>	<ul style="list-style-type: none"> <li>• Snow management</li> <li>–tall wheatgrass barriers</li> <li>–annual crop barriers</li> <li>–field shelterbelts/ tree windbreaks</li> <li>–bench terraces w/ grassed dikes</li> </ul>
	Winter Wheat (WW)	BA-fallow		
	Spring Wheat (WS)	WW/WS-BA-fallow		
	Oats (OT)	WS-WW-fallow	<ul style="list-style-type: none"> <li>• Nutrient management</li> <li>• Stripcropping</li> <li>• Pest management</li> </ul>	
	Flax (FL)	WW-BA-SB		
	Safflower (SA)	WS-SF/SA/SB		
	Sunflower (SF)	WS-OT-SF/SA/FL-BA		
	Grain Corn (CG)	WS-WW-CG-SB/SF		
	Soybean (SB)	BA-WW-CG-SB/SF		
	Alfalfa (AL)	WW-CG-MO-fallow		
	Millet (MO)	WW-SF-fallow		
		CG-SB		
		WS-FL/SF/SA-fallow		
	BA-CG			
Pacific Northwest	Spring Lentil (LDs)	WW-LDs/PF	<ul style="list-style-type: none"> <li>• Slot mulching</li> <li>• No-tillage</li> <li>• Mulch tillage</li> <li>• Summer fallow</li> <li>• Weed control</li> <li>• Terrace</li> <li>• Contouring</li> </ul>	<ul style="list-style-type: none"> <li>• Nutrient management</li> <li>• Stripcropping</li> <li>• Pest management</li> </ul>
	Winter Lentil (LDw)	WW-LDw		
	Spring Barley (BAs)	BAs-fallow		
	Rapeseed (RB)	BAs-PF		
	Green Pea (PG)	RB-fallow		
	Austrian Winter Pea (AW)	PG-RB		
	Winter Wheat (WW)	AW-WW-BAs		
	Spring Wheat (WS)	WW-AW-BAs/WS		
	Spring Pea (PF)	WS-fallow WW-fallow		
Pacific Southwest	Winter Wheat (WW)	WW-fallow	<ul style="list-style-type: none"> <li>• Water harvesting</li> <li>• Summer fallow</li> <li>• No-tillage</li> <li>• Mulch tillage</li> <li>• Nutrient management</li> </ul>	<ul style="list-style-type: none"> <li>• Terrace</li> <li>• Snow melt control w/ flyash</li> <li>• Weed control</li> <li>• Pest management</li> </ul>
	Pasture (PT)	WW-PT-fallow		
	Spring Barley (BAs)	BAs-fallow BAs-BAs-fallow		

## Subpart 507B References

- Bauer, A., and A.L. Black. 1981. Soil carbon, nitrogen, and bulk density comparisons in two cropland tillage systems after 25 years and in virgin grassland. *Soil Science Society of America J.* 45:1166-1170.
- Beck, D.L., and R. Doerr. 1992. No-till guidelines for the arid and semi-arid prairies. *Agricultural Exp. Sta. Publ. B712.* South Dakota State University. Brookings, SD.
- Beck, D.L. 1996. Increasing the Efficient Utilization of Precipitation on the Great Plains and Prairies of North America. *Dakota Lakes Research Farm.* Pierre, SD.
- Beck, D.L. 1997. Crop diversity aids time and equipment needs. *Proceedings, Vol. 9.* Colorado Conservation Tillage Association. Sterling, CO.
- Bregle, K.G. 1982. *Principles and Practices of Dryland Farming.* Colorado Associated University Press. Boulder, CO.
- Cannell, G.H., and H.E. Dregne. 1983. Chapter 1—Regional Setting. *In* H.E. Dregne and W.O. Willis (eds.) *Dryland Agriculture.* Agronomy Monograph 23. American Society of Agronomy. Madison, WI. pp. 3-17.
- Duley, F.L., and J.J. Coyle. 1955. Farming where rainfall is 8-20 inches a year. *In* *Yearbook of Agriculture,* Washington, DC.
- Gleissman, S.R. 1998. *Agroecology-Ecological Processes in Sustainable Agriculture.* Ann Harbor Press. Chelsea, MI.
- Haas, H.J., C.E. Evans, and E.F. Miles. 1957. Carbon and nitrogen changes in Great Plains soils as influenced by cropping and soil treatments. U.S. Department of Agriculture, *Tech. Bull.* 1164. Washington, DC.
- Hargreaves, M.W.M. 1957. *Dry Farming in the Northern Great Plains, 1900-1925.* Harvard Univ Press. Cambridge, MA.
- Higbee, E. 1958. *American Agriculture: Geography, Resources, Conservation.* John Wiley and Sons, Inc. New York, NY.
- King, A.D. 1977. Soil conditioning indices for irrigated crops in Colorado. *Technical Note No. 52.* Soil Conservation Service. Denver, CO.
- Oram, P. 1980. What are the world resources and constraints for dryland agriculture? *In* *Proceedings of the International Congress for Dryland Farming.* Dept. Agriculture. Adelaide, South Australia.
- Reicosky, D.C., W.D. Kemper, G.W. Langdale, C.L. Douglas, Jr., and P.E. Rasmussen. 1995. Soil organic matter changes resulting from tillage and biomass production. *J. Soil and Water Conserv.* 20:253-261.
- Savory, A. 1988. *Holistic Resource Management.* Island Press, Washington, DC.
- Stewart, B.A. 1988. Chapter 14—Dryland Farming: The North American Experience. *In* Unger, P.W., W.R. Jordan, T.V. Sneed, and R.W. Jensen (eds.) *Challenges in Dryland Agriculture-A Global Perspective.* International Conference on Dryland Farming. Texas Agricultural Experiment Station. College Station, TX.
- Stewart, B.A. and E. Burnett. 1987. Water conservation technology in rainfed and dryland agriculture. *In* Jordan, W.R. (ed.) *Water and Water Policy in World Food Supplies.* Texas A&M Univ. College Station, TX.
- U.S. Department of Agriculture, Soil Conservation Service. 1976. Soil conditioning indices for major irrigated and non-irrigated crops grown in the United States. *Technical Note No. 27.* West National Technical Center. Portland, Oregon.

---

<b>Contents:</b>	<b>Subpart 508A</b>	<b>Agronomic responsibilities in soil surveys</b>	<b>508–1</b>
	<b>Subpart 508B</b>	<b>Agronomic soil interpretations</b>	<b>508–1</b>
	<b>Subpart 508C</b>	<b>Soil management</b>	<b>508–2</b>
	508.30	Soil conditioning index for cropland management systems—background .....	508–2
	508.31	The benchmark condition .....	508–3
	508.32	Basis for the organic matter (OM) component .....	508–4
	508.33	Basis for the field operations (FO) component .....	508–7
	508.34	Basis for the erosion (ER) component .....	508–8
	508.35	Subfactor values and their relationship .....	508–8
	508.36	Calculating the Soil Conditioning Index .....	508–9
	508.37	Calibration of the Soil Conditioning Index to other research sites .....	508–11
	<b>Subpart 508D</b>	<b>References</b>	<b>508–11</b>

---



---

**Subpart 508A Agronomic respon-  
sibilities in soil surveys**  
(Reserved)

---

**Subpart 508B Agronomic soil  
interpretations**  
(Reserved)

Technical guidance for developing Ecological Site Descriptions and Forage Suitability Groups are in the National Range and Pasture Handbook.

## Subpart 508C Soil management

### 508.30 Soil conditioning index for cropland management systems—background

#### (a) Regional versions of the Soil Conditioning Index

In 1964, Wayne Austin published Conservation Agronomy Technical Note No. 27, Soil Conditioning Rating Indices for Major Irrigated and Non-Irrigated Crops Grown in the Western United States, through the then SCS West National Technical Center (WNTC), Portland, Oregon. This Technical Note was revised by J.W. Turelle in 1967, and again reprinted by F.L. Brooks in 1974.

A.D. King and others prepared a shorter version in 1986 through the South National Technical Center (SNTC), Fort Worth, Texas.

#### (b) A National Version

This version of the rating procedure adapts the concept for use nationwide, by introducing the effects of climate on organic matter decomposition at various geographic locations. The latest version of the Soil Conditioning Index is available as an Excel spreadsheet at

<ftp://ftp.nssc.nrcs.usda.gov/pub/agronomySCIfiles/>

The important components of the Index (SCI) include

- the amount of organic material returned to the soil,
- the effects of the tillage and planting system on organic matter decomposition, and
- the effect of predicted erosion associated with the management system.

Rating values for these variables were determined subjectively, and are described below.

#### (c) The concept

For much of its history, NRCS worked primarily on the problem of soil erosion on agricultural and other lands. Predictive/evaluation tools such as the Universal Soil Loss Equation (USLE) and the Wind Erosion Equation (WEQ) enhanced conservation planning for erosion control.

New concepts of planning developed in the 1990's broadened the planning approach to consider five resources—soil, water, air, plant, and animal—and multiple resource concerns associated with each resource.

One area of concern is degradation of soil quality through processes that are influenced by management. One such concern is organic matter decline under cultivation. The Soil Conditioning Index is a tool to predict the consequences of management actions on the state of soil organic matter.

Precedents for this predictive tool are in WNTC Technical Note No. 27 (1964) and the SNTC version developed in 1986, discussed in 508.30 (a).

This version of the Index predicts organic matter change qualitatively, not quantitatively. It predicts one of three outcomes — organic matter decline, organic matter increase, or organic matter equilibrium.

The procedure depends on the assumption that the amount of biomass that must be returned, to maintain equilibrium, is directly proportional to rate of decay. In moist climates, decomposition is more rapid than in dry climates, thus more biomass is needed. The same is true comparing warm to cool climates. *Maintenance amounts* of crop residue at locations throughout the United States were calculated based on this assumption.

The Index considers organic material (biomass) produced and returned to the soil, the influence of climate on organic matter decay, the influence of tillage, and the influence of erosion.

Decomposition functions of Revised Universal Soil Loss Equation (RUSLE) were used to estimate relative rates of plant residue decomposition at different locations. Climate at each location is expressed as average monthly precipitation and average monthly temperature.

#### (d) Components of the Soil Conditioning Index

A combination of effects causes degradation of soil condition. Wind and water erosion remove fine soil particles, organic matter, and plant nutrients, thus reducing productivity and the ability of the soil to hold water. Excessive tillage accelerates erosion and organic matter decay, and causes compaction. Crop rotations which produce low amounts of residue, and/or which involve extensive residue removal, result in inadequate amounts of organic material returned to the soil.



The formula for the Soil Conditioning Index is:

$$SCI = OM + FO + ER$$

where:

*SCI is the Soil Conditioning Index:* Soil Conditioning Index estimates the combined effect of three variables on trends in soil organic matter. Soil organic matter trends are assumed to be an indicator of improvement or degradation of soil condition.

*OM is organic material:* This component accounts for the effect of organic material returned to the soil. Organic material from plant or animal sources may be either grown and retained on the site or imported to the site.

*FO is field operations:* This component accounts for the effect of field operations that stimulate organic matter breakdown. Tillage, planting, fertilizer application, spraying and harvesting crush and shatter plant residues and aerate or compact the soil. These effects increase the rate of residue decomposition and affect the placement of organic material in the soil profile.

*ER is erosion:* This component accounts for the effect of removal or sorting, or both, of surface soil material by the sheet, rill, or wind erosion processes that are predicted by water and wind erosion models. It does NOT account for the effect of concentrated flow erosion such as ephemeral or classic gullies. Erosion contributes to loss of organic matter and decline in long-term productivity.

**(e) Using the Soil Conditioning Index to evaluate conservation practices and systems**

The Soil Conditioning Index tool predicts the effect of management systems on soil organic matter. Soil organic matter level is a primary indicator of soil condition. It affects such soil characteristics and processes as cation exchange, aggregate stability, water holding capacity, and soil biological activity. Soil condition is the degree to which a soil maintains the ability to accept, store and release water, nutrients, and energy, to promote and sustain root growth, to sustain soil biological and chemical processes, and to resist erosion, compaction, and other management impacts.

(i) The Index evaluates the effect of farming practices on soil organic matter. The Index expresses whether the cropping sequence, soil disturbing operations, and other management inputs tend to increase or decrease soil organic matter under a given climatic regime.

(ii) Similar to the way in which water and wind erosion models are used to assess the effects of management systems on water and wind erosion, the Soil Conditioning Index is a tool to estimate the effect of the same management systems on the physical condition of the soil resource. Like erosion models, it has broader application than any single practice, but can be used to evaluate how changes in single practices influence the effect of the management system on the soil resource.

(iii) Because erosion (the present or a planned system) is one of the variables considered, erosion estimates using RUSLE or WEQ, or both, are part of the Soil Conditioning Index procedure.

When the crop rotation is managed as part of a system to maintain or improve soil condition, criteria for design of the rotation should include the use of high-residue crops in cropping sequences. The rotation should be supplemented as needed by additional sources of organic matter such as cover crops, green manure crops, or animal manure.

Management of plant residue to maintain or improve soil condition includes limitations on residue removal by any means including grazing.

Management of field operations to maintain or improve soil condition involves limiting the number of tillage operations and the degree of soil disturbance by each operation.

Any combination of practices that help stabilize the site by controlling erosion within specified limits conserves soil organic matter. These systems may include any of the practices discussed above, as well as supporting practices such as terraces, stripcropping, or windbreaks.

### 508.31 The benchmark condition

This kind of predictive tool requires a point of reference or *benchmark*. A situation was selected where the impact on organic matter of various management systems and production levels could be determined from the research. The selected location was the experiment station at Renner, Texas, from 1948 to 1959.

The benchmark condition is a specific combination of organic material produced by the crop rotation, tillage and planting operations, and associated erosion that resulted in maintaining soil organic matter at a steady state during 12 years of research (Laws, 1961). The same three variables

are the basis for determining maintenance amounts of crop residues and calculating the Soil Conditioning Index at any location when compared to the benchmark condition as a point of reference.

The time and location define the climate during the period of the research. Published papers tell us about the crops grown, production levels, tillage and residue management, and associated organic matter trends. Reasonable assumptions can also be made about amounts of erosion under the research conditions. Research results at Renner are described throughout this section, and are summarized in table 508.5.

### 508.32 Basis for the organic matter (OM) component

#### (a) Background

This subfactor is based on the amount of organic material returned to the soil (residue, roots, cover crops, green manure crops, animal waste) for organic matter maintenance or restoration. The maintenance amount is the assumed amount, expressed as Residue Equivalent Value (see 508.32(c)), that must be returned to the soil annually to maintain soil organic matter at a constant level (neither increasing nor decreasing).

Table 508.1 shows the maintenance amounts, for locations throughout the United States, that apply when tillage and erosion are similar to conditions during the Blacklands Farming Systems Studies at Renner, Texas, 1948–59. The Organic Material Subfactor (OM) = 0 when these conditions apply [see 508.35(a)(1)(i)]. The maintenance amount varies by climate, based on precipitation and temperature that govern biomass production and rates of decay. These are the maintenance amounts used to calculate the Soil Conditioning Index.

#### (b) The organic material budget

##### (1) Amount returned to the soil

(i) Amount produced on the site—Crop sequence and management affect organic matter maintenance. The kind of crops grown, their yields, removal of products from the field, and management of remaining residues, all affect the amount of organic material returned to the system, and soil organic matter levels.

(ii) Amount added or lost—Accounting for additions of organic material such as manure or mulch.

Residue removed at harvest or during the non-crop season include harvest for silage, grazing of crop aftermath, removal for bedding, burning, and similar practices. These losses are accounted for when estimating residue returned.

Physical losses not accounted for are those caused by shattering, materials blown from the field by wind or carried off the field by runoff water.

(iii) Root mass—Calculations of residue produced include estimated root mass to a depth of 4 inches. These estimates are based on the ratio of maximum root mass in the top 4 inches to above ground residue produced at harvest, taken from the RUSLE data base (see table 508.6 — RUSLE crop parameter data).

#### (2) Climatic effects on decomposition of organic material

(i) Climate, particularly temperature and precipitation, affects plant growth, biological activity, and organic matter decomposition.

(ii) An inverse relationship exist between mean annual temperature and the level of organic matter in regions of comparative rainfall. Higher temperatures stimulate microbial decomposition more than they stimulate plant growth. The decay processes that break down organic matter are more rapid in warmer climates and go on for a longer period during the year.

(iii) Organic matter levels also vary with precipitation. Both plant growth and rates of organic matter decay are higher where rainfall is high. Relatively little organic matter is found in arid soils where vegetation is sparse, because the raw materials are lacking.

#### (c) Determining the maintenance amount at Renner, Texas

##### (1) Maintenance amounts of crop residues are based on results of the Blacklands Farming Systems studies at the Renner research station, 1948-59.

(i) Residue production and trends in soil organic matter—Table 508.5 summarizes the crop rotations used in the Renner experiments, the amount of above ground crop residues produced, and the effect on soil organic matter content. System 8 (wheat-cotton-sorghum, not fertilized) and System 9 (wheat-cotton-sorghum, fertilized, manure added) are the basis for the conclusions in this paper.

System 8 produced an average of 3,865 pounds of aboveground crop residue per year, and percent organic matter declined 0.14 percent during the 12-year experiment (1948 to 1959).

Wheat 5,114 lb/ac/yr x 4 yr = 20,456 lb/ac  
 Cotton 3,015 lb/ac/yr x 4 yr = 12,060 lb/ac  
 Grain sorghum 3,466 lb/ac/yr x 4 yr = 13,864 lb/ac  
 Total crop residue = 46,380 lb/ac  
 Average crop residue = (46,380 lb/ac)/12 yr  
 = 3,865 lb/ac/yr

System 9 produced an average of 4,189 pounds of aboveground crop residue per year. In addition, each plot received four applications of manure, totaling 20 tons per acre. Assuming open lot manure at 50 percent moisture content, dry matter applied = 10 tons per acre. Percent organic matter increased 0.64 percent during the 12 year experiment.

Wheat 5,318 lb/ac/yr x 4 yr = 21,272 lb/ac  
 Cotton 3,237 lb/ac/yr x 4 yr = 12,948 lb/ac  
 Grain sorghum 4,013 lb/ac/yr x 4 yr = 16,052 lb/ac  
 Manure 5,000 lb dry matter/ac/yr x 4 yr  
 = 20,000 lb/ac  
 Total crop residue + manure = 70,272 lb/ac  
 Average crop residue + manure  
 = (70,272 lb/ac)/12 yr = 5,856 lb/ac/yr

## (2) *Estimating the maintenance amount*

(i) The maintenance amount at Renner was estimated by analysis of System 8 and System 9. (See table 508.5.)

(ii) Percent organic matter (OM) increased 0.78 percent with 1991 pounds additional aboveground residue. Interpolating, OM loss/gain = 0 (steady state) when aboveground biomass = 4,222 lb.

$$[(.14/.78) \times 1991] + 3,865 = 4,222 \text{ lb}$$

(iii) Factoring the amount of residue supplied by each crop and manure equally gives the following:

Wheat  $[(.14/.78) \times 204] + 5,114 = 5,151 \text{ lb/ac/yr} \times 4 \text{ yr} = 20,604 \text{ lb/ac}$   
 Cotton  $[(.14/.78) \times 222] + 3,015 = 3,055 \text{ lb/ac/yr} \times 4 \text{ yr} = 12,220 \text{ lb/ac}$   
 Grain Sorghum  $[(.14/.78) \times 547] + 3,466 = 3,564 \text{ lb/ac/yr} \times 4 \text{ yr} = 14,256 \text{ lb/ac}$   
 Manure  $[(.14/.78) \times 5,000] + 0 = 897 \text{ lb/ac/yr} \times 4 \text{ yr} = 3,588 \text{ lb/ac}$   
 Total crop residue + manure = 50,668 lb/ac  
 Average crop residue + manure = (50,668 lb/ac)/12 yr = 4,222 lb/ac/yr

(iv) Adjustment for root mass. The values calculated above are increased to account for root mass in the upper 4 inches, using root mass adjustments from table 508.6.

Wheat 5,151 lb/ac x 1.259 = 6,485 lb/ac  
 Cotton 3,055 lb/ac x 1.118 = 3,415 lb/ac  
 Grain sorghum 3,564 x 1.291 = 4,601 lb/ac  
 Manure 897 x 1.0 = 897 lb/ac  
 Total above and below ground residue + manure = 15,398 lb/ac  
 Average all residue + manure = (15,398 lb/ac)/3 yr = 5,133 lb/ac/yr

(v) 5,133 pounds per acre per year is the calculated amount of above and below ground residue, including manure, at which organic matter content of the Renner plots stabilized. See 508.32(d)(3) for conversion to Residue Equivalent Value (REV).

## (d) *Residue equivalent values*

To deal with variability in the rate of decomposition between various classes of crop residues, Residue Equivalent Values (REV) were developed to convert all crop residues to a common standard. Crop Group C, which includes corn, grain sorghum, and sunflower is used as the standard because these crops are commonly grown throughout much of the United States, and because the RUSLE decomposition coefficient (0.016) is intermediate in value among eight major crop groups. The Residue Equivalent Value of any plant material is its mass expressed as the equivalent mass of Crop Group C residue, based on relative annual decomposition rates. The following conversion factors for eight crop groups at Renner, Texas are calculated from their relative decomposition rates at Renner.

Crop groups and crops	Conversion to REV	Crop groups and crops	Conversion to REV
A Small grains, except NW wheat and range region: Oats Barley Flax Manure, surface application, straw or newspaper bedding Millet Rye Wheat, spring Wheat, winter	1.27	E Legumes: Alfalfa Broccoli Cabbage Red clover	0.96
B Cotton; burley tobacco; peanuts: Cotton Peanuts Sugarcane Tobacco	1.01	F Soybeans; sugar beets: Beans, field Cauliflower Soybean Strawberry Sugarbeets	0.94
C Corn; grain sorghum; sunflower: Canola Corn Safflower Sorghum Sudan Sunflower Tomato plantain	1.00	G Vegetables and specialty crops: Asparagus Beans, green-snap Beans, lima Carrot Cucumber Lentils Manure, swine, beef and dairy, settling basin Muskmelon Native cover, PR Peas Peppers Potato, sweet Potato, white Pumpkin Radish Squash, summer Tomato, fresh market Tomato, processing Watermelon	0.93
D Small grains, except NW wheat and range region; canola; grasses: CRP grassland PNW barley PNW winter wheat Bromegrass Manure, swine, beef and dairy, open lots and buildings, no bedding Orchardgrass Ryegrass cover Tall fescue Winter cover	0.97	H Manure, surface application, poultry litter:	0.93

Examples of finding Residue Equivalent Values:

$$3,200 \text{ lb soybean residue} \times 0.94 \\ = 3,008 \text{ lb Residue Equivalent Value (REV)}$$

$$4,000 \text{ lb wheat residue} \times 1.27 = 5,080 \text{ lb REV}$$

Applying these conversion factors to the maintenance amounts of aboveground residue at Renner (calculated above) gives the following:

$$\text{Wheat } 6,485 \text{ lb} \times 1.27 = 8,236 \text{ lb REV}$$

$$\text{Cotton } 3,415 \text{ lb} \times 1.01 = 3,449 \text{ lb REV}$$

$$\text{G Sorg } 4,601 \text{ lb} \times 1.00 = 4,601 \text{ lb REV}$$

$$\text{Manure } 897 \text{ lb} \times 0.97 = 870 \text{ lb REV}$$

$$\text{Total residue + manure expressed as REV} \\ = 17,156 \text{ lb/ac}$$

$$\text{Average residue + manure expressed as REV (17,156} \\ \text{lb/ac)/3 yr} = 5,719 \text{ lb/ac/yr}$$

The maintenance amount of above and below ground residue at Renner has a calculated Residue Equivalent Value of 5,719 lb/ac/yr when tillage and erosion are similar to conditions during the research. Maintenance amounts and REV conversion factors at other locations in the United States are shown in table 508.1.

Continuously updated versions of the tables of data for the worksheets are located at:  
<ftp://ftp.nssc.nrcs.usda.gov/pub/agronomy/SCIfiles/>

**(e) Determining the maintenance amount at other locations**

The maintenance amount of crop residues determined above is applicable at Renner under the field conditions that existed at the research plots during the years of the research. At other locations, this amount is adjusted to account for differences in climate (monthly average precipitation and temperature). The adjusted amount is applicable when soil disturbance by tillage and the amount of erosion are similar to those conditions during the research at Renner.

When the effects of tillage and other field operations are more severe than the system used on the Renner plots, the amount of crop residue needed for maintenance of organic matter is correspondingly greater. When these effects are less severe, the maintenance amount is correspondingly less. In the same way, the amount needed for maintenance is greater when predicted erosion exceeds the estimated erosion on the Renner plots (4 tons/ac/yr), and is less when predicted erosion is less than 4 tons per acre per year.

The following procedure was used to establish maintenance amounts and subfactor values:

- As discussed, the maintenance amount at Renner, Texas, was determined to be 5,719 lbs of above and belowground residue (Residue Equivalent Value).
- Using the C factor routines of RUSLE, the annual decay rate of Crop Group C (corn, grain sorghum, sunflower) residue at Renner, Texas (30.95 inches average annual precipitation and 65.1 degrees mean annual temperature) was calculated.
- Annual decay rates of Crop Group C residue at other locations were then calculated in the same manner. Assuming that the average annual amount of residue needing to be returned is directly proportional to annual rates of decay:
  - The maintenance amount at any location = [(decay at the location)/(decay at Renner, TX)] x 5719, and
  - The subfactor value (OM) at the location = [residue returned (REV) - maintenance amount (REV)] x [1.0/maintenance amount (REV)].

### 508.33 Basis for the field operations (FO) component

**(a) Background**

Tillage increases the rate of decay as well as the hazard of organic matter loss caused by erosion. The frequency, depth, and aggressiveness of each tillage operation determine the magnitude of the effects on aeration, lifting, shattering or compaction. Clean tillage systems consisting of one deep primary and two or more secondary operations result in the most soil disturbance. Noninversion tillage (mixing or undercutting), involving fewer tillage trips and retaining more residues on the surface, results in slower decay rates as well as less loss to erosion. No-till systems result in the least soil disturbance.

**(b) The Soil Disturbance Rating (SDR)**

Each soil disturbing field operation was evaluated for its impact on **Inversion, Mixing, Lifting, Shattering, Aeration, and Compaction**. Each of these six impacts was subjectively assigned a value of 0 through 5, with 0 being no impact and 5 being severe impact. See table 508.2. The Soil Disturbance Rating (SDR) for each field operation is the sum of the six impact values.

**(c) The Soil Disturbance Rating at Renner**

The Soil Disturbance Rating (SDR), cumulative and average annual, at the Renner, Texas research plots is calculated as follows:

Soil disturbance operations	Rating (SDR)*
Year 1: Grain sorghum	
Chop cotton stalks	3
Tandem disk (finishing)	18
Tandem disk (finishing)	18
Planter, runner shoe	1
Row crop cultivate (multiple sweeps)	19
Row crop cultivate (single sweep)	16
Harvest	5
Year 2: Winter wheat	
Shred sorghum residue	3
Buzzard wing sweeps	21
Tandem disk (finishing)	18
Tandem disk (finishing)	18
Drill wheat, hoe opener	17
Harvest	5
Year 3: Cotton	
Tandem disk (primary tillage)	26
Tandem disk (finishing)	18
Tandem disk (finishing)	18
Planter, runner shoe	1
Row crop cultivate (multiple sweeps)	19
Row crop cultivate (multiple sweeps)	19
Row crop cultivate (multiple sweeps)	19
Row crop cultivate (single sweeps)	16
Harvest	5
Cumulative Soil Disturbance Rating (SDR)	303

Average Annual SDR =  $303/3 = 101$

\*Soil Disturbance Rating (SDR) values are in table 508.2

**508.34 Basis for the erosion (ER) component****(a) Estimated erosion at Renner**

Actual erosion, 1948 to 1959, on the Renner research plots is unknown. Erosion levels at about 4 tons per acre per year are assumed to have occurred, based on the following RUSLE calculation:

Rainfall factor  $R = 290$ .

Soil: Houston black clay, soil erodibility factor  $K = 0.32$  adjusted to 0.29; soil loss tolerance  $T = 5$  tons/ac/yr

Estimated slope: 1% x 300 ft, slope factor  $LS = 0.17$ .

Crop rotations and field operations as described above, estimated cropping-management factor  $C = 0.286$ .

Straight-row farming, support practice factor  $P = 1.0$ .

Estimated erosion =  $290 \times 0.29 \times 0.17 \times 0.286 \times 1.0 = 4.0$  tons/ac/yr

**508.35 Subfactor values and their relationship****(a) Subfactor values**

Each subfactor has a value of 0 (zero) for conditions at assumed equilibrium (soil organic matter maintained, neither increasing nor decreasing). A subfactor will have a negative value when its effects tend to decrease soil organic matter, compared to the benchmark condition at Renner; it will have a positive value when its effects tend to increase soil organic matter compared to the benchmark condition. The range of values is described below.

**(b) Organic Material (OM) subfactor**

This subfactor value equals 0 (equilibrium) at Renner when above and below ground biomass (grown on the site or applied) = approximately 5,719 pounds of Residue Equivalent Value (REV). At other locations this maintenance amount is adjusted for climate (precipitation and temperature).

At any given location, the subfactor value = 0 when the amount of residue produced or applied to the site is equal to the adjusted maintenance amount for that location. The subfactor value = -1.0 when no biomass is grown on or applied to the site. All other positive and negative values are proportionate to this relationship.



Organic Material (OM) subfactor values are calculated as follows:

$$\begin{aligned} & [\text{Residue returned (REV)} \\ & - \text{maintenance amount (REV)}] \\ & \times (1.0/\text{maintenance amount}) \end{aligned}$$

### Field Operations (FO) subfactor :

Field operations (tillage and planting systems) are assigned positive or negative values based on the number, type, and severity of tillage operations compared with the system used at Renner.

The subfactor value = 0 for the system used on the Renner research plots (SDR = 101).

The subfactor value = +1.0 (plus 100%) when no soil disturbance occurs (SDR = 0). All other positive and negative values are proportionate to this relationship.

Field Operations (FO) subfactor values are in table 508.3.

### Erosion (ER) subfactor :

The subfactor value = 0 when predicted erosion is 4 tons per acre per year, and = +1.0 (plus 100%) when predicted soil loss = 0. Estimated erosion in excess of 4 tons per acre per year, is assigned negative values.

The organic matter enrichment of eroded sediment decreases as erosion increases and rills become more dominant, because organic matter is greatest at the surface. Therefore the appropriate erosion subfactor relationship is curvilinear.

Erosion (ER) subfactor values are in table 508.4.

### Relative weighting of subfactor values

The Soil Conditioning Index is the sum of the three subfactor values, weighted for their relative importance.

The weighting factors are:

Organic material	40%
Field Operations	40%
Erosion	20%

## 508.36 Calculating the Soil Conditioning Index

### (a) To determine the maintenance amount of crop residue at your location

Table 508.1 gives the maintenance amount of crop residue at selected locations in pounds per acre per year, expressed as Residue Equivalent Value (REV), when the subfactor values for Field Operations (FO) and Erosion (ER) = 0 (Reference Condition).

### (b) To evaluate the present cropping-management system

#### *Determine the Organic Material subfactor:*

Determine the total amount of residue produced on the site by the crop rotation (crop yield x pounds per unit of yield x residue to yield ratio). Adjust for root mass. Residue production parameters for various crops as used in RUSLE are in table 508.6. Adjust for any residue removed from or added to the site.

Convert residue amounts for each crop to Residue Equivalent Value (REV). REV conversion factors for seven crop groups are given for selected locations in table 508.1.

Divide total REV for the crop rotation by number of years in the rotation to determine average annual REV.

Calculate the Organic Material (OM) subfactor value.

$$[\text{Residue Returned (REV)} - \text{Maintenance Amount (REV)}] \times [1.0/\text{Maintenance Amount (REV)}]$$

#### *Determine the Field Operations subfactor:*

List all field operations (tillage, planting, fertilizing, cultivating, etc.). Find the Soil Disturbance Rating (SDR) for each operation in table 508.2. Total the Soil Disturbance Rating values and divide the cumulative total by the number of years in the rotation to determine average annual Soil Disturbance Rating.

Find the corresponding field operations (FO) subfactor value in table 508.3.

#### *Determine the Erosion subfactor:*

Determine predicted average annual erosion using RUSLE or WEQ, or both, if applicable.

Find the corresponding Erosion (ER) subfactor value in table 508.4.

**Calculate the Soil Conditioning Index (SCI):**

$$SCI = (OM \times 0.4) + (FO \times 0.4) + (ER \times 0.2)$$

If the SCI value is negative, soil organic matter is predicted to be decreasing, and corrective measures should be planned. If the SCI value is zero or positive, soil organic matter is predicted to be stable or increasing.

**(c) To evaluate one or more alternative systems:**

To formulate alternatives, plan changes in the cropping-management system that will address negative subfactor values. For example:

- If the Organic Material (OM) subfactor is negative, plan for additional high residue crops in the rotation, and/or limit residue removal.
- If the Field Operations (FO) subfactor is negative, plan changes in the tillage/planting system to reduce the number and/or severity of field operations.
- If the Erosion (ER) subfactor is negative, consider supporting practices such as terracing, strip cropping, etc., as well as changes in the crop rotation or field operations.

Describe the alternative system (rotation and field operations) and follow the same procedure as (b) To evaluate the present cropping-management system above.

**(d) Example problem****Site information**

Location: Lincoln, NE

Soil: Sharpsburg silty clay loam

Soil loss tolerance T = 5 tons/ac/yr

Slope: 6% x 200 ft

Supporting conservation practices: None

Maintenance amount (table 508.1):

5455 lb/ac/ yr, REV

Crop rotation:

Year 1 - Corn, 125 bu/ac

Year 2 - Drilled soybeans, 35 bu/ac

Residue management:

All residues returned, 5399 lb/ac/yr, REV

Organic Material subfactor OM

$[(RP - MA)/MA] = -0.01$

Or-

**Present management system**

Fall mulch tillage

Year 1

Chisel plow, straight points

Tandem finishing disk

Field cultivator, w/sweeps

Plant corn, double disk opener

Harvest

Year 2

Chisel plow, straight points

Tandem finishing disk

Field cultivator, w/ sweeps

Drill soybeans, double disk opener

Harvest

Cumulative Soil Disturbance Rating SDR (table 508.2) = 138

Average annual SDR =  $138/2 = 69$

Field Operations subfactor FO (table 508.3) = +0.31

Predicted erosion = 10.5 tons/ac/yr

Erosion subfactor ER (table 508.4) = -1.28

Soil Conditioning Index SCI

=  $OM \times 0.4 + FO \times 0.4 + ER \times 0.2$

=  $(-0.01 \times 0.4) + (0.31 \times 0.4) + (-1.28 \times 0.2)$

=  $-0.004 + 0.124 - 0.256 = (-)0.136$

The SCI value is negative. Soil organic matter is predicted to be decreasing, and corrective measures should be planned. Erosion is the major factor affecting organic matter loss. Some alternatives are:

- change to a no-till system, which will reduce erosion and minimize soil disturbance, or
- apply measures such as terracing and contour farming to reduce erosion.

**Alternative management system**

No till

Year 1

Broadcast fertilizer

Plant corn, >2-inch fluted coulters

Harvest

Year 2

Drill soybeans, single disk opener

Harvest

Cumulative Soil Disturbance Rating SDR (table 508.2) = 26

Average Annual SDR =  $26/2 = 13$

Field Operations Subfactor FO (table 508.3) = +0.87

Predicted erosion = 3.2 t/ac/yr. Erosion Subfactor ER (table 508.4) = +0.25

Soil Conditioning Index SCI

=  $OM \times 0.4 + FO \times 0.4 + ER \times 0.2$

=  $(-0.01 \times 0.4) + (0.87 \times 0.4) + (0.25 \times 0.2)$

=  $-0.004 + 0.348 + 0.05 = +0.39$

The SCI value is positive. Soil organic matter is predicted to be increasing, and this alternative is suitable.



### 508.37 Calibration of the Soil Conditioning Index to other research sites

Research data from locations in the Corn Belt (Clarinda, Iowa) and the Northern Great Plains (Culbertson, Montana) was used to test the Soil Conditioning Index procedure under varying conditions of crops, tillage, and climate. The index agreed, within reasonable limits, with results of the research.

At Clarinda, Iowa, under a continuous corn rotation that ran for 12 years, cornstalk residue grown on the plots were removed each fall after grain harvest. Chopped residue were then artificially applied in amounts of 0, 1,785, 3,569, 7,139, and 14,278 pounds per acre per year. A system of moldboard plowing and clean tillage was used. Erosion was estimated to average 5.6 tons/acre/year. Under these conditions, organic carbon decreased when 3,569 pounds per acre per year of residue was applied, and increased when 7,139 pounds per acre per year was applied. By interpolation, organic carbon stabilized when about 5,156 pounds per acre per year was applied under the research conditions. When 5,156 pounds of above ground residue is returned (OM subfactor = +0.08), tillage includes fall moldboard plowing followed by two spring tillage operations (FO subfactor = +0.11), and erosion is 5.6 tons/acre/year (ER subfactor = -0.30), the Soil Conditioning Index = +0.01.)

Research at Culbertson on a spring wheat—summer fallow system maintained organic matter at a constant level when only 316 pounds per acre per year of wheat residue was returned in alternate years. Slow decomposition because of the relatively cool dry climate, subsurface tillage, and low erosion rates helped offset the effect of low residue amounts. In this experiment, four residue levels were established in the spring following harvest by removing or adding wheat straw—0, 1,500, 3,000, and 6,000 pounds per acre. Tillage to control weeds during the summer fallow year usually consisted of five operations with a V-blade. A tandem disk operation was performed in the following spring just before planting. With 316 pounds of residue returned in alternate years (OM subfactor = -0.82), stubble mulch fallow (FO subfactor = +0.41), and erosion of 1 ton/acre/year (ER subfactor = +0.75), the Soil Conditioning Index = -0.02.

### Subpart 508D References

- Acton, D.F. 1990. A Soil Quality Evaluation Program for Assessing Agricultural Sustainability in Canada — A draft proposal.
- Austin, Wayne W. 1960. Soil Productivity Index. U.S. Dept. Agric. Soil Conservation Service [Western States] Technical Note, Agronomy No. 13.
- Franzmeier, D.P., G.D. Lemme, and R.J. Miles. 1985. Organic carbon in soils of North Central United States. *Soil Sci. Soc. Am. J.* 49: 702-708.
- Fryrear, Donald W. 1981. Long-Term Effect of Erosion and Cropping on Soil Productivity. Geological Society of America, Special Paper 186.
- Karlen, D.L., D.C. Erbach, T.C. Kaspar, T.S. Colvin, E.C. Berry, and D.R. Timmons. 1990. Soil tilth: A review of past perceptions and future needs. *Soil Sci. Soc. Am. J.* 54: 153-161.
- King, A.D. and others. 1987. Soil Condition Indices for the Southeast.
- Klemme, A.E., and O.T. Coleman. 1939. Evaluating Annual Changes in Soil Productivity. Missouri Agricultural Experiment Station Bulletin 405.
- Klemme, A.E., and O.T. Coleman. 1949. Evaluating Annual Changes in Soil Productivity. Missouri Agricultural Experiment Station Bulletin 522.
- Laws, W. Derby. 1961. Farming Systems for Soil Improvement in the Blacklands. Texas Research Foundation Bulletin 10.
- Lucas, R.E., and M.L. Vitosh. 1978. Soil Organic Matter Dynamics. Michigan State University Research Report.
- Parton, W.J., D.S. Schimel, C.V. Cole, and D.S. Ojima. 1987. Analysis of Factors Controlling Soil Organic Levels in Great Plains Grasslands. *Soil Science Soc. Am. J.* 51: 1173-1179.
- Salter, R.M., and T.C. Green. 1933. Factors affecting the accumulation and loss of nitrogen and organic carbon on cropped Soils. *Jour. of the Am. Soc. of Agron.* 25: 622-630.

Soil Conservation Service, Temple, Texas. 1987. Soil Condition Rating Indices. Technical Note — Agronomy TX-8.

Soil Conservation Service, West Technical Service Center, Portland, Oregon. 1974. Soil Conditioning Rating Indices for Major Irrigated and Non-Irrigated Crops Grown in the Western United States. Technical Note No. 27.

Tiessen, J., J.W.B. Stewart, and J.R. Bettany, 1982. Cultivation effects on the amounts and concentration of carbon, nitrogen, and phosphorus in grassland soils. *Agronomy Journal* 74: 831-835.

**Table 508-1** Maintenance amounts (residue equivalent pounds) and Residue Equivalent Value factors

City Code	Location	State	Mainten- ance amt. including roots	Small Grains except Pacific NW & manure with bedding materials	Cotton, sugarcane, and Peanuts	Corn, grain sorghum, canola, & Sun- flower	Forage grasses, winter cover, manure- open lots & Pacific NW Small Grains	Legumes, cabbage, & Broc- coli	Soybeans, field beans, sugar beets, cauli- flower, & straw- berries	Vege- tables, specialty crops & manure- settling basin	Poultry litter
			Reference Condition	Crop Group A	Crop Group B	Crop Group C	Crop Group D	Crop Group E	Crop Group F	Crop Group G	Crop Group H
1001	BIRMINGHAM	AL	5943	1.19	1.01	1.00	0.98	0.98	0.97	0.97	0.96
1002	MOBILE	AL	6053	1.14	1.01	1.00	0.99	0.98	0.98	0.98	
1003	MONTGOMERY	AL	5960	1.18	1.01	1.00	0.98	0.98	0.97	0.97	0.97
2150	BIG DELTA	AK	3652	1.64	1.04	1.00	0.90	0.73	0.79	0.94	0.64
2151	BIG DELTA IRR	AK	4024	1.59	1.04	1.00	0.91	0.80	0.81	0.73	0.68
2340	FAIRBANKS WSO	AK	3047	1.71	1.05	1.00	0.89	0.62	0.75	0.76	0.57
2341	FAIRBANKS IRR	AK	4194	1.57	1.04	1.00	0.92	0.83	0.82	0.68	0.70
2430	HOMER WSO	AK	3605	1.65	1.04	1.00	0.90	0.72	0.78	0.77	0.63
2490	KENAI	AK	3501	1.66	1.04	1.00	0.90	0.78	0.72	0.62	

This data is excerpted from this table in sciver11.xls. The latest version of the Soil Conditioning Index is located at:  
<ftp://ftp.nssc.usda.gov/pub/agronomy/SCIfiles/>

50680	RAWLINS	WY	3056	1.71	1.05	1.00	0.89	0.86	0.78	0.72	0.57
50720	ROCK SPRINGS	WY	2996	1.72	1.05	1.00	0.89	0.86	0.75	0.69	0.56
51001	WASHINGTON	DC	5774	1.25	1.01	1.00	0.97	0.97	0.75	0.68	0.94
80000	GUAM	PB	6132	1.08	1.00	1.00	1.00	1.00	0.95	0.94	0.99
80040	KOROR	PB	6145	1.06	1.00	1.00	1.00	1.00	0.99	0.99	1.00
80080	MAJURO	PB	6143	1.06	1.00	1.00	1.00	1.08	1.00	1.00	1.00
80100	PAGOPAGO	PB	6142	1.06	1.00	1.00	1.00	1.00	1.00	1.00	1.00
80120	POHNPEI	PB	6143	1.06	1.00	1.00	1.00	1.08	1.00	1.00	1.00
80130	KOSRAE	PB	6144	1.06	1.00	1.00	1.00	1.08	1.00	1.00	1.00
80140	CHUUK	PB	6144	1.06	1.00	1.00	1.00	1.08	1.00	1.00	1.00
80180	YAP	PB	6143	1.06	1.00	1.00	1.00	1.08	1.00	1.00	1.00
81000	GUAM IRR.	PB	6136	1.07	1.00	1.00	1.00	1.08	1.00	1.00	0.99

**Table 508-2** Soil Disturbance Ratings

Operation number	Field Operations	----- Soil disturbing actions -----						Soil Disturbance Rating
		Inver- sion	Mixing	Lifting	Shat- tering	Aera- tion	Compac- tion	
1	Add mulch	0	0	0	0	0	5	5
2	Aerator, field surface, ground driven	1	1	2	3	4	1	12
3	Aerial seeding	0	0	0	0	0	0	0
4	Bale straw or residue	0	0	0	0	0	3	3
5	Bed shaper	1	1	1	1	1	2	7
6	Bed shaper, 12 in	1	1	1	1	1	2	7
7	Bedder, hipper, disk hiller	5	5	5	5	5	4	29
8	Bedder, hipper, hiller 12 in high	5	5	5	5	5	4	29
9	Bedder, hipper, hiller 15 in high	5	5	5	5	5	4	29
10	Bedder, hipper, hiller 18 in high	5	5	5	5	5	4	29
11	Begin growth	0	0	0	0	0	0	0
12	Begin new growth	0	0	0	0	0	0	0
13	Begin weed growth	0	0	0	0	0	0	0
14	Bulldozer, clearing	5	5	5	5	5	5	30
15	Burn residue	0	0	0	0	0	0	0

This data is excerpted from this table in sciver11.xls. The latest version of the Soil Conditioning Index is located at:  
<ftp://ftp.nssc.usda.gov/pub/agronomy/SCIfiles/>

169	Seedbed finisher	2	3	2	5	3	4	19
170	Shredder, flail or rotary	0	0	0	0	0	3	3
171	Shredder, rotary, regrow veg	0	0	0	0	0	3	3
172	Shredder, rotary, remove residue	0	0	0	0	0	3	3
173	Sprayer, kill crop	0	0	0	0	0	3	3
174	Sprayer, post emergence	0	0	0	0	0	3	3
175	Stalk puller	2	1	0	1	1	1	6
176	Striptiller w/middlebuster on beds	4	4	3	4	4	4	23
177	Subsoiler	1	2	2	4	5	1	15
178	Subsoiler bedder (ripper/hipper)	5	5	5	5	5	4	29
179	Subsoiler ripper, 24 to 40 in. deep	1	2	2	5	5	1	16
180	Sweep plow 20-40 in wide	0	0	5	5	4	3	17

**Table 508-3** Field operations subfactor

Average annual soil distribution rating	Field operations subfactor value	Average annual soil distribution rating	Field operations subfactor value	Average annual soil distribution rating	Field operations subfactor value	Average annual soil distribution rating	Field operations subfactor value	Average annual soil distribution rating	Field operations subfactor value
0	1.00	46	0.55	92	0.09	138	-0.37	184	-0.82
1	0.99	47	0.54	93	0.08	139	-0.38	185	-0.83
2	0.98	48	0.53	94	0.07	140	-0.39	186	-0.84
3	0.97	49	0.52	95	0.06	141	-0.40	187	-0.85
4	0.96	50	0.51	96	0.05	142	-0.41	188	-0.86
5	0.95	51	0.50	97	0.04	143	-0.42	189	-0.87
6	0.94	52	0.49	98	0.03	144	-0.43	190	-0.88
7	0.93	53	0.48	99	0.02	145	-0.44	191	-0.89
8	0.92	54	0.47	100	0.01	146	-0.45	192	-0.90
9	0.91	55	0.46	101	0.00	147	-0.46	193	-0.91
10	0.90	56	0.45	102	-0.01	148	-0.47	194	-0.92
11	0.89	57	0.44	103	-0.02	149	-0.48	195	-0.93
12	0.88	58	0.43	104	-0.03	150	-0.49	196	-0.94
13	0.87	59	0.42	105	-0.04	151	-0.50	197	-0.95
14	0.86	60	0.41	106	-0.05	152	-0.51	198	-0.96
15	0.85	61	0.40	107	-0.06	153	-0.52	199	-0.97
16	0.84	62	0.39	108	-0.07	154	-0.53	200	-0.98
17	0.83	63	0.38	109	-0.08	155	-0.54	201	-0.99
18	0.82	64	0.37	110	-0.09	156	-0.55	202	-1.00
19	0.81	65	0.36	111	-0.10	157	-0.55	203	-1.01
20	0.80	66	0.35	112	-0.11	158	-0.56	204	-1.02
21	0.79	67	0.34	113	-0.12	159	-0.57	205	-1.03
22	0.78	68	0.33	114	-0.13	160	-0.58	206	-1.04
23	0.77	69	0.32	115	-0.14	161	-0.59	207	-1.05
24	0.76	70	0.31	116	-0.15	162	-0.60	208	-1.06
25	0.75	71	0.30	117	-0.16	163	-0.61	209	-1.07
26	0.74	72	0.29	118	-0.17	164	-0.62	210	-1.08
27	0.73	73	0.28	119	-0.18	165	-0.63	211	-1.09
28	0.72	74	0.27	120	-0.19	166	-0.64	212	-1.10
29	0.71	75	0.26	121	-0.20	167	-0.65	213	-1.11
30	0.70	76	0.25	122	-0.21	168	-0.66	214	-1.12
31	0.69	77	0.24	123	-0.22	169	-0.67	215	-1.13
32	0.68	78	0.23	124	-0.23	170	-0.68	216	-1.14
33	0.67	79	0.22	125	-0.24	171	-0.69	217	-1.15
34	0.66	80	0.21	126	-0.25	172	-0.70	218	-1.16
35	0.65	81	0.20	127	-0.26	173	-0.71	219	-1.17
36	0.64	82	0.19	128	-0.27	174	-0.72	220	-1.18
37	0.63	83	0.18	129	-0.28	175	-0.73	221	-1.19
38	0.62	84	0.17	130	-0.29	176	-0.74	222	-1.20
39	0.61	85	0.16	131	-0.30	177	-0.75	223	-1.21
40	0.60	86	0.15	132	-0.31	178	-0.76	224	-1.22
41	0.59	87	0.14	133	-0.32	179	-0.77	225	-1.23
42	0.58	88	0.13	134	-0.33	180	-0.78	226	-1.24
43	0.57	89	0.12	135	-0.34	181	-0.79	227	-1.25
44	0.56	90	0.11	136	-0.35	182	-0.80	228	-1.26
45	0.55	91	0.10	137	-0.36	183	-0.81	229	-1.27

**Table 508-3** Field operations subfactor—continued

Average annual soil distribution rating	Field operations subfactor value	Average annual soil distribution rating	Field operations subfactor value	Average annual soil distribution rating	Field operations subfactor value	Average annual soil distribution rating	Field operations subfactor value
230	-1.28	276	-1.73	322	-2.19	368	-2.64
231	-1.29	277	-1.74	323	-2.20	369	-2.65
232	-1.30	278	-1.75	324	-2.21	370	-2.66
233	-1.31	279	-1.76	325	-2.22	371	-2.67
234	-1.32	280	-1.77	326	-2.23	372	-2.68
235	-1.33	281	-1.78	327	-2.24	373	-2.69
236	-1.34	282	-1.79	328	-2.25	374	-2.70
237	-1.35	283	-1.80	329	-2.26	375	-2.71
238	-1.36	284	-1.81	330	-2.27	376	-2.72
239	-1.37	285	-1.82	331	-2.28	377	-2.73
240	-1.38	286	-1.83	332	-2.29	378	-2.74
241	-1.39	287	-1.84	333	-2.30	379	-2.75
242	-1.40	288	-1.85	334	-2.31	380	-2.76
243	-1.41	289	-1.86	335	-2.32	382	-2.78
244	-1.42	290	-1.87	336	-2.33	383	-2.79
245	-1.43	291	-1.88	337	-2.34	384	-2.80
246	-1.44	292	-1.89	338	-2.35	385	-2.81
247	-1.45	293	-1.90	339	-2.36	386	-2.82
248	-1.46	294	-1.91	340	-2.37	387	-2.83
249	-1.47	295	-1.92	341	-2.38	388	-2.84
250	-1.48	296	-1.93	342	-2.39	389	-2.85
251	-1.49	297	-1.94	343	-2.40	390	-2.86
252	-1.50	298	-1.95	344	-2.41	391	-2.87
253	-1.51	299	-1.96	345	-2.42	392	-2.88
254	-1.52	300	-1.97	346	-2.43	393	-2.89
255	-1.53	301	-1.98	347	-2.44	394	-2.90
256	-1.54	302	-1.99	348	-2.45	395	-2.91
257	-1.55	303	-2.00	349	-2.46	396	-2.92
258	-1.55	304	-2.01	350	-2.47	397	-2.93
259	-1.56	305	-2.02	351	-2.48	398	-2.94
260	-1.57	306	-2.03	352	-2.49	399	-2.95
261	-1.58	307	-2.04	353	-2.50	400	-2.96
262	-1.59	308	-2.05	354	-2.51	401	-2.97
263	-1.60	309	-2.06	355	-2.52	402	-2.98
264	-1.61	310	-2.07	356	-2.53	403	-2.99
265	-1.62	311	-2.08	357	-2.54	404	-3.00
266	-1.63	312	-2.09	358	-2.55		
267	-1.64	313	-2.10	359	-2.55		
268	-1.65	314	-2.11	360	-2.56		
269	-1.66	315	-2.12	361	-2.57		
270	-1.67	316	-2.13	362	-2.58		
271	-1.68	317	-2.14	363	-2.59		
272	-1.69	318	-2.15	364	-2.60		
273	-1.70	319	-2.16	365	-2.61		
274	-1.71	320	-2.17	366	-2.62		
275	-1.72	321	-2.18	367	-2.63		

**Table 508-4** Erosion subfactors

Rate of erosion	Erosion value	Rate of erosion	Erosion value	Rate of erosion	Erosion value	Rate of erosion	Erosion value
0.00	1.00	11.75	-1.48	23.50	-2.95	34.50	-3.77
0.25	0.94	12.00	-1.52	23.75	-2.98	34.75	-3.79
0.50	0.88	12.25	-1.56	24.00	-3.00	35.00	-3.80
0.75	0.81	12.50	-1.60	24.25	-3.03	35.25	-3.81
1.00	0.75	12.75	-1.64	24.50	-3.05	35.50	-3.82
1.25	0.69	13.00	-1.68	24.75	-3.08	35.75	-3.83
1.50	0.63	13.25	-1.72	25.00	-3.10	36.00	-3.84
1.75	0.56	13.50	-1.76	25.25	-3.12	36.25	-3.85
2.00	0.50	13.75	-1.80	25.50	-3.14	36.50	-3.86
2.25	0.44	14.00	-1.84	25.75	-3.16	36.75	-3.87
2.50	0.38	14.25	-1.88	26.00	-3.18	37.00	-3.88
2.75	0.31	14.50	-1.92	26.25	-3.20	37.25	-3.89
3.00	0.25	14.75	-1.96	26.50	-3.22	37.50	-3.90
3.25	0.19	15.00	-2.00	26.75	-3.24	37.75	-3.91
3.50	0.13	15.25	-2.03	27.00	-3.26	38.00	-3.92
3.75	0.06	15.50	-2.06	27.25	-3.28	38.25	-3.93
4.00	0.00	15.75	-2.09	27.50	-3.30	38.50	-3.94
4.25	-0.05	16.00	-2.12	27.75	-3.32	38.75	-3.95
4.50	-0.10	16.25	-2.15	28.00	-3.34	39.00	-3.96
4.75	-0.15	16.50	-2.18	28.25	-3.36	39.25	-3.97
5.00	-0.20	16.75	-2.21	28.50	-3.38	39.50	-3.98
5.25	-0.25	17.00	-2.24	28.75	-3.40	39.75	-3.99
5.50	-0.30	17.25	-2.27	29.00	-3.42	40.00	-4.00
5.75	-0.35	17.50	-2.30	29.25	-3.44		
6.00	-0.40	17.75	-2.33	29.50	-3.46		
6.25	-0.45	18.00	-2.36	29.75	-3.48		
6.50	-0.50	18.25	-2.39	30.00	-3.50		
6.75	-0.55	18.50	-2.42	30.25	-3.52		
7.00	-0.60	18.75	-2.45	30.50	-3.53		
7.25	-0.65	19.00	-2.48	30.75	-3.55		
7.50	-0.70	19.25	-2.51	31.00	-3.56		
7.75	-0.75	19.50	-2.54	31.25	-3.58		
8.00	-0.80	19.75	-2.57	31.50	-3.59		
8.25	-0.85	20.00	-2.60	31.75	-3.61		
8.50	-0.90	20.25	-2.63	32.00	-3.62		
8.75	-0.95	20.50	-2.65	32.25	-3.64		
9.00	-1.00	20.75	-2.68	32.50	-3.65		
9.25	-1.05	21.00	-2.70	32.75	-3.67		
9.50	-1.10	21.25	-2.73	33.00	-3.68		
9.75	-1.15	21.50	-2.75	33.25	-3.70		
10.00	-1.20	21.75	-2.78	33.50	-3.71		
10.25	-1.24	22.00	-2.80	33.75	-3.73		
10.50	-1.28	22.25	-2.83	34.00	-3.74		
10.75	-1.32	22.50	-2.85	34.25	-3.76		
11.00	-1.36	22.75	-2.88				
11.25	-1.40	23.00	-2.90				
11.50	-1.44	23.25	-2.93				

**Table 508-5** The effects of the farming systems on crop yields, residue production and maintenance of the soil organic matter (Texas A&M, Renner Research Station published research)

System number (lb/acre)	Crop grown (lb/acre)	Crop grown (lb/acre)	---- Residue returned -----		--- Organic matter ---		Total residue
			By crop (percent)	By system (percent)	At start (ton/acre)	At 12 years	
8	Wheat	984	5,114				
	Cotton	762	3,015				
	Sorghum	2,410	3,466	3,865	3.34	3.2	23.2
9	Wheat	1,128	5,318				
	Cotton	870	3,237				
	Sorghum	2,945	4,013	4,189	3.53	4.17*	44.9**

\*Increase or decrease is statistically significant at a probability of 5%.

\*\*Includes 5 tons of manure applied to row crops after 1954.



**Table 508-6** RUSLE crop parameter data

Crop code number	Crop name	Harvest Units	Yield	Pounds per unit	Residue: Yield ratio	Above Ground residue (lb)	Surface decomp. coeff.	Sub-surface decomp. coeff.	Roots in top 4 inches (lb)	Root-mass adjustment	Crop group
2	alf. brome /oat, harv	tons	1	2000	1	2000	0.019	0.019	4300	3.15	E
3	alf. brome, fall seed	tons	1	2000	1	2000	0.019	0.019	2500	2.25	E
4	alf. brome, spring seed	tons	1	2000	1	2000	0.019	0.019	4300	3.15	E
5	alf. brome, spring seed	tons	1	2000	1	2000	0.019	0.019	4300	3.15	E
6	alf. brome	tons	1.8	2000	1.0286	3703	0.019	0.019	4900	2.3232	E
7	alf. brome, winter graze	tons	1.8	2000	1.0286	3703	0.019	0.019	4900	2.3232	E
8	alf. brome, senes	tons	1.8	2000	1.0286	3703	0.019	0.019	4900	2.3232	E
9	alf. brome, senes winter graze	tons	1.8	2000	1.0286	3703	0.019	0.019	4900	2.3232	E
10	alf. fall seed senes	tons	1	2000	1	2000	0.02	0.02	2500	2.25	E
11	alf. spring seed senes	tons	1.6	2000	1	3200	0.02	0.02	2500	1.7812	E
12	alf. spring seed y2 regrowth	tons	1.6	2000	1	3200	0.02	0.02	2500	1.7812	E
13	alf. yr2 senes to yr3	tons	1	2000	1	2000	0.02	0.02	3000	2.5	E
14	alf. yr2 senes winter graze	tons	1	2000	1	2000	0.02	0.02	3000	2.5	E
15	alf. yr3 senes to yr4 regrowth	tons	1	2000	1	2000	0.02	0.02	3500	2.75	E

This data is excerpted from this table in sciver11.xls. The latest version of the Soil Conditioning Index is located at:  
<ftp://ftp.nssc.usda.gov/pub/agronomy/SCIfiles/>

262	Wheat, spring 14in rows	bu	35	60	1.3	2730	0.008	0.008	950	1.3479	A
263	Wheat, spring 7 in, NWRR	bu	60	60	1.353	4870.8	0.017	0.017	720	1.1478	D
264	Wheat, spring 7in rows	bu	30	60	1.3	2340	0.008	0.008	970	1.4145	A
265	Wheat, spring, 10 in, NWRR	bu	40	60	1.353	3247.2	0.017	0.017	520	1.1601	D
266	Wheat, winter 14in rows	bu	45	60	1.7	4590	0.008	0.008	1200	1.2614	A
267	Wheat, winter 7in rows	bu	40	60	1.7	4080	0.008	0.008	1080	1.2647	A
268	Wheat, winter cover	lbs	4000	1	1	4000	0.017	0.017	400	1.1	D
269	Wheat, winter graze out South	lbs	800	1	1	800	0.008	0.008	1000	2.25	A
270	Wheat, winter graze, grain	bu	30	60	1.7	3060	0.008	0.008	850	1.2777	A
271	Wheat, winter grazed forage	lbs	2000	1	0.2	400	0.017	0.017	660	2.65	D
272	Wheat, winter low yield NWRR	bu	30	60	1.75	3150	0.017	0.017	250	1.079365	D
273	Wheat, winter late seed NWRR	bu	30	60	1.75	3150	0.017	0.017	150	1.047619	D
274	Wheat, winter S.E.	bu	40	60	1.7	4080	0.008	0.008	1070	1.2622	A
275	Wheat, winter silage	tons	2	2000	0.056	224	0.017	0.017	1000	5.4642	D
276	Wheat, winter, early seed, 10 in	bu	50	60	1.434	4302	0.017	0.017	690	1.160391	D
277	Wheat, winter, early seeding	bu	60	60	1.434	5162.4	0.017	0.017	970	1.187897	D
278	Wheat, winter, hay or silage	tons	2	2000	0.056	224	0.017	0.017	940	5.196429	D
279	Wheat, winter, late seeding	bu	70	60	1.43	6006	0.017	0.017	1080	1.17982	D
280	Barley, spring, AK	bu	30	48	1.5	2160	0.008	0.008	830	1.3842	A
281	Broccoli, AK	lbs	9500	1	0.30526	2900	0.02	0.02	250	1.0862	E
282	Bromegrass, seedng yr, AK	tons	1.5	2000	1	3000	0.017	0.017	1700	1.5666	D
283	Bromegrass, y2 senesc to yr3 AK	tons	1	2000	1	2000	0.017	0.017	2500	2.25	D
284	Bromegrass, yr3 senesc to yr4 AK	tons	1	2000	1	2000	0.017	0.017	2500	2.25	D
285	Cabbage, AK	cwt	230	100	0.11	2530	0.02	0.02	240	1.0948	E
286	Canola, spring, AK	bu	25	50	2.4	3000	0.016	0.016	800	1.2666	C
287	Cauliflower, AK	lbs	10300	1	0.25	2575	0.02	0.02	290	1.1126	E

# Soil Conditioning Index Worksheet

Version 10 September 15, 1999

Producer:  Location:  Staff:   
 Tract:  Field:

## A. Site Information

Location code:  City:  Rainfall Factor R:  (RUSLE)  
(From City Tab)  
 Soil:  Soil Erodibility Factor K (adjusted Kf) :  (RUSLE)  
 Slope, Length & Percent (LS factor) :  (RUSLE)  
  
 Maintenance Amount:  "Residue Equivalent Values" (REV) :  lbs./ac

## B. Management Information

Number of Yrs in Rotation:  Crop Rotation:   
 Tillage System:  Crop Mgt Factor C:  (RUSLE)  
 Support Conservation Practices:  Support Practice Factor P:  (RUSLE)

## C. Organic Material (OM)

(From Crop Tab)

Crop #	Crop	Yield	Harv Unit/Ac	Wt Harv Unit (lbs)	Res: Yield Ratio	Res Prod	Root Mass Adjust	Biomass Prod	Biomass Removed or Added	Total Biomass	Crop Group	REV Conv	REV lbs/ac

TOTAL REV:	<input style="width: 100px;" type="text"/>
NO. YEARS IN ROT.:	<input style="width: 100px;" type="text"/>
AVE. ANNUAL (RP):	<input style="width: 100px;" type="text"/>
MAINT. AMNT. (MA):	<input style="width: 100px;" type="text"/>
<b>SUBFACTOR (OM):</b>	<input style="width: 100px;" type="text"/>



---

## Conversions

Soil weight	=	2,000,000 pounds per acre furrow slice (one acre to a depth of 6 2/3 in.)
Soil organic matter (humus)	=	Soil organic carbon x 1.72
Soil organic carbon	=	Soil organic matter x 0.58
Weight of residue x 0.30	=	Soil organic matter
OM content of eroded sediment	=	Soil OM x 1.5

Annual rate of soil organic matter (humus) decay:

Loam or clay loam . . . . .	2.5%	of total soil reserve
Sandy loam . . . . .	3.5%	of total soil reserve
Loamy sand . . . . .	4.5%	of total soil reserve

---

<b>Contents:</b>	<b>Subpart 509A</b>	<b>Introduction and responsibilities</b> .....	509-1
		509.00 Background .....	509-1
		509.01 Responsibilities .....	509-1
	<b>Subpart 509B</b>	<b>Database management</b> .....	509-2
		509.10 Databases for erosion prediction tools .....	509-2
		509.11 Pesticide properties database .....	509-2
		509.12 Plant nutrient content database .....	509-2



---

**Subpart 509A Introduction and responsibilities****509.00 Background**

NRCS' s agronomic data exists in both electronic and hard copy formats, and is maintained at many different locations by a large number of people. There is no organized network among those who maintain the data to facilitate data sharing and to ensure against duplication of effort in data collection. Coordination is needed among all those in NRCS who collect, use, and manage data to share similar data sets that may apply in more than one state or region. This will reduce workloads and ensure data accuracy and integrity.

A large portion of the agronomic data used by NRCS is contained in data files developed for the implementation of various tools at the State and field office level, such as erosion prediction, nutrient management and pest management tools.

**509.01 Responsibilities**

The national agronomist is responsible for preparation of national policy and instructions pertaining to data management.

The cooperating scientists for water and wind erosion are responsible for developing and maintaining data for the implementation and application of erosion prediction models. They work directly with the National database coordinator for RUSLE2 and WEPS in developing and maintaining the databases used in these models. They provide national coordination for the development of Climate Zones, Crop Management Zones, Crop Management Templates, and assist in assigning dates of operations used in developing Crop Management Templates for erosion prediction tools.

The national nutrient management specialist is responsible for developing and maintaining databases for assisting States with implementation and application of nutrient management tools.

The national pest management specialist is responsible for developing and maintaining databases for assisting States with implementation and application of pest management tools.

The national database coordinator for RUSLE2 and WEPS is responsible for maintaining the national Vegetation and Operation databases used in these erosion prediction models. He/she assists in the coordination of Climate Zones, Crop Management Zones, dates of operations used in developing Management Templates, Crop Management Templates, and associated guidelines used in the Templates, and works closely with other national specialists to minimize duplication of effort in the Agency's data collection efforts. RUSLE/WEPS regional contacts serves as the liaisons with other agronomists and erosion specialists in the regions and with the cooperating scientists for wind and water erosion. They are responsible for maintaining consistency, both within regions and between regions, in data used erosion prediction tools.

At the State level, the appropriate State specialist (agronomist, nutrient/pest management specialist or water quality specialist) is responsible for proper use of NRCS databases in field office applications. They are also responsible for identifying if different or additional types of data are needed at the field level.

## Subpart 509B Database management

### 509.10 Databases for erosion prediction tools

#### (a) Crop and field operations databases

(1) An initial set of plant and operation data records has been developed under the leadership of ARS. These data records serve as guides for developing additional plant data records. Additional data records will be added to include all plant types and field implements and operations needed by NRCS. A national set of databases for each model, known as the NRCS Crop Database and the NRCS Operation Database, will be maintained by the agency. These official NRCS databases are to be used in RUSLE2 and WEPS 1.0 by NRCS field offices. The data records needed for the operations used and crops grown in the local area will be downloaded from the official databases onto field office computers.

(2) The national database coordinator will manage the official NRCS databases. The coordinator is responsible for adding, modifying, and revising all parameter values in the Crop and Operation Databases. Agronomists or designated erosion specialists, in coordination with the RUSLE/WEPS regional contacts, can submit additions or revisions to the NRCS Crop or Operation databases. If additional crop or operation records or revisions of existing records are needed, States will furnish any available data inputs to the database coordinator through their regional contact. The database coordinator will coordinate the development of the record and issue it for peer review and eventual posting to the official NRCS database. All agronomists or designated erosion specialists will be notified when new records have been posted.

#### (b) Climate databases

(1) For RUSLE2, the average monthly temperature and precipitation from one designated climate station will be used to represent each Climatic Zone. Local climate data records will be developed using these temperature and precipitation values, but location-specific R factor and 10-year storm EI values will be used in that local climate record. The national database coordinator will provide national coordination and assist the States in developing local climate records. Only official NRCS RUSLE2 Climate Databases

are to be used by NRCS field offices. The data records needed for the local area will be downloaded from the official NRCS Climate Database onto field office computers.

(2) Either simulated climate data (using WINDGEN and CLIGEN weather generators imbedded in the model) or actual climate data (stored in the model) will be used in WEPS 1.0.

#### (c) Soil databases

A soil data download from the National Soils Information System (NASIS) will be created and placed on the field office computer in a Microsoft Access database in conjunction with the Customer Service Toolkit. This database will contain soil data to be used in that field office as inputs for RUSLE2 and WEPS 1.0. The soil database downloaded to each field office will be the official NRCS Soil Database and will be updated only as supported by agency policy.

### 509.11 Pesticide properties database

The pesticide properties database is used by the National Agricultural Pesticide risk Analysis (NAPRA) model and the Windows-Pesticide Screening Tool (WIN\_PST). These environmental risk screening tools are used to predict the potential for pesticides to move with water and eroded soil/organic matter and affect non-target organisms.

The national pest management specialist will work with the Agricultural Research Service and representatives of companies that produce pesticides to keep this database current.

### 509.12 Plant nutrient content database

The Plant Nutrient Content Database contains estimates of the nitrogen, phosphorus, and potassium content in plant biomass for many agricultural crops. This information is useful to nutrient management planners who need estimates of plant nutrient content to develop nutrient management plans. It becomes particularly valuable when nutrient are applied in quantities that are a function of the nutrient content of plant biomass.

The national nutrient management specialist will work with the Agricultural Research Service and Land Grant Universities to update and expand this database.



---

# Glossary

---

<b>A factor</b>	The computed longtime average annual soil loss carried by runoff from specific field slopes in specified cropping and management systems. It is expressed in the RUSLE model in tons/acre/year.
<b>Abrasion</b>	Breakdown of clods, crusts, and plant material by the impact of particles moved by wind in saltation. The impacting particles may also abrade. Abrasion causes soil aggregates to break down progressively as wind erosion continues.
<b>Accelerated erosion</b>	Erosion of soil resulting from disturbance of the natural landscape. It results largely from the consequences of human activity, such as tillage, grazing and removal of vegetative cover.
<b>Adsorption</b>	The process by which atoms, molecules, or ions are taken up from the soil solution or soil atmosphere and retained on the surfaces of solids by chemical or physical binding.
<b>Aggregate stability</b>	The ability of a soil aggregate to resist various destructive forces, such as tillage, abrasion by wind or flowing water, or raindrop force.
<b>Aggregation, soil</b>	The cementing or binding together of primary soil particles (sand, silt, and clay) into a secondary unit, which unit contributes to the soil structure.
<b>Agronomic rate</b>	The rate at which fertilizers, organic wastes or other amendments can be added to soils for optimum plant growth.
<b>Air-dry weight</b>	Weight of a substance after it has been allowed to dry to equilibrium with the atmosphere.
<b>Amendment</b>	A substance added to the soil to improve plant growth, such as lime.
<b>Allelopathy</b>	Production of a substance by one organism that inhibits one or more other organisms.
<b>Angle of deviation</b>	The angle between prevailing wind erosion direction and a line perpendicular to: (1) the long side of the field or strip, when determining unsheltered distance using a wind erosion direction factor, or (2) row direction when determining effect of wind direction on the ridge roughness factor.
<b>Available water holding capacity</b>	The capacity of a soil to hold water in a form available to plants, usually expressed in inches of water per inch of soil depth. Commonly defined as the amount of water held in the soil between field capacity and wilting point.
<b>Avalanching</b>	The increase in rate of soil flow with distance downwind across an area being eroded by wind.
<b>Biomass</b>	The total mass of living organisms in a given volume or mass of soil, or in a particular environment. Compare <b>Phytomass</b> .
<b>Biochemical oxygen demand (BOD)</b>	The amount of oxygen required by aerobic organisms to carry out oxidative metabolism in water containing organic matter, such as sewage. BOD is used as an indirect measure of the concentration of biologically degradable material present in organic wastes. Also known as Biological oxygen demand.

---

<b>Bioremediation</b>	The use of biological agents to reclaim soil and water polluted by substances hazardous to the environment or human health.
<b>Buffer strip</b>	A narrow strip of grass or other close-growing vegetation that, when placed along the contour on a slope, traps sediment that was produced on the hillslope above.
<b>Bulk density, soil</b>	The mass of dry soil per unit bulk volume, including both solids and pore space. The value is expressed as grams per cubic centimeter ( $\text{g/cm}^3$ ) or megagrams per cubic meter, ( $\text{Mg/m}^3$ ).
<b>C factor - Water erosion</b>	Cover and management factor in RUSLE. It combines the effects of prior land use, crop canopy, surface cover, surface roughness, and soil moisture to predict a soil loss ratio for a crop or other vegetation, cropping period, or season.
<b>C Factor – Wind erosion</b>	Climatic factor in WEQ. It is an index of climatic erosivity, specifically wind speed and surface soil moisture. The factor for any given location is based on long-term climatic data and is expressed as a percentage of the C factor for Garden City, KS, which has been assigned a value of 100.
<b>Calcareous soil</b>	Soil containing sufficient free calcium carbonate or magnesium carbonate to effervesce visibly when treated with cold 0.1 <i>N</i> hydrochloric acid. High content of lime (up to about 5 percent), particularly in the clay fraction, appreciably increases erodibility by wind.
<b>Calcium carbonate equivalent</b>	The content of carbonate in a liming material or calcareous soil calculated as if all of the carbonate is in the form of $\text{CaCO}_3$ . See also <b>Lime, agricultural</b> .
<b>Canopy</b>	The vertical projection downward of the aerial portion of plants, usually expressed as percent of ground so occupied.
<b>Carbon cycle</b>	The sequence of transformations whereby carbon dioxide is converted to organic forms by photosynthesis or chemosynthesis, recycled through the biosphere (with partial incorporation into sediments), and ultimately returned to its original state through respiration or combustion.
<b>Carbon-nitrogen ratio</b>	The ratio of the mass of organic carbon to the mass of organic nitrogen in soil, organic material, plants, or microbial cells.
<b>Cation exchange capacity (CEC)</b>	The sum of exchangeable bases plus total soil acidity at a specific pH values, usually 7.0 or 8.0. It is usually expressed in milliequivalents per 100 grams ( $\text{meq}/100 \text{ g}$ ) or centimoles per kilogram ( $\text{cmol}/\text{kg}$ ).
<b>Classical gully erosion</b>	Erosion caused by the action of runoff water in concentrated flow channels. These flow channels are well-defined, permanent drainageways that cannot be crossed by ordinary farming operations.
<b>Climatic erosivity</b>	The relative influence of climate on field erodibility by wind in different regions, specifically the effects of average wind speed and effective soil surface moisture.

---



---

<b>Clod</b>	A compact, coherent mass of soil greater than 2 millimeters in equivalent diameter, often created by tillage or other mechanical disturbance of the soil.
<b>Coarse fragments</b>	Rock or mineral particles greater than 2 millimeters in diameter.
<b>Compost</b>	Organic residues, or a mixture of organic residues and soil, that have been mixed, piled, and moistened, with or without addition of fertilizer and lime, and generally allowed to undergo thermophilic decomposition until the original organic materials have been substantially altered or decomposed.
<b>Contour farming</b>	The practice of using ridges and furrows left by tillage to redirect runoff from a path directly downslope to a path around the hillslope.
<b>Cover crop</b>	Close-growing crop that provides soil protection, seeding protection and soil improvement between periods of normal crop production, or between trees in orchards and vines in vineyards. When incorporated into the soil, cover crops may be referred to as <b>Green manure crops</b> .
<b>Critical wind erosion period</b>	Period of the year when the greatest amount of wind erosion can be expected to occur from a field under an identified management system. It is the period when the combination of vegetative cover, soil surface conditions, and expected erosive winds result in the greatest potential for wind erosion.
<b>Crop residue management</b>	Maintaining stubble, stalks, and other crop residue on the soil surface or partially incorporated into the surface layer to reduce erosion, conserve soil moisture, and improve soil tilth.
<b>Crop rotation</b>	A planned sequence of several different crops grown on the same land in successive years or seasons, done to replenish the soil, reduce insect, weed and disease populations, or to provide adequate feedstocks for livestock operations.
<b>Crop tolerance to wind erosion</b>	Ability of crop plants to tolerate wind blown soil particles when in the seedling stage or exposure of plant roots where soil is eroded away, or burial of plants by drifting soil, or desiccation and twisting of plants by the wind.
<b>Crust</b>	A thin surface layer, where aggregates are bound together and the surface is sealed. It is more compact and mechanically stable than the soil material immediately beneath it. Crust is characterized by its dense, platy structure that becomes less distinct with depth until it merges with the soil below. Crust is a transitory condition.
<b>Deposition</b>	The accumulation of eroded soil material on the land surface when the velocity or transport capacity of the transporting agent (wind or water) is reduced.
<b>Desert pavement</b>	A non-erodible soil surface devoid of erodible materials or consisting of gravel or stones left on the land surface. It occurs in desert regions as a result of the removal of fine materials by wind or water erosion. Desert pavement is virtually non-erodible.

---

<b>Detachment</b>	The removal of transportable fragments of soil material from the soil mass by an eroding agent, usually falling raindrops, running water, wind, or windblown soil particles. Detachment is the process that makes soil particles or aggregates available for transport.
<b>Drought year</b>	Any year when precipitation is less than 80 percent of the long-term normal.
<b>Dry aggregate</b>	A compound or secondary air-dry soil particle that is not destroyed by dry sieving.
<b>Dryland farming</b>	Crop production without irrigation (rain-fed agriculture).
<b>Dust storm</b>	A strong turbulent wind carrying large amounts of soil particles in suspension.
<b>E tables</b>	Tables derived from computer solutions (WEROSE) of the Wind Erosion Equation that display values of average annual wind erosion per acre (E) for various combinations of soil erodibility (I), ridge roughness (K), climate (C), unsheltered distance (L), and vegetative cover (V).
<b>Effective precipitation</b>	That portion of the total rainfall precipitation which becomes available for plant growth.
<b>Electrical conductivity (EC<sub>e</sub>)</b>	The electrical conductance of an extract from a soil saturated with distilled water. The preferred units are decisiemens per meter (dS/m) at 25° C, but it may also be expressed as siemens per meter (S/m) or millimhos per centimeter (mmhos/cm). See <b>Saline soil</b> .
<b>Ephemeral gully erosion</b>	Erosion that occurs from the action of runoff water which concentrates in shallow flow channels when rills converge. These flow channels are alternately filled with soil by tillage operations and re-formed in the same general location by subsequent runoff events.
<b>Erodibility</b>	The susceptibility of soil to erosion. For water erosion, soils with low erodibility include fine textured soils high in clay that are resistant to detachment, and coarse textured soils high in sand that have low runoff. Soils having a high silt content are highly susceptible to erosion. For wind erosion, soil erodibility is related to the percentage of nonerodible surface soil aggregates larger than 0.84 millimeters in size. Soil erodibility is expressed by the K factor in RUSLE, and by the I factor in the WEQ.
<b>Erosive wind energy</b>	The capacity of winds above the threshold velocity to cause erosion. Erosive wind energy is a function of the cube of wind speed and the duration of erosive winds.
<b>Erosive wind energy distribution</b>	The distribution of erosive wind energy over time at any geographic location.
<b>Erosivity</b>	The energy (amount) and intensity of rainstorms that cause soil to erode. Erosivity includes the effects of raindrop impact on the soil and the amount and rate of runoff likely to be associated with the rainfall event.

<b>Evapotranspiration</b>	The combined loss of water from a given area, and during a specified period of time, by evaporation from the soil surface and by transpiration from plants.
<b>Eutrophication</b>	A process that increases the amount of nutrients, especially nitrogen and phosphorus, in an aquatic ecosystem. Eutrophication occurs naturally over geological time but may be accelerated by human activities, such as poor nutrient management, waste disposal or land drainage, leading to an increase in aquatic vegetation and a decrease in plant diversity.
<b>Fallow</b>	The practice of leaving land uncropped, either weed-free or with volunteer vegetation, during at least one period when a crop would normally be grown; done to control weeds or accumulate water or available plant nutrients.
<b>Fertility, soil</b>	The quality of a soil that enables it to provide nutrients in adequate amounts and in proper balance for the growth of specified plants or crops.
<b>Fertilizer</b>	Any organic or inorganic material of natural or synthetic origin (other than liming materials) that is added to a soil to supply one or more plant nutrients essential to the growth of plants.
<b>Fertilizer analysis</b>	The percent composition of a fertilizer as determined in a laboratory and expressed as total N, available phosphoric acid (P <sub>2</sub> O <sub>5</sub> ) equivalent, and water-soluble potash (K <sub>2</sub> O) equivalent.
<b>Fibric organic soil materials</b>	The least decomposed of all the organic soil materials, containing very high amounts of fiber that are well preserved and readily identifiable as to botanical origin. Compare <b>Hemic organic soil</b> and <b>Sapric organic soil</b> .
<b>Field capacity (Field water capacity)</b>	The content of water, on a mass or volume basis, remaining in a soil two to three days after being saturated with water, and from which free drainage is negligible.
<b>Friable</b>	A term describing soils that when either wet or dry can be easily crumbled between the fingers.
<b>Geologic erosion</b>	The wearing away of the earth's surface by the forces of water and wind. Sometimes referred to as natural erosion, it is responsible for the natural topographic cycles, as it wears away higher points of elevation and constructs valleys and alluvial plains.
<b>Green manure crop</b>	Any crop grown for soil improvement by being incorporated into the soil while green or soon after maturity. See <b>Cover crop</b> .
<b>Greenhouse effect</b>	The absorption of solar radiant energy by the earth's surface and its release as heat into the atmosphere; longer infrared heat waves are absorbed by the air, principally by carbon dioxide and water vapor, thus, the atmosphere traps heat much as does the glass in a greenhouse.
<b>Ground water</b>	That portion of the water below the surface of the ground at a pressure equal to or greater than atmospheric. See also <b>Water table</b> .

<b>Hard seed</b>	Seed that is dormant due to a seed coat impervious to either water or oxygen.
<b>Hemic organic soil materials</b>	An organic soil that is intermediate in degree of decomposition between the less decomposed <b>fibric</b> and the more decomposed <b>sapric</b> materials.
<b>Hydrologic cycle</b>	The fate of water from the time of precipitation until the water has been returned to the atmosphere by evaporation and is again ready to be precipitated.
<b>Hydroseeding</b>	Planting seed in a water mixture by pumping through a nozzle that sprays the mixture onto a seedbed. The water mixture may also contain fertilizer and mulches.
<b>Inoculate</b>	To treat, usually seeds, with microorganisms to create a favorable response. Most often refers to the treatment of legume seeds with <b>Rhizobium</b> or <b>Bradyrhizobium</b> bacteria to stimulate dinitrogen fixation.
<b>Isolated field</b>	A field where the rate of soil flow is zero at the windward edge of the field due to the presence of a stable border. An isolated field is not protected by barriers and is exposed to open wind velocities. The <b>Wind Erosion Equation</b> applies to conditions on an isolated field.
<b>Isoline</b>	A line on a map or chart along which there is a constant value of a variable such as wind velocity or climatic erosivity.
<b>K factor - Water Erosion</b>	Soil erodibility factor in RUSLE that quantifies the susceptibility of soil particles to detachment and movement by water. The K value is the soil-loss rate per erosion index unit for a specified soil as measured on a standard plot, which is defined as a 72.6-ft length of uniform 9 percent slope in continuous clean-tilled fallow.
<b>K Factor – Wind Erosion</b>	The soil roughness factor K, for WEQ. It is a measure of the effect of oriented roughness (ridges) and random roughness (cloddiness) on erosion. See <b>Random Roughness</b> and <b>Ridge Roughness</b> .
<b>Knoll</b>	An abrupt change in topography characterized by windward slope change greater than 3 percent and windward slope less than 500 feet long.
<b>Knoll erodibility</b>	The increase in wind erosion potential resulting from the compression of wind flowlines and accompanying increased velocity over the crest of knolls. A knoll erodibility factor is used to adjust estimated erosion where these conditions occur.
<b>Land capability</b>	The suitability of land for use without permanent damage. Land capability, as ordinarily used in the USA, is an expression of the effect of physical land conditions, including climate, on the total suitability for use, without damage, for crops that require regular tillage, for grazing, for woodland, and for wildlife. Land capability involves consideration of the risks of land damage from erosion and other causes and the difficulties in land use owing to physical land characteristics, including climate.

<b>Land capability class</b>	<p>One of the eight classes of land in the land capability classification of NRCS; distinguished according to the risk of land damage or the difficulty of land use; they include:</p> <p>Land suitable for cultivation and other uses.</p> <p>Class I - Soils that have few limitations restricting their use.</p> <p>Class II - Soils that have some limitations, reducing the choice of plants or requiring moderate conservation practices.</p> <p>Class III - Soils that have severe limitations that reduce the choice of plants or require special conservation practices, or both.</p> <p>Class IV - Soils that have very severe limitations that restrict the choice of plants, require very careful management or both.</p> <p>Land generally not suitable for cultivation (without major treatment).</p> <p>Class V - Soils that have little or no erosion hazard, but that have other limitations, impractical to remove, that limit their use largely to pasture, range, woodland, or wildlife food and cover.</p> <p>Class VI - Soils that have severe limitations that make them generally unsuited for cultivation and limit their use largely to pasture or range, woodland, or wildlife food and cover.</p> <p>Class VII - Soils that have very severe limitations that make them unsuited to cultivation and that restricts their use largely to grazing, woodland, or wild life.</p> <p>Class VIII - Soils and landforms that preclude their use for commercial plant production and restrict their use to recreation, wildlife, water supply, or aesthetic purposes.</p>
<b>Leaching</b>	The removal of soluble materials from one zone in soil to another via water movement in the profile.
<b>Liebig's law of the minimum</b>	A logical principle of crop production, summarized as: <i>The level of crop production is constrained by the essential element that is most limiting.</i>
<b>Lime, agricultural</b>	A soil amendment containing calcium carbonate, magnesium carbonate and other materials, used to neutralize soil acidity and furnish calcium and magnesium for plant growth. Classification, including calcium carbonate equivalent and limits in lime particle size, is usually prescribed by law or regulation.
<b>Loess</b>	Soil material transported and deposited by wind, consisting predominantly of silt-sized particles.
<b>LS factor</b>	The <b>RUSLE</b> factor that accounts for the combined effects of length and steepness of slope on soil loss. The factor value represents the ratio of soil loss on a given slope length and steepness to soil loss from a slope that has a length of 72.6-ft and a steepness of 9 percent, where all other conditions are the same.
<b>Management period</b>	A period of time during a cropping sequence when cover and management effects are approximately uniform or otherwise result in uniform rates of erosion during the period.
<b>Mineral soil</b>	A soil composed mainly of, and having its properties determined by, mineral matter, with less than 20% organic matter. Compare <b>Organic soil</b> .



<b>Mineralization</b>	The conversion of an element from an organic form to an inorganic state as a result of microbial activity.
<b>Mulch</b>	Any material such as straw, sawdust, leaves, plastic film, loose soil, or similar material that is spread or formed upon the surface of the soil to protect the soil and/or plant roots from the effects of raindrops, soil crusting, freezing, evaporation, etc.
<b>Mulch tillage</b>	Managing the amount, orientation, and distribution of crop and other plant residue on the soil surface year-round, while growing crops where the entire field surface is tilled prior to planting.
<b>Nitrogen cycle</b>	The continuous process by which nitrogen circulates among the air, soil, water, plants, and animals of the earth. Nitrogen in the atmosphere is converted by bacteria into forms that green plants can absorb from the soil; animals eat these plants (or eat other animals that feed on the plants); the animals and plants die and decay; the nitrogenous substances in the decomposed organic matter return to the atmosphere and the soil.
<b>No-till/Strip till</b>	Managing the amount, orientation and distribution of crop and other plant residues on the soil surface year-round, while growing crops in narrow slots, or tilled or residue free strips in soil previously untilled by full-width inversion implement
<b>Northwestern Wheat and Range Region (NWR)</b>	Areas of non-irrigated cropland in the Pacific Northwest and mountainous regions of the west. It includes portions of eastern Washington, north central Oregon, northern and southeastern Idaho, western Montana, western Wyoming, northern Utah and northern California. Rainfall and erosion processes in this region are dominated by winter events.
<b>Organic farming</b>	A crop production system that reduces, avoids or largely excludes the use of synthetically-produced fertilizers, pesticides, growth regulators and livestock feed additives.
<b>Organic soil</b>	A soil that contains a high percentage (greater than 20 percent) of organic matter throughout the solum. Compare <b>Mineral soil</b>
<b>Oven-dry weight</b>	The weight of a substance after it has been dried in an oven at 105 degrees C to equilibrium.
<b>P factor</b>	The support practice factor in RUSLE. It is a measure of the soil loss with a specific support practice to the corresponding loss with upslope and downslope tillage. On cultivated land, support practices considered in RUSLE include contouring, stripcropping, buffer strips, and terraces. These practices principally effect erosion by modifying the flow pattern, grade or direction of surface runoff and by reducing the amount and rate of runoff.
<b>Permanent wilting point (Wilting coefficient)</b>	The largest water content of a soil at which indicator plants, growing in that soil, wilt and fail to recover when placed in a humid chamber. Often estimated by the soil water content at $-1.5$ MPa ( $-15$ bars) soil matric potential.



<b>Permeability</b>	The ease with which water, air, or plant roots penetrate or pass through a soil horizon.
<b>Phytomass</b>	The total mass of plant material in a given system or environment. Compare <b>Biomass</b> .
<b>Precipitation-effectiveness (PE) index</b>	An index of the effectiveness of precipitation, calculated from mean monthly precipitation and mean monthly temperature at a specific geographical location. A modified P-E index is used to represent effective surface soil moisture in calculation of the WEQ climatic factor C.
<b>Preponderance</b>	A ratio which expresses how much of the erosive wind energy occurs parallel to the prevailing wind erosion direction, as compared to the amount of erosive wind energy occurring perpendicular to the prevailing direction. A preponderance of 1.0 indicates that as much wind erosion force occurs perpendicular to the prevailing direction as occurs parallel to that direction. A higher preponderance indicates more of the force is parallel to the prevailing wind erosion direction.
<b>Prevailing wind direction</b>	The direction from which winds most commonly occur. This may not be the same as the prevailing wind erosion direction.
<b>Pure live seed</b>	Percentage of pure germinating seed: (pure seed percentage x germination percentage)/100.
<b>Prevailing wind erosion direction</b>	The direction of erosive winds where there is potential for the greatest amount of soil to be moved, relative to the erosive force of winds from other directions.
<b>R equivalent (<math>R_{eq}</math>) factor</b>	The factor used in place of the RUSLE R factor in the Northwestern Wheat and Range Region of the U.S. to measure the unique effects of melting snow, rain on snow, and/or rain on thawing soil. Much of this soil loss occurs by rilling when the surface part of the soil profile thaws and snowmelt or rain occurs on the still partially frozen soil.
<b>R factor</b>	The rainfall and runoff factor in RUSLE that accounts for the energy and intensity of rainstorms. It is a measure of total storm energy times the maximum 30-minute intensity.
<b>Random roughness</b>	The standard deviation of the soil surface elevations when changes because land slope or nonrandom (oriented) tillage marks are removed from consideration. Random roughness decreases water erosion by ponding water and sediment in small localized depressions, decreasing transport capacity and runoff detachment of overland flow. Random roughness decreases wind erosion by increasing the threshold wind speed at which erosion begins and by trapping soil being moved by the wind.
<b>Reference condition</b>	A standard wind tunnel condition for small grain equivalent determination where small grain stalks 10 inches long are lying flat on the soil surface in 10-inch rows which are perpendicular to the wind direction, with stalks oriented parallel to the wind direction.

---

<b>Relative field erodibility</b>	An index of relative erodibility under field conditions. Wind tunnel erodibility is adjusted for the effect of unsheltered distance and of the resistance of soil textural classes to breakdown of surface crusts by abrasion and avalanching. Compared to the wind tunnel, erodibility of a field surface is greater because the longer unsheltered distance allows abrasion and avalanching to occur.
<b>Ridge roughness</b>	The degree of oriented roughness determined by the height and width of ridges formed by tillage and planting implements. Ridges provide sheltered zones that trap moving soil particles.
<b>Rill</b>	A small, intermittent water course with steep sides; usually only several centimeters deep.
<b>Rhizobia</b>	Bacteria able to live symbiotically in roots of leguminous plants, from which they receive energy and often utilize molecular nitrogen. Collective common name for the genus <i>Rhizobium</i> . See <b>Inoculate</b> .
<b>Runoff</b>	That portion of precipitation or irrigation on an area which does not infiltrate, but instead is discharged from the area.
<b>RUSLE (Revised Universal Soil Loss Equation)</b>	An empirical model that predicts long-term average annual soil loss from rainfall and runoff for a given set of climatic conditions, on a defined land slope, and under a specified cropping and tillage management system. Expressed as $A=RKLSCP$ , where E is the average annual soil loss in tons/acre/year, R is the rainfall-runoff factor, K is the soil erodibility factor, L is slope length, S is slope steepness, C is the cover-management factor and P is the support practice factor. RUSLE is an update of the USLE, and is made available as a computer program to facilitate calculations.
<b>Saline seep</b>	Intermittent or continuous saline water discharge at or near the soil surface under dryland conditions that reduces or eliminates crop growth. It is differentiated from other saline soil conditions by recent and local origin, shallow water table, saturated root zone, and sensitivity to cropping systems and precipitation.
<b>Saline soil</b>	A nonsodic soil containing sufficient soluble salt to adversely affect the growth of most crop plants. The lower limit of saturation extract electrical conductivity of such soils is conventionally set at 4 dS m <sup>-1</sup> (at 25° C). Actually, sensitive plants are affected at half this salinity and highly tolerant ones at about twice this salinity.
<b>Saltation</b>	Soil movement in wind where particles skip or bounce along the soil surface in response to wind forces. Particles in the size range from 0.1 to 0.5 mm (0.004 to 0.02 in) usually move in this manner.
<b>Salt-affected soil</b>	Soil that has been adversely modified for the growth of most crop plants by the presence of soluble salts, with or without high amounts of exchangeable sodium.
<b>Salt tolerance</b>	The ability of plants to resist the adverse, nonspecific effects of excessive soluble salts in the rooting medium.

---

<b>Sapric organic soil materials</b>	The most highly decomposed of the organic materials, having the highest bulk density, least amount of plant fiber, and lowest water content at saturation. Compare <b>Hemic organic soil</b> and <b>Fibric organic soil</b> .
<b>Seasonally variable K factor</b>	The average annual soil erodibility K factor value that has been adjusted to reflect the temporal variability associated with freezing and thawing or wetting and drying cycles during the year.
<b>Sheet erosion</b>	A form of water erosion in which a very thin layer is removed from the soil surface by detachment and overland flow.
<b>Small grain equivalent (SGe)</b>	The wind erosion control equivalent of <b>vegetative cover</b> , compared to a small grain standard. The standard (reference condition) is defined as small grain stalks 10 inches long lying flat on the soil surface in 10-inch rows which are perpendicular to the wind direction, with stalks oriented parallel to the wind direction. The small grain equivalent value is a function of kind, amount, and orientation of growing plants or plant residues on the soil surface.
<b>Soil erodibility index (I)</b>	The potential soil loss, in tons per acre per year, from a wide, level, unsheltered, isolated field with a bare, smooth, loose, and non-crustured surface, under climatic conditions like those in the vicinity of Garden City, Kansas.
<b>Soil loss tolerance (T)</b>	T is expressed as the average annual soil erosion rate (tons/acre/year) that can occur in a field with little or no long-term degradation of the soil resource thus permitting crop productivity to be sustained for an indefinite period of time.
<b>Soil surface moisture</b>	Adsorbed water films surrounding surface soil particles that increase the soil resistance to erosion. In developing the climatic factor, soil surface moisture is assumed to be proportional to the Thornthwaite Precipitation-Effectiveness (P-E) Index.
<b>Sorting</b>	Separation of various size classes of soil particles or aggregates during wind erosion. Soils tend to become coarser in response to continued sorting by erosion.
<b>Sprigging</b>	Vegetative establishment of herbaceous species using stolons, rhizomes, or tillers with soil. Vegetative material may be broadcast and then lightly covered with soil, or planted using a sprigging implement.
<b>Stable border</b>	A stable border defines the upwind boundary of an isolated field. It is an area with sufficient protection to prevent saltation from starting, and capable of trapping and holding incoming saltation from eroding areas upwind, thus preventing saltating soil particles from entering areas downwind.
<b>Stripcropping</b>	The practice of growing two or more crops in alternating strips along contours to control erosion.
<b>Surface armor</b>	A layer of coarse fragments or other non-erodible particles resistant to abrasion that remain on the soil surface after the removal of fine particles by erosion.

<b>Surface creep</b>	Soil movement by wind in which the coarser fractions are transported by rolling and sliding along the ground surface, primarily by the impact of particles in saltation rather than by direct force of the wind. Particles greater than 0.5 mm (0.02 in) in size are usually moved in this manner.
<b>Suspension</b>	Soil movement in wind whereby the finer fractions are transported over long distances floating in the windstream. Suspension is usually initiated by the impact of saltating particles. Particles moving in this manner are usually less than 0.1 mm (0.004 in) in size. Many suspension-size particles are created by abrasion during erosion.
<b>Threshold velocity</b>	The minimum velocity at which wind will begin moving soil particles from a smooth, bare, non-crusted surface. The threshold velocity is usually considered to be 13 mph at 1 foot above the soil surface, or 18 mph at 30 feet height.
<b>Tillage</b>	<p><b>Conventional</b> Primary and secondary tillage operations normally performed in preparing a seedbed and/or cultivating for a given crop grown in a given geographical area, usually resulting in little or no crop residues remaining on the surface after completion of the tillage sequence.</p> <p><b>Inversion</b> Reversal of vertical order of occurrence of layers of soil, or of the soil within a layer.</p> <p><b>Non-inversive</b> Tillage that does not mix (or minimizes the mixing of) soil horizons or does not vertically mix soil within a horizon.</p> <p><b>Subsoiling</b> Any treatment to non-inversively loosen soil below the A<sub>p</sub> horizon with a minimum of vertical mixing of the soil. Any treatment to fracture and/or shatter soil with narrow tools below the depth of normal tillage without inversion and with a minimum mixing of the soil. This loosening is usually performed by lifting action or other displacement of soil dry enough so that shattering occurs.</p>
<b>Tilth</b>	The physical condition of soil as related to its ease of tillage, fitness as a seedbed, and its impedance to seedling emergence and root penetration.
<b>Total Maximum Daily Load (TMDL)</b>	The maximum quantity of a particular water pollutant that can be discharged into a body of water without violating a water quality standard.
<b>Transport</b>	The movement of detached soil material across the land surface or through the air by wind or running water. Transport of soil particles in wind is by three modes: (1) saltation, (2) suspension, and (3) surface creep.
<b>Transport capacity</b>	The maximum amount of soil material that can be carried by wind or running water under given conditions.
<b>Trap strip</b>	A strip of grass or other erosion-resisting vegetation, planted between cultivated strips or fields and having sufficient width, height, and density to trap and store incoming saltation. Trap strips are usually not tall enough to create significant barrier effects.
<b>Unit plot</b>	A standard plot used to experimentally determine factor values in USLE and RUSLE. It is arbitrarily defined as being 72.6-feet long, with a uniform slope of 9 percent, in continuous fallow, tilled up and down the slope.

<b>Unsheltered distance</b>	The distance across an erodible field, measured along the prevailing wind erosion direction, beginning at a stable border on the upwind side and continuing downwind to a non-erodible or stable area, or to the downwind edge of the area being evaluated.
<b>Unsheltered field</b>	A field or portion of a field characterized by the absence of windbreaks or barriers and fully exposed to open wind velocity.
<b>USLE (Universal Soil Loss Equation)</b>	An empirical model that predicts long-term average annual soil loss for a given set of climatic conditions, on a defined land slope, and under a specified cropping and tillage management system. It has been replaced by RUSLE.
<b>Vegetative cover factor</b>	The effect of vegetative cover in the Wind Erosion Equation. It is expressed by relating the kind, amount and orientation of vegetative material present on the field to its equivalent in pounds per acre of small grain residue in reference condition <b>Small Grain Equivalent (SGe)</b> .
<b>Vegetative wind barrier</b>	Narrow strips of annual or perennial vegetation planted at intervals across fields for wind erosion control, snow management, or protection of sensitive crops. Barriers have sufficient height and density to create a sheltered zone downwind. In the protected zone, wind velocities are reduced enough to prevent saltation from beginning. Vegetative barriers may also trap incoming saltation, but this is a secondary function.
<b>Water erosion</b>	The detachment, transport, and deposition of soil particles by rainfall and runoff.
<b>Water table</b>	The upper surface of ground water or that level in the ground where the water is at atmospheric pressure.
<b>Wide field</b>	Any field with sufficient width to allow the rate of soil flow to reach the maximum that an erosive wind can sustain. This distance is the same for any erosive wind. It varies only and inversely with erodibility of the field surface. That is, the more erodible the surface, the shorter the distance in which maximum flow is reached.
<b>Windbreak</b>	A planting of trees, shrubs, or other vegetation, usually perpendicular or nearly so to the principal wind direction, to protect soil, crops, homesteads, roads, etc., against the effects of winds, such as wind erosion and the drifting of soil and snow.
<b>Wind erodibility group</b>	A grouping of soils that have similar properties affecting their resistance to wind erosion.
<b>Wind erosion</b>	The detachment, transport, and deposition of soil by wind.
<b>Wind erosion direction factor</b>	A numerical factor used to calculate the equivalent unsheltered distance. The factor accounts for field shape (length/width ratio), field width, preponderance, and angle of deviation of the prevailing wind erosion direction from a line perpendicular to the long side of the field or strip.

---

<b>WEQ (Wind Erosion Equation)</b>	An equation used to estimate wind erosion and design wind erosion control systems. Expressed as $E = i(KCLV)$ where E is the average annual soil loss expressed in tons per acre per year; I is the soil erodibility; K is the soil ridge roughness factor; C is the climatic factor; L is the equivalent unsheltered distance across the field along the prevailing wind erosion direction; and V is the equivalent vegetative cover.
<b>Wind stripcropping</b>	A method of farming whereby erosion-resistant crop strips are alternated with strips of erosion-susceptible crops or fallow. Erosion-resistant strips reduce or eliminate saltation and act as soil traps designed to reduce soil avalanching. Strips are perpendicular or nearly so to the direction of erosive winds.
<b>Wind tunnel</b>	A duct in which experimental situations are created and tested by exposure to air streams under controlled conditions. Both laboratory and portable field wind tunnels are used in wind erosion research.
<b>Windbreak</b>	A living barrier of trees or combination of trees and shrubs designed to reduce wind erosion, conserve energy or moisture, control snow deposition, or provide shelter for livestock or wildlife. When used to control wind erosion, windbreaks deflect wind forces and reduce wind velocity in the downwind sheltered zone below the threshold required for initiation of soil movement.
<b>Yield</b>	The amount of a specified substance produced (e.g., grain, straw, total dry matter) per unit area.