

Universal Library™

User's Guide



Document Revision 6.6, July, 2005

© Copyright 2005, Measurement Computing Corp

Your new Measurement Computing product comes with a fantastic extra —

Management committed to your satisfaction!

Refer to www.mccdaq.com/excteam.html for the names, titles, and contact information of each key executive at Measurement Computing.

Thank you for choosing a Measurement Computing product—and congratulations! You own the finest, and you can now enjoy the protection of the most comprehensive warranties and unmatched phone tech support. It's the embodiment of our two missions:

- To offer the highest-quality, computer-based data acquisition, control, and GPIB hardware and software available—at the best possible price.
- To offer our customers superior post-sale support—FREE. Whether providing unrivaled telephone technical and sales support on our latest product offerings, or continuing that same first-rate support on older products and operating systems, we're committed to you!

30 Day Money Back Guarantee: You may return any Measurement Computing Corporation product within 30 days of purchase for a full refund of the price paid for the product being returned. If you are not satisfied, or chose the wrong product by mistake, you do not have to keep it. Please call for an RMA number first. No credits or returns accepted without a copy of the original invoice. Some software products are subject to a repackaging fee.

These warranties are in lieu of all other warranties, expressed or implied, including any implied warranty of merchantability or fitness for a particular application. The remedies provided herein are the buyer's sole and exclusive remedies. Neither Measurement Computing Corporation, nor its employees shall be liable for any direct or indirect, special, incidental or consequential damage arising from the use of its products, even if Measurement Computing Corporation has been notified in advance of the possibility of such damages.

Licensing Information

Each original copy of Universal Library is licensed for development use on one CPU at a time. It is theft to make copies of this program for simultaneous program development. If a customer creates an application using the Universal Library, they may distribute the necessary runtime files (Universal Library driver files) with their application royalty free. They may not distribute any files that give their customer the ability to develop applications using the Universal Library.

Trademark and Copyright Information

MEGA-FIFO, the CIO prefix to data acquisition board model numbers, the PCM prefix to data acquisition board model numbers, PCM-DAS08, PCM-DAC02, PCM-DAS16D/12, PCI-DAS6402/16, Universal Library, *InstaCal*, Measurement Computing Corporation, and the Measurement Computing logo are either trademarks or registered trademarks of Measurement Computing Corp.

SoftWIRE and the SoftWIRE logo are registered trademarks of SoftWIRE Technology.

Pentium is a trademark of Intel Corp.

PC is a trademark of International Business Machines Corp.

Microsoft, MS-DOS, Visual Basic, Visual C#, Visual Studio .NET, Windows, and Windows NT are trademarks of Microsoft Corp.

All other trademarks are the property of their respective owners.

Information furnished by Measurement Computing Corp. is believed to be accurate and reliable. However, no responsibility is assumed by Measurement Computing Corp. neither for its use; nor for any infringements of patents or other rights of third parties, which may result from its use. No license is granted by implication or otherwise under any patent or copyrights of Measurement Computing Corp.

All rights reserved. No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form by any means, electronic, mechanical, by photocopying, recording or otherwise without the prior written permission of Measurement Computing Corp.

Notice

Measurement Computing Corporation does not authorize any Measurement Computing Corporation product for use in life support systems and/or devices without the written approval of the CEO of Measurement Computing Corporation. Life support devices/systems are devices or systems which, a) are intended for surgical implantation into the body, or b) support or sustain life and whose failure to perform can be reasonably expected to result in injury. Measurement Computing *Corporation* products are not designed with the components required, and are not subject to the testing required to ensure a level of reliability suitable for the treatment and diagnosis of people.

Table of Contents

Table of MCC Hardware with UL Support.....	vi
1 Introducing the Universal Library	1
Universal Library overview	1
2 Installation and Configuration.....	3
Installing the Universal Library	3
The CB.CFG file and <i>InstaCal</i>	3
Installation – .NET support.....	3
Installation – SoftWIRE® support	3
SoftWIRE MCC DAQ Components for VS .NET	3
Installation – HP VEE support.....	4
Licensing information	4
Redistributing a custom UL application	4
Distributing <i>InstaCal</i> in addition to your custom UL application.....	4
Integrating <i>InstaCal</i> into your custom UL installation CD or disk.....	5
3 Getting Started	6
Example programs.....	6
4 Universal Library Description and Use.....	7
General UL language interface description	7
Function arguments.....	7
Constants	7
Options arguments.....	7
Error handling.....	8
16-bit values using a signed integer data type	8
Using the Universal Library in Windows.....	8
Real-time acquisition under Windows	9
Processor speed	9
Visual Basic for Windows	9
Microsoft Visual C++	10
Borland C /C++ for Windows.....	10
Delphi example programs	10
Using the Library with SoftWIRE®	10
SoftWIRE Mcc Daq Components for .NET.....	11
Using the Library with DOS BASIC	12
BASIC header file.....	12
Using the Library within the integrated BASIC environment.....	12
Using the Library with the BASIC command line compiler	12
Sample BASIC programs	12
Passing arguments to the Universal Library.....	12
Using the Library with VisualBasic® for DOS	14
Compiling stand-alone EXE files	14
Using the Library with C for DOS	14
C header file.....	14
Memory models.....	15
Large data arrays	15
Compiling the sample C programs	15
Using the Library with HP VEE	15
New HP VEE functions.....	16
Installation note	16
Using VEE 3.2 or later.....	16
5 Universal Library for .NET Description & Use	17
Configuring a UL for .NET project.....	17
General UL for .NET language interface description.....	18
MccBoard class.....	18
ErrorInfo class	19

MccService class	20
GlobalConfig class	20
MccDaq enumerations	20
Parameter data types	22
Differences between the UL and UL for .NET	22
Board number	22
MCC classes	23
Methods	23
Enumerated types	23
Error handling	24
Service methods	24
Configuration methods	24
6 How to Use the "Streamer" File Functions	25
File functions overview	25
Hard disk vs. RAM disk files	25
Maximum sampling speed	25
How to determine the maximum sampling speed	26
Speeding up disk files (defragmenting)	26
RAM disks	27
Installing a RAM disk	27
Using the RAM disk	27
7 Analog Input Boards	28
Introduction	28
Trigger support	28
Digital Trigger	28
Analog Trigger	28
Sampling rate using SINGLEIO	29
PCI-DAS6000 Series	30
PCI-DAS4020 Series	36
PCI-DAS64/Mx/16 Series	41
PCI- and CIO-DAS6402 and DAS3202 Series	44
PCI-DAS1602, PCI-DAS1200 & PCI-DAS1000 Series	48
PCIM-DAS1602 and PCIM-DAS16JR Series	52
CIO-DAS800 Series	55
CIO-, PCI-, and PC104-DAS08 Series	57
CIO-DAS08/Jr and CIO-DAS08/Jr/16 Series	60
PCM-DAS08	62
Determining the maximum sampling rate in DOS	63
PPIO-AI08	64
CIO- and PC104-DAS16	65
PCM- and PC-CARD-DAS16 Series	69
CIO-DAS1400 and CIO-DAS1600 Series	72
CIO-DAS48/PGA	75
DAS-TC Series	76
CIO-DAS-TEMP	77
USB-TEMP, USB-TC	78
miniLAB 1008	80
USB-1208 Series	83
USB-1608 Series	88
USB-1616 Series	91
8 Analog Output Boards	94
Introduction	94
DAC04 HS Series	95
DAC Series (Excluding HS Series)	96
PCI-DAC6700 Series	97
PCM- and PC-CARD- DAC Series	98
PCIM- and CIO- DDA06 Series	99
PCI- and CPCI- DDA Series	100
cSBX-DDA04	101

9	Digital Input/Output Boards.....	102
	Introduction	102
	Basic signed integers	102
	AC5 Series	103
	DIO Series	104
	DIO24/CTR3 and D24/CTR3 Series	105
	PCI-DIO48/CTR15	106
	PDISO8 and PDISO16 Series.....	107
	Establishing and requesting control of an E-PDISO16	107
	Sending a request for control of an E-PDISO16.....	107
	Receiving a request for control of an E-PDISO16	108
	Receiving a message	108
	CIO-PDMA16 and CIO-PDMA32	109
	USB-1024 and USB-DIO24 Series	110
	USB-DIO96 Series (formerly USB-1096 Series).....	111
	USB-SSR Series.....	112
	Switch & Sense 8/8.....	113
10	Digital Input Boards	114
	Introduction	114
	CIO- and PC104- DI Series.....	115
	CIO-DISO48.....	116
11	Digital Output Boards	117
	Introduction	117
	CIO-RELAY Series	118
	USB-ERB Series.....	119
	CIO- and PC104-DO Series.....	120
12	Counter Boards	121
	Introduction	121
	Basic signed integers	121
	Counter chip variables.....	121
	CTR Series	122
	INT32 Series.....	124
	PPIO-CTR06.....	125
	QUAD Series	126
13	MetraBus Boards.....	128
	Introduction	128
	MDB64 Series.....	129
	MIO and MII Digital I/O	130
	MEM Series Relay	131
	MSSR-24 SSR	132
14	Expansion Boards.....	133
	Introduction	133
	CIO-EXP Series	134
	MEGA-FIFO	135
15	Other Hardware	136
	Introduction	136
	COM422 Series	137
	COM485 Series	137
	Demo-Board.....	138
	Appendix – MCC Device IDs.....	140

Table of MCC Hardware with UL Support

CPCI boards

CPCI-DDA02/12.....	100
CPCI-DDA02/16.....	100
CPCI-DDA04/12.....	100
CPCI-DDA04/16.....	100
CPCI-DDA08/12.....	100
CPCI-DDA08/16.....	100
CPCI-DIO24H.....	104
CPCI-DIO48H.....	104
CPCI-DIO96H.....	104

Ethernet boards

E-PDISO16.....	107-8
----------------	-------

Expansion boards

CIO-EXP16.....	134
CIO-EXP32.....	134
CIO-EXP-BRIDGE.....	134
CIO-EXP-GP.....	134
CIO-EXP-RTD.....	134

ISA boards

CIO-COM422.....	137
CIO-COM485.....	137
CIO-CTR05.....	121-23
CIO-CTR10.....	121-23
CIO-CTR10HD.....	121-23
CIO-CTR20HD.....	121-23
CIO-DAC02.....	96
CIO-DAC02/16.....	96
CIO-DAC04/12-HS.....	95
CIO-DAC04/16-HS.....	95
CIO-DAC08.....	96
CIO-DAC08/16.....	96
CIO-DAC08-I.....	96
CIO-DAC16.....	96
CIO-DAC16/16.....	96
CIO-DAC16-I.....	96
CIO-DAS08.....	57-59
CIO-DAS08/Jr.....	60
CIO-DAS08/Jr/16.....	60
CIO-DAS08/Jr/16-AO.....	60
CIO-DAS08/Jr-AO.....	60
CIO-DAS1401/12.....	72-74
CIO-DAS1402/12.....	72-74
CIO-DAS1402/16.....	72-74
CIO-DAS16.....	65-68
CIO-DAS16/330.....	65-68
CIO-DAS16/330i.....	65-68
CIO-DAS16/F.....	65-68
CIO-DAS16/Jr.....	65-68
CIO-DAS16/Jr/16.....	65-68
CIO-DAS16/M1.....	65-68
CIO-DAS16/M1/16.....	65-68
CIO-DAS1601/12.....	72-74
CIO-DAS1602/12.....	72-74
CIO-DAS1602/16.....	72-74
CIO-DAS48/PGA.....	75
CIO-DAS48-I.....	75
CIO-DAS6402/12.....	44-47

CIO-DAS6402/16.....	44-47
CIO-DAS800.....	55-56
CIO-DAS801.....	55-56
CIO-DAS802.....	55-56
CIO-DAS802/16.....	55-56
CIO-DAS-TC.....	76
CIO-DAS-TEMP.....	77-79
CIO-DDA06.....	99
CIO-DDA06/16.....	99
CIO-DDA06/JR.....	99
CIO-DDA06/JR/16.....	99
CIO-DI192.....	115
CIO-DI48.....	115
CIO-DI96.....	115
CIO-DIO192.....	104
CIO-DIO24.....	104
CIO-DIO24/CTR3.....	105
CIO-DIO24H.....	104
CIO-DIO48.....	104
CIO-DIO48H.....	104
CIO-DIO96.....	104
CIO-DISO48.....	116
CIO-DO192H.....	119-20
CIO-DO24DD.....	119-20
CIO-DO48DD.....	119-20
CIO-DO48H.....	119-20
CIO-DO96H.....	119-20
CIO-DUAL422.....	137
CIO-DUAL-AC5.....	103
CIO-INT32.....	124
CIO-PDISO16.....	107-8
CIO-PDISO8.....	107-8
CIO-PDMA16.....	109
CIO-PDMA32.....	109
CIO-QUAD02.....	126-27
CIO-QUAD04.....	126-27
CIO-RELAY08.....	118
CIO-RELAY16.....	118
CIO-RELAY16/M.....	118
CIO-RELAY24.....	118
CIO-RELAY32.....	118
DEMO-BOARD.....	138-39
ISA-MDB64.....	129

Memory boards

MEGA-FIFO.....	135
----------------	-----

MetraBus boards

MEM-32.....	131
MEM-8.....	131
MSSR-24.....	132

PC104 boards

PC104-AC5.....	103
PC104-CTR10HD.....	121-23
PC104-DAC06.....	96
PC104-DAS08.....	57-59
PC104-DAS16/Jr/12.....	65-68
PC104-DAS16/Jr/16.....	65-68
PC104-DI48.....	115

PC104-DIO48.....	104
PC104-DO48H.....	119-20
PC104-MDB64.....	129
PC104-PDISO8.....	107-8

PCI boards

cSBX-DDA04.....	101
PCI-CTR05.....	121-23
PCI-CTR10.....	121-23
PCI-CTR20HD.....	121-23
PCI-DAC6702.....	97
PCI-DAC6703.....	97
PCI-DAS08.....	57-59
PCI-DAS1000.....	48-51
PCI-DAS1001.....	48-51
PCI-DAS1002.....	48-51
PCI-DAS1200.....	48-51
PCI-DAS1200/JR.....	48-51
PCI-DAS1602/12.....	48-51
PCI-DAS1602/16.....	48-51
PCI-DAS3202/16.....	44-47
PCI-DAS4020/12.....	36-40
PCI-DAS6013.....	30-35
PCI-DAS6014.....	30-35
PCI-DAS6023.....	30-35
PCI-DAS6025.....	30-35
PCI-DAS6030.....	30-35
PCI-DAS6031.....	30-35
PCI-DAS6032.....	30-35
PCI-DAS6033.....	30-35
PCI-DAS6034.....	30-35
PCI-DAS6035.....	30-35
PCI-DAS6036.....	30-35
PCI-DAS6040.....	30-35
PCI-DAS6052.....	30-35
PCI-DAS6070.....	30-35
PCI-DAS6071.....	30-35
PCI-DAS64/M1/16.....	41-43
PCI-DAS64/M2/16.....	41-43
PCI-DAS64/M3/16.....	41-43
PCI-DAS6402/12.....	44-47
PCI-DAS6402/16.....	44-47
PCI-DAS-TC.....	76
PCI-DDA02/12.....	100
PCI-DDA02/16.....	100
PCI-DDA04/12.....	100
PCI-DDA04/16.....	100
PCI-DDA08/12.....	100
PCI-DDA08/16.....	100
PCI-DIO24.....	104
PCI-DIO24/LP.....	104
PCI-DIO24/S.....	104
PCI-DIO24H.....	104
PCI-DIO24H/CTR3.....	105
PCI-DIO48H.....	104
PCI-DIO48H/CTR15.....	106-7
PCI-DIO96.....	104
PCI-DIO96H.....	104

PCI-DUAL-AC5.....	103	PCM-DAS16D/12	69–71	USB-1024LS	110
PCI-INT32	124	PCM-DAS16D/12AO..	69–71	USB-1096HFS111, See USB-	
PCIM-DAS1602/16	52–54	PCM-DAS16D/16	69–71	DIO96H	
PCIM-DAS16JR/16.....	52–54	PCM-DAS16S/12	69–71	USB-1208FS.....	83–87
PCI-MDB64	129	PCM-DAS16S/16	69–71	USB-1208LS	83–87
PCIM-DDA06/16	99	PCM-DAS16S/330	69–71	USB-1608FS.....	88–90
PCI-PDISO16	107–8	PCM-QUAD02.....	126–27	USB-1616FS.....	91–93
PCI-PDISO8	107–8	PPIO boards		USB-DIO24/37	110
PCI-QUAD04	126–27	PPIO-AI08	64	USB-DIO24/37	110
PCI-QUAD-AC5	103	PPIO-CTR06	125	USB-DIO96H	111
PCMCIA cards		PPIO-DIO24	104	USB-DIO96H/50	111
PC-CARD-D24/CTR3	105	USB devices		USB-ERB08	119
PC-CARD-DAS16/12..	69–71	miniLAB 1008.....	80–82	USB-ERB24	119
PC-CARD-DAS16/12AO	69–71	PMD-1024HLS.....	110	USB-PDISO8.....	107–8
PC-CARD-DAS16/16..	69–71	PMD-1024LS.....	110	USB-PDISO8/40	107–8
PC-CARD-DAS16/16AO	69–71	PMD-1208FS.....	83–87	USB-SSR08	112
PC-CARD-DAS16/330	69–71	PMD-1208LS.....	83–87	USB-SSR24	112
PC-CARD-DIO48	104	PMD-1608FS.....	88–90	USB-TC.....	79
PCM-D24/CTR3.....	105	Switch & Sense 8/8.....	113	USB-TEMP	79
PCM-DAS08	62–63	USB-1024HLS.....	110		

Introducing the Universal Library

Congratulations and thank you for selecting the Universal Library (UL). We believe it is the most comprehensive and easiest-to-use data acquisition software interface available anywhere. As easy as Universal Library is to use, significant documentation and explanation is still required to help new users get going, and to allow previous users to take advantage of all the package's powerful features.

The fast changing nature of the software industry makes it very difficult to provide a totally up to date user guide in written form. Adding to this complexity are the new features and functions that are constantly being added to the library. To provide the most complete information possible and at the same time keep the information current, the Universal Library documentation is offered in four parts:

- **Universal Library User's Guide:** The User's Guide provides a general description of the UL, offers an overview of the various features and functions, and discusses and how they can be used in different operating systems and languages. The User's Guide also provides board-specific information relating to the features and functions that are included with the Universal Library.
- **Universal Library Function Reference:** The Function Reference contains detailed information about the Universal Library functions, usage, and options. This document is available on our web site at www.mccdaq.com/PDFmanuals/sm-ul-functions.pdf.
- **Example programs:** The examples programs demonstrate the use of many of the most frequently used functions, and are valuable learning tools. They are written for many popular languages. Each example program is fully functional, and provides an ideal starting place for your own programming effort. You can cut and paste from the example programs to create your own programs. It's easier to cut-and-paste pieces from a known, working program than to start writing everything from scratch.
- **Readme files:** The best way to get the latest, most up to date information is through Readme files. We incorporate this information into our documentation as quickly as we can, but for the latest, greatest information, read the Readme file.

Universal Library overview

The Universal Library is the software that you need to write your own programs for use with any of Measurement Computing's data acquisition and control boards. The library is universal in three ways:

Universal across boards: The library contains high level functions for all of the common operations for all boards. Each of the boards has different hardware but the Universal Library hides these differences from your program. So, for example, a program written for use with one A/D board will work "as is" with a different A/D board.

Universal across languages: The Universal Library provides the identical set of functions and arguments for each supported language. If you switch languages, you will not have to learn a new library, with new syntax, and different features.

If you are programming for the .NET framework, you will find that the Universal Library for .NET has the same "look and feel" as the Universal Library for 32-bit windows applications, and is just as easy to program.

If you are a SoftWIRE[®] user, and are using data acquisition controls, specific support components of applicable UL functions are required and used by SoftWIRE. Refer to "[Using the Library with SoftWIRE](#)" on page 10 for more information.

Languages supported by the Universal Library, at the time this manual was published, are listed in the following table. Both 16- and 32-bit versions are supported where applicable.

Microsoft Windows Languages	Borland Windows Languages	
Visual Basic	Borland C++	
Visual C/C++	Borland C++ Builder	
Quick C for Windows	Delphi	
Microsoft C		
Microsoft DOS Languages	Borland DOS Languages	Hewlett Packard (Now Agilent)
QuickBasic 4.5	Turbo C	HP VEE
Professional Basic 7.0	Turbo C++	
Visual Basic for DOS	Borland C++	
Quick C		
.NET Languages		
VB .NET		
C# .NET		

Universal across platforms: The Universal Library provides the same sets of functions for DOS, Windows 3.x and 32-bit Windows (95/98/ME/NT/2000/XP). Additionally, these functions have been extended to support the .NET environment.


Installation and Configuration

Installing the Universal Library


To install the Universal Library, follow the steps below

1. Place the Universal Library CD in your CD drive.

The **Measurement Computing CD** dialog opens.

If the dialog does not open, use Windows Explorer to run  SETUP.EXE on the root of the CD.

2. From the **Measurement Computing CD** dialog, click on the **Install InstaCal and the Universal Library** button.



3. Follow the installation instructions as prompted.
4. Leave the Universal Library CD in your CD drive, and restart your computer.

InstaCal is a powerful installation, test, and calibration software package that is installed as part of the Universal Library package. Refer to the *Quick Start Guide* for examples of using *InstaCal* with MCC's DEMO-BOARD

Using SoftWIRE data acquisition controls with UL:

If you are going to be using SoftWIRE for data acquisition, you may need to load the latest version of the Universal Library. Refer to "[Installation - SoftWIRE® support](#)" below for installation instructions.

The CB.CFG file and *InstaCal*

All board-specific information, including current installed options, are stored in the file CB.CFG which is read by Universal Library. *InstaCal* creates and/or modifies this file when board configuration information is added or updated. The Universal Library will not function without the CB.CFG file.

For this reason, you must use *InstaCal* to modify all board setups and configurations as well as to install or remove boards from your system.

Installation – .NET support

Universal Library support for .NET requires that the Microsoft .NET framework already be installed on the system before you install the Universal Library.

Installation – SoftWIRE® support

SoftWIRE MCC DAQ Components for VS .NET

SoftWIRE Graphical Programming for VS .NET is one of the applications installed from the Measurement Computing DAQ Software CD that ships with all MCC hardware. SoftWIRE includes a set of MCC DAQ components that perform many of the UL functions, and can be designed in a graphical programming environment.

For instructions on installing SoftWIRE, refer to the *Quick Start Guide* that came with your hardware (available on our web site at www.mccdaq.com/PDFmanuals/DAQ-Software-Quick-Start.pdf).

Installation – HP VEE support

Before installing HP VEE support, install the Universal Library and *InstaCal*.

After you install the HP VEE application and drivers, run *InstaCal* and configure the driver. *InstaCal* is an installation, calibration, and test program that creates a required configuration file describing the specifics of the hardware installed.

The changes made to your system when installing HP VEE Support are identical to the changes made when installing the Universal Library, except for the following:

- The menu bar program VEE.MNU (or CBI.MNN, depending on the version) is written to the VEE directory.

Handling multiple custom menu bars (VEE.MNU)

If you use a custom VEE.MNU, such as the one shipped with DT-VEE, the install program may overwrite it. Contact MCC's technical support for information on handling multiple custom menu bars.

- Example programs are added to the VEE installation directory. The Universal Library sample VEE programs have a .VEE extension. For a list of sample programs, refer to the "Example Programs" chart in Chapter 1, "Functional Overview," of the *Universal Library Function Reference*, available on our web site at www.mccdaq.com/PDFmanuals/sm-ul-functions.pdf.

Licensing information

Each original copy of Universal Library is licensed for development use on one CPU at a time. It is theft to make copies of this program for simultaneous program development.

Redistributing a custom UL application

The easiest way to distribute an application written with the Universal Library is to include a copy of Measurement Computing's *InstaCal* installation package with the application. Instruct the end user to install *InstaCal* before installing the application.

Some developers may want to integrate the installation of the required Universal Library drivers into the custom application's installation. This should only be attempted by developers experienced in installation development.

Following is an overview of the two methods.

Distributing *InstaCal* in addition to your custom UL application

If you create an application using the Universal Library, you may distribute the necessary runtime files (Universal Library driver files) with the application royalty free. These files can be installed from Measurement Computing's *InstaCal* installation package. To distribute a custom UL application, provide the end user with two CDs or disks:

- One CD or disk that contains Measurement Computing's *InstaCal* application. *InstaCal* must be installed before the custom UL application.
- One CD or disk that contains the setup program for their custom VB or C++ application.

You may not distribute any files that give the end user the ability to develop applications using the Universal Library.

Integrating *InstaCal* into your custom UL installation CD or disk

For developers who wish to distribute their application on one CD, refer to the *Universal Library Redistribution Guide*. This document contains procedures to merge the setup programs for both *InstaCal* and the custom UL application into one setup program that you can distribute on one CD or disk. The merging process is complicated — only experienced programmers should attempt to do this.

When you install the software, the *Universal Library Redistribution Guide* (ULRedist.pdf) is copied to the default installation directory "C:\MCC\Documents" on your local drive.

Getting Started

The Universal Library is callable from many languages and environments, including Visual Basic®, Visual C++, Borland C++ Builder, and Delphi. A list of the languages currently supported by the Universal Library is provided on page 1. Additionally, the UL is now callable from any language supported by the .NET framework. This chapter describes how to use the library from each of the languages, as well as several 16-bit environments. The first section of the chapter describes details of the library that apply to all languages. The following sections describe the differences for each language.

Before starting your application, you should perform the following:

- Set up and test your boards with *InstaCal*. The Universal Library will not function until *InstaCal* has created a configuration file (CB.CFG).
- Run the example programs for the language you program in.

Example programs

Example programs are installed into the Sample32 and Sample16 installation subdirectory for each programming language mentioned above. Note that 16-bit sample programs are only installed when you install the 16-bit library. The names of the installation folders are:

- C
- CWIN
- DELPHI
- VBWIN

All .NET applications run in the 32-bit Windows environment. A complete set of UL for .NET example programs are included in the C# and VB.NET folders of the Universal Library installation directory. Each program illustrates the use of Universal Library functions from within a .NET program.

For a complete list of example programs, refer to the UL Function Reference

The *Universal Library Function Reference* contains tables that list the UL and UL for .NET example programs. Each table contains the name of the sample program and the functions that the program demonstrates. This document is available on our web site at www.mccdaq.com/PDFmanuals/sm-ul-functions.pdf.

Universal Library Description and Use

The Universal Library consists of a set of functions that are callable from your program. These functions are grouped according to their purpose. All of the groups except for *Miscellaneous* are based on which type of device they are used with.

Important - Read the UL documentation, Readme file, and run the example programs

In order to understand the functions, please read the board-specific information section contained in this manual and in the Readme files supplied on the Universal Library disk. We also urge you to examine and run one or more of the example programs supplied prior to attempting any programming of your own. Following this advice can save you hours of frustration and wasted time.

General UL language interface description

The interface to all languages is a set of function calls and a set of constants. The list of function calls and constants are identical for each language. All of the functions and constants are defined in a "header" file for each language. Refer to the sections below, and especially to the example programs for each language. This manual is brief with respect to details of language use and syntax. For more detailed information, review the example programs. Example programs for each language are located in the installation directory.

Function arguments

Each library function takes a list of arguments and most return an error code. Some functions also return data via their arguments. For example, one of the arguments to `cbAIIn()` is the name of a variable in which the analog input value will be stored. All function arguments that return data are listed in the "Returns" section of the function description.

Constants

Many functions take arguments that must be set to one of a small number of choices. These choices are all given symbolic constant names. For example, `cbTIn()` takes an argument called `Scale` that must be set to `CELSIUS`, `FAHRENHEIT` or `KELVIN`. These constant names are defined, and are assigned a value in the "header" file for each language. Although it is possible to use the numbers rather than the symbolic constant names, we strongly recommend that you use the names. Using constant names make your programs more readable and more compatible with future versions of the library. The numbers may change in future versions, but the symbolic names always remain the same.

Options arguments

Some library functions have an argument called `Options`. The `Options` argument is used to turn on and off various optional features associated with the function. If you set `Options = 0`, the function sets all of these options to the default value, or `OFF`.

Some options can have an alternative value, such as `DTCCONNECT` and `NODTCCONNECT`. If an option can have more than one value, one of the values is designated as the default. Individual options can be turned on by adding them to the `Options` argument. For example:

- `Options = BACKGROUND` will turn on the "background execution" feature.
- `Options = BACKGROUND+CONTINUOUS` will select both the "background execution" and the "continuous execution" feature.

Error handling

Most library functions return an error code. If no errors occurred during a library call, 0 (or NOERRORS) is returned as the error code. Otherwise, it is set to one of the codes listed in the *Universal Library Function Reference* "Error Codes" chapter. This document is available on our web site at www.mccdaq.com/PDFmanuals/sm-ul-functions.pdf

If a non-zero error code is returned, you can use `cbGetErrMsg()` to convert the error code to a specific error message. As an alternative to checking the error code after each function call, you can turn on the library's internal error handling with `cbErrHandling()`.

16-bit values using a signed integer data type

When using functions that require 16-bit values, the data is normally in the range of 0 to 65535. However, some programming languages, such as BASIC and Visual Basic only provide signed data types. When using signed integers, reading values above (32767) can be confusing.

The number (32767) in decimal is equivalent to (0111 1111 1111 1111) binary. The next increment (1000 0000 0000 0000) binary has a decimal value of (-32768). The maximum value (1111 1111 1111 1111) binary translates to (-1) decimal. Keep this in mind if you are using Basic, Visual Basic (up to version 6) or other languages that don't support unsigned integers.

There is additional information on this topic in the *Universal Library Function Reference*. This document is available on our web site at www.mccdaq.com/PDFmanuals/sm-ul-functions.pdf. Also, refer to the documentation supplied with your language compiler.

Using the Universal Library in Windows

All 32-bit applications (including console applications) access the 32-bit Windows Dynamic Link Library (DLL) version of the Universal Library (CBW32.DLL). Example programs are provided for MS Visual C++, MS Visual Basic, Borland C++, and Borland Delphi in the Sample32 subdirectories of the installation directory. These sample programs illustrate the use of CBW32.DLL.

For 16-bit Windows applications, or Windows applications running in Windows 3.x, the 16-bit Windows DLL version of the Universal Library (CBW.DLL) should be used. Example programs are provided for Visual Basic and both Borland and MS C in the Sample16 subdirectories of the installation directory. These programs illustrate the use of CBW.DLL.

Due to the differences in memory management among DOS, Windows 3.x, and 32-bit Windows (95/98/ME/NT/2000/XP), the scan functions have slightly different argument lists. In DOS libraries, all scan functions take a pointer to a data array as one of their arguments. In Windows 3.x, these functions take a handle to a Windows Global Memory buffer instead of a pointer to an array. In the 32-bit Windows version, these functions take a pointer (a 32-bit virtual address) or a handle returned from `cbWinBufAlloc()`.

The affected functions are:

- `cbAInScan()`
- `cbAOutScan()`
- `cbAPretrig()`
- `cbDInScan()`
- `cbDOutScan()`
- `cbStoreOnInt()`

The Windows library contains four functions for managing these Windows global memory buffers:

- `cbWinBufAlloc()`
- `cbWinBufFree()`
- `cbWinArrayToBuf()`
- `cbWinBufToArray()`

Real-time acquisition under Windows

Real-time acquisition is available for Windows. To operate at full speed in Windows, the A/D board must have an onboard FIFO buffer. All of our advanced designs have FIFO buffers, including our PCI-DAS boards (except for the PCI-DAS08), and many of our CIO- boards, such as the CIO-DAS80x, CIO-DAS160x, CIO-DAS140x, and CIO-DAS16/330x. All of these data acquisition boards will operate at full speed in Windows.

Applying software calibration factors in real time on a per-sample basis eats up machine cycles. If your CPU is slow, or if processing time is at a premium, withhold calibration until after the acquisition run is complete. Turning off real-time software calibration saves CPU time during a high speed acquisition run.

Processor speed

Processor speed remains a factor for DMA transfers and for real-time software calibration. Processors of less than a 150 megahertz (MHz) Pentium class may impose speed limits below the capability of the board (refer to specific board information.)

If your processor is less than a 150 MHz Pentium and you need an acquisition speed in excess of 200 kilohertz (kHz), use the `NOCALIBRATEDATA` option to turn off real-time software calibration and save CPU time. After the acquisition is run, calibrate the data with `cbACalibrateData()`.

Visual Basic for Windows

To use the Universal Library with Visual Basic, include the Universal Library declaration file `CBW.BAS` in your program. Include the file as a module in the project, or include it by reference inside those Forms which call into the Universal Library. Once the declarations for the Universal Library have been added to your project, call the library functions from any Form's event handlers.

When using the 32-bit version of Visual Basic, `CBW.BAS` references `CBW32.DLL` to call Universal Library functions. This is accomplished with conditional compile statements. When using 16-bit versions of the Visual Basic (such as versions 3.0 or older), these conditional compile statements must be deleted.

For Visual Basic 6.0 and older, Windows memory buffers cannot be mapped onto arrays. As a consequence, the `cbWinArrayToBuf()` and `cbWinBufToArray()` functions must be used to copy data between arrays and Windows buffers.

Example:

```
Count = 100
MemHandle = cbWinBufAlloc (Count)
cbAInScan (.....,MemHandle,...)
cbWinBufToArray (MemHandle, dataArray(0), 0, Count)
For i = 0 To Count
    Print dataArray(i)
Next i
cbWinBufFree (MemHandle)
```

Visual Basic example programs

A complete set of Visual Basic example programs is included in the VBWIN folder of the Universal Library installation directory. Each program illustrates the use of a Universal Library function from within a Visual Basic program. The .FRM files contain the programs, and the corresponding .VBP or .MAK files are the project files used to build the programs for Visual Basic.

Microsoft Visual C++

To use the Universal Library with MS Visual C++, include the Universal Library header file CBW.H in your C/C++ program and add the library file CBW32.LIB to your library modules for linking to the CBW32.DLL. When using a 16-bit version of MS Visual C++, replace the library file CBW32.LIB with CBW.LIB.

Microsoft Visual C++ example programs

The CWIN folder of the Universal Library installation directory contains three sample programs - wincai01, wincai02 and wincai03. Each program is an example of a simple C program that calls a few of the Universal Library functions from a Windows application. These programs contain directives for building 16- OR 32- bit applications. Use the .MAK project files to build a 16-bit application, and the .DSP project files to build a 32-bit application.

The non-Windows C examples in the C folder of the installation directory provide a more complete set of examples. You can compile these programs as 32-bit console applications for Windows by using the MAKEMC32.BAT file.

Borland C /C++ for Windows

For 32-bit Borland(or Inprise) C/C++ compilers, include the Universal Library header file CBW.H in your program and link with the import library file CBW32BC.LIB.

When using the 16-bit version of Borland C/C++, use a tool called IMPLIB to generate an OMF-style import library that your application can link with. For 16-bit users, IMPLIB accepts a DLL (CBW.DLL) as input and creates an OMF-style import library (BCBW.LIB). You can run IMPLIB on CBW.DLL to emit a 16-bit OMF-style import library (BCBW.LIB).

Borland C/C++ example programs

The non-Windows C examples provide an extensive set of examples. These can be compiled as 32-bit console applications using the MAKEBC32.BAT file.

Delphi example programs

A complete set of Delphi example programs is included in the DELPHI folder of the Universal Library installation directory. Each program illustrates the use of one Universal Library function from within a Delphi program. The .PAS files contain the programs. The corresponding .DPR file is the Project file used to build the program in a 16 bit or 32 bit Delphi environment.

In 16-bit Delphi environments, use the `cbw.d11` header. In 32-bit Delphi environments use the `cbw32.d11` header. Conditionals within the example programs determine which of the DLLs is used. Where integers are passed by reference to a Universal Library function, use the `SmallInt` data type in 32-bit environments. The relevant functions are defined this way in the 32-bit header, so if you try to pass an Integer data type you will get a compiler error.

Using the Library with SoftWIRE®

To understand how SoftWIRE interacts with DAQ I/O boards, study both this manual and the example programs supplied with SoftWIRE. It is very important that you read the entire manual for information that

relates to usability and performance. Remember, SoftWIRE uses the Universal Library as the interface to the I/O boards. Library performance factors are reflected in SoftWIRE controls that use the library.

Each SoftWIRE component is implemented as a graphic block. You can access all arguments and properties on the screen. You connect constants, variables, or objects by dragging a “wire” from “pin-to-pin.” In large projects, the ability to easily supply an argument with a control variable that acquires its value elsewhere is especially powerful. See the SoftWIRE Help topic for each component for detailed information on how to do this.

SoftWIRE Mcc Daq Components for .NET

SoftWIRE is a simple and efficient way to build application programs. Read the Help file, start with simple examples, and then begin working up your own projects. Please call us with any suggestions or questions you may have. The following table lists the data acquisition components in SoftWIRE that require the UL software support components.

SoftWIRE component	Explanation
AI Read	Calls the UL's <code>AIn()</code> method to read the value, or state, of a single analog input channel on an A/D board, and output the value.
AI Scan	Calls the UL's <code>AInScan()</code> method to scan a range of analog input channels and output the data in a one- or two-dimensional array of data.
AI Trigger	Calls the UL's <code>ATrig()</code> method to continuously read the value of an analog input channel, compare the value to a specified trigger value, and output the first value that meets the trigger criteria.
AO Scan	Calls the UL's <code>AOutScan()</code> method to scan a range of analog output channels and values from an input array to those channels.
AO Update	Calls the UL's <code>AOut()</code> method to set the value of an analog output channel.
Configure 8254 Counter	Calls the UL's <code>C8254Config()</code> method to configure an 8254 counter.
Configure 9513 Counter	Calls the UL's <code>C9513Config()</code> method to configure a 9513 counter
DI Read Byte	Calls the UL's <code>DIn()</code> method to read a digital byte value from a specified board and digital input port.
DI Read Bit	Calls the UL's <code>DBitIn()</code> method to read a digital bit value from a digital I/O port.
DO Write Byte	Calls the UL's <code>DBitOut()</code> method to set the value, or state, of a single bit on a digital I/O port.
DO Write Bit	Calls the UL's <code>DOut()</code> method to set the value, or state, of a single port on a digital I/O board.
Initialize 9513 Counter	Calls the UL's <code>C9513Init()</code> method to initialize a 9513 counter
Load Counter	Calls the UL's <code>CLoad32()</code> method to load a count value to a specified counter
Read Counter	Calls the UL's <code>CIn32()</code> method to read the current count from a counter and then output the count from one of its data output pins
Read 9513 Frequency	Calls the UL's <code>CFreqIn()</code> method to read the frequency read by a 9513 counter and then output it from one of its data output pins
TEMP In	Calls the UL's <code>TIn()</code> method to read a value from a single temperature input channel and output the value in degrees
TEMP In Scan	Calls the UL's <code>TInScan()</code> method to scan a range of temperature input channels and output a two-dimensional array in degrees

Using the Library with DOS BASIC

Each of the supported versions of BASIC consists of two distinct systems. Programs can be loaded into the BASIC editor and run from within the integrated BASIC environment. Programs can also be compiled by a command line compiler into stand-alone executable programs that can be run on their own without the help of the integrated BASIC environment. The Universal Library provides the tools for both methods.

BASIC header file

Every BASIC program that uses the Universal Library must have a line which includes the BASIC Universal Library header file - CB.BI. The following line should appear near the start of every program, before the first library call is made.

```
'$INCLUDE: 'CB.BI'
```

Using the Library within the integrated BASIC environment

When you start up BASIC, load the "quick library" version of Universal Library.

For Quick BASIC, type:

```
qb /1 cbqb
```

For Professional BASIC, type:

```
qbx /1 cbpb
```

For VisualBasic for DOS, type:

```
vbdos /1 cbvb
```

Using the Library with the BASIC command line compiler

To build stand-alone executable files with the command line compiler, you must link your compiled BASIC program with the stand-alone version of the Universal Library. To do this, you must supply the linker with the library name. The names of the .lib files are:

- QuickBasic: CBQB.LIB
- Professional Basic: CBPB.LIB
- VisualBasic for DOS: CBVB.LIB

Sample BASIC programs

The sample BASIC programs demonstrate how to call each function in the Universal Library. These programs can be run from within the integrated BASIC environment. They can also be compiled using the command line compiler with the batch file supplied. The names of the batch files are:

- QuickBasic: MAKEQB.BAT
- Professional BASIC: MAKEPB.BAT
- VisualBasic for DOS: MAKEVB.BAT

Passing arguments to the Universal Library

All functions in the library require that arguments be passed to them. The file CB.BI contains the definition of all the argument types that are passed. In general, there are two classes of arguments: inputs and outputs.

Input arguments

Input arguments to a library function are listed in the CB.BI file definition as BYVAL. You can pass these arguments as either a variable or a constant. For example, both of these versions are acceptable:

```
BoardNum% = 0
cbStopBackground (BoardNum%)
```

or

```
cbStopBackground (0)
```

Output arguments

Output arguments pass information back to the calling function. For example, `cbAIn()` returns the value from an A/D to the `DataValue%` argument. Others arguments are both inputs and outputs. For example, the `Rate&` argument specifies the requested sampling rate for `cbAInScan()` (Input).

The actual sampling rate can vary from the requested sampling rate. `cbAInScan()` returns the actual rate to the `Rate&` argument (output). Output and input/output arguments are defined in the CB.BI function definitions as SEG. All SEG arguments can only be passed via a variable.

The following example is correct:

```
Count& = 1000
Rate& = 15000
cbAInScan (0, 0, 1, Count&, Rate&, BIP5VOLTS, dataArray(0), 0)
```

The following example is NOT correct:

```
cbAInScan (0, 0, 1, 1000, 15000, BIP5VOLTS, dataArray(0), 0)
```

DataArray argument with multiple channels

Some functions have a `DataArray` argument. `DataArray` either receives the data from an input function, such as `cbAInScan()`, or contains the data to send to an output function, such as `cbAOutScan()`.

`DataArray` must be dimensioned to be large enough to contain all of the data. The array can either be dimensioned with one-dimension or two dimensions. When sampling more than one channel, it is often more straightforward to use a two-dimensional array. The code below shows both methods:

```
DIM DataBuffer (1999)          'One-dimensional array. 0 to 1,999 (2,000)
elements.
```

or

```
DIM DataBuffer (1, 999)       'Two-dimensional array. 0 & 1 with 0-999
(1,000) elements each.
```

```
LowChan% = 2
```

```
HighChan% = 3
```

```
Count& = 2000
```

```
Rate& = 1000
```

```
cbAInScan (0, LowChan%, HighChan%, Count&, Rate&, BIP5VOLTS, DataBuffer(0), 0)
```

or

```
cbAInScan (0, LowChan%, HighChan%, Count&, Rate&, BIP5VOLTS, DataBuffer(0,
0), 0)
```

The advantage of using the two-dimensional array is that you can directly address the data in the array by channel. Therefore, in the example above, `DataBuffer (0, 99)` addresses the 100th sample for channel 2 (channel 2 was the first element in the array; `LowChan%`).

When running UL for .NET, order Visual Basic arrays as `DataArray (sample, chan)`. The above example would be written in UL for .NET as `DataBuffer (99, 0)`.

String arguments

`cbGetErrMsg()` requires that a string variable be passed as an argument. This string variable must have been previously allocated to be large enough to hold the longest error message. To do this, use Quick BASIC's `space$` function as it is done in the example program.

```
ErrStr$ = space$ (ERRSTRLEN)
```

Integer arguments

BASIC does not support unsigned integers (0 to 65,535). Values for the integer data type range from -32,768 to 32,767. When using functions that require unsigned integers, the data must be converted. (Refer to "[16-bit values using a signed integer data type](#)" on page 8 for information on 16-bit values using unsigned integers.)

BACKGROUND operation

If you use the `BACKGROUND` option with any function, you must declare the associated data array as `'$STATIC`.

Unless you declare an array as `'$STATIC`, BASIC may move the array around in memory as the program is executing. Whenever you use the `BACKGROUND` option, the I/O function reads/writes from the data array in the background while the BASIC program continues executing in the "foreground." If BASIC moves the array while the I/O function is reading/writing to it, it will cause intermittent and unpredictable problems.

`cbStopBackground()` should be executed after normal termination of all background functions to clear variables and flags.

Using the Library with VisualBasic® for DOS

Compiling stand-alone EXE files

Due to a quirk in VisualBasic for DOS, the following message displays if you compile a stand-alone EXE file from within the IDE and set the EXE type to "Stand alone EXE file":

```
"fixup overflow at 334 in the segment -TEXT target external 'B$CEND'".
```

Disregard this error message. The compiled program will run without error.

Using the Library with C for DOS

The C libraries included with the system can be used with either the Microsoft or Borland C compilers.

C header file

Every C program that uses the Universal Library must have a line which includes the Universal Library C header file, `CB.H`. The following line should appear near the start of every program, before the first library call is made.

```
#include "cb.h"
```

Memory models

Both Borland and Microsoft C compilers support different memory models. The Universal Library comes with the following four versions of the library.

- CBCC.LIB - For use with compact model
- CBCS.LIB - For use with small model
- CBCM.LIB - For use with medium model
- CBCL.LIB - For use with large and huge model

Large data arrays

The Universal Library supports input and output from very large (>64K) amounts of data. If your program requires storage and transfer of large single data sets, you must compile it for the "huge" model and use the CBCL.LIB library. If you declare an array to hold the data, it should be declared `__huge`.

If you allocate memory (as is done in the example programs using `malloc`) it should be allocated using `_halloc` (Microsoft) or `halloc` (Borland), the pointer declared as `__huge` and memory freed using `_hfree` (Microsoft) or `hfree` (Borland). Note that you must also include the `malloc.h` header.

Compiling the sample C programs

The example programs demonstrate how to call each of the Universal Library functions from a C program. Two batch files are provided that show how to compile and link the sample programs using the Microsoft and Borland compilers.

- MAKEMC16.BAT - compile and link with Microsoft C
- MAKETC16.BAT - compile and link with Borland C

Using the Library with HP VEE

The Universal Library with HP VEE includes a complete interface to HP VEE providing a DataAcq-specific menu bar addition and functions as well as complete examples of all the library functions.

To understand how the interface to HP VEE interacts with I/O boards, you need to study both this manual and the example programs. This manual is written for symbolic programming languages such as BASIC and C. VEE is a graphical programming language.

It is very important that you scan the entire manual for information that relates to general performance. Remember, VEE is using the entire Universal Library as the interface to the I/O boards. Limitations and performance factors in the library are reflected in VEE programs that use the library. The manual contains related information throughout the contents. We encourage you to review the entire manual.

The Universal Library interface to VEE follows the structure of the library as it is used with all other languages. The arguments presented here in symbolic format are the same arguments you will need to specify when using VEE to control an I/O board. The manual explains the functions and each of the arguments. The VEE examples show how the function is interfaced to VEE and show how to use the function to control the I/O boards.

There is one exception to this rule: the programming argument `MemHandle` is replaced in VEE with the argument `DataArray`. VEE allocates data arrays directly. Windows programming languages use another method of pointing to data arrays. In addition to a name change, there is some VEE programming logic done to dimension a two-dimensional data array for all multichannel operations. This logic can be seen by examining the design view of the function.

Each function is implemented as a panel. All the arguments are accessible on the panel and require a value. In the example programs and in simple projects this method of presenting the functions is easiest to use. Each value is hard-coded into the panel.

If more complex projects are undertaken, open the design view of the function and drag certain arguments outside the panel. Dragging an object outside the panel will create a 'pin' to which you can connect constants, variables, or objects such as slider bars. In large projects the ability to supply an argument with a variable that acquires its value elsewhere is especially useful. See the VEE manual for information on how to do this.

See the example program `ULAI06.VEE` for an example of the multiple uses of several arguments, where it is better to specify the argument values globally. In this example, we have brought several arguments out of the panel.

Remember, if you drag an argument outside a panel you must reconnect the program flow (top and bottom pins) of the remaining arguments; the one above to the one below the argument you removed.

New HP VEE functions

Several new functions have been added strictly for use with HP VEE. These functions are listed separately in a section devoted to the VEE-specific functions. All VEE-specific functions begin with the name `cbv`, rather than `cb`. The new functions add VEE style data and array handling to the library.

Using the HP VEE interface is simple, and is a great way to connect your VEE programs to the real world. Read the manual, start with the examples, and then begin working up your own projects. Remember to call us with suggestions!

Installation note

Install the Universal Library in the default directory. The HP VEE library import block `CBI_UL` contains an exact path specification for the library `CBV.DLL` and its header file `CBV.H`. If you do not install these files into the default directory suggested by the install program, you will have to edit the library import block `CBI_UL` to point to the directory where the files are installed.

To edit the library import block `CBI_UL`:

1. Click on the **DataAcq** menu item and then click on its `cbLibrary` sub-menu item.
2. Place the mouse cursor at the desired location for the library import block and press the left mouse button once.
3. Double-click on the library import block object. A detailed `CBI_UL` library block will be displayed.
4. Within the `CBI_UL` library block, click on the button to the right of **File Name**, then enter the new path with the file name and click **OK**.
5. Click on the button to the right of **Definition File**, then enter the new path with the file name and click **OK**.

Using VEE 3.2 or later

If you are using VEE 3.2 or later, edit the library import block and change the library name from `CBV.DLL` to `CBV32.DLL`. Be sure to include the proper path.

Universal Library for .NET Description & Use

Programming the Universal Library API is now available through the various languages supported by the Microsoft .NET framework. All .NET applications access the 32-bit Windows Universal Library (CBW32.DLL) through the MccDaq .NET assembly (MCCDAQ.DLL). The MccDaq assembly provides an interface that exposes each Universal Library function that is callable from the .NET language.

The Universal Library for .NET is designed to provide the same "look and feel" as the Universal Library for 32-bit Windows. This design makes it easier to port over existing data acquisition programs, and minimizes the learning curve for programmers familiar with the CBW32.DLL interface.


In the Universal Library for .NET, each function is exposed as a class method with virtually the same parameter set as their UL counterparts.

Configuring a UL for .NET project

In a .NET application, there are no header files to include in your project. You define methods and constants by adding the MccDaq assembly, or Namespace, as a reference to your project. You access UL for .NET methods through a class that has the Universal Library as a member.


To add the MccDaq Namespace as a reference in a Visual Studio .NET project:

1. Start a new Visual Basic or C# project in Visual Studio .NET.
2. From the Visual Studio .NET Solution Explorer window, right-click on **References** and select **Add Reference**.



The **Add Reference** window appears.


3. From the **.NET** tab, select the **MccDaq** option from the displayed list of .NET assemblies and click on the **Select** button.



MccDaq displays in the **Selected Components** area on the window.

4. Click on the **OK** button.

MccDaq appears under the **References** folder in the Solution Explorer window.



The MccDaq Namespace is now referenced by your Visual Studio .NET project.

General UL for .NET language interface description

The **MccDaq Namespace** provides an interface that exposes each Universal Library for .NET method as a member of a class with virtually the same parameters set as their UL counterparts. The MccDaq Namespace is a logical naming scheme for grouping related types. The .NET Framework uses a hierarchical naming scheme for grouping types into logical categories of related functionality.

When you develop a .NET application that uses the Universal Library, you add the MccDaq Namespace as a reference to your project. There are no "header" files in a .NET project.

The MccDaq Namespace contains the classes and enumerated values by which UL for .NET applications access the Universal Library data types and functions.

The MccDaq Namespace contains four main classes:

- MccBoard class
- ErrorInfo class
- MccService class
- GlobalConfig class

The MccDaq assembly allows you to design Common Language Specification (CLS)-compliant programs. A CLS-compliant program contains methods that can be called from any existing or future language developed for the Microsoft .NET framework. Use CLS-compliant data types to ensure future compatibility.

MccBoard class

The MccBoard class provides access to all of the methods for data acquisition and properties providing board information and configuration for a particular board.

Class Constructors

The MccBoard class provides two constructors; one which accepts a board number argument and one with no arguments.

The following code examples demonstrate how to create a new instance of the MccBoard class using the latter version with a default board number of 0:

Visual Basic	<pre>Private DaqBoard As MccDaq.MccBoard DaqBoard = New MccDaq.MccBoard()</pre>
C#	<pre>private MccDaq.MccBoard DaqBoard; DaqBoard = new MccDaq.MccBoard();</pre>

The following code examples demonstrate how to create a new instance of the `MccBoard` class with the board number passed to it:

Visual Basic	<pre>Private DaqBoard As MccDaq.MccBoard DaqBoard = New MccDaq.MccBoard(BoardNumber)</pre>
C#	<pre>private MccDaq.MccBoard DaqBoard; DaqBoard = new MccDaq.MccBoard(BoardNumber);</pre>

Class properties

The `MccBoard` class also contains six properties that you can use to examine or change the configuration of your board. The configuration information for all boards is stored in the `CB.CFG` file, and is loaded from `CB.CFG` by all programs that use the library.

Properties	Description
BoardName	Name of the board associated with an instance of the <code>MccBoard</code> class.
BoardNum	Number of the board associated with an instance of the <code>MccBoard</code> class.
BoardConfig	Gets a reference to a cBoardConfig class object. Use this class reference to get or set various board settings.
CtrConfig	Gets a reference to a cCtrConfig class object. Use this class reference to get or set various counter settings.
DioConfig	Gets a reference to a cDioConfig class object. Use this class reference to get or set various digital I/O settings.
ExpansionConfig	Gets a reference to a cExpansionConfig class object. Use this class reference to get or set various expansion board settings.

Class methods

The `MccBoard` class contains close to 80 methods that are equivalents of the function calls used in the standard Universal Library. The `MccBoard` class methods have virtually the same parameters set as their UL counterparts.

The following code examples demonstrate how to call the `AIn()` method of the `MccBoard` object `MccDaq`:

Visual Basic	<pre>ULStat = DaqBoard.AIn(Chan, Range, DataValue)</pre>
C#	<pre>ULStat = DaqBoard.AIn(Chan, Range, out DataValue);</pre>

Many of the arguments are `MccDaq` enumerated values. Enumerated values take settings such as range types or scan options and put them into logical groups. For example, to set a range value, reference a value from the `MCCDaq.Range` enumerated type, such as `Range.Bip5Volts`. Refer to Table 5-1 on page 20 for a list of `MccDaq` enumerated values.

The *Universal Library Function Reference* contains detailed information about all `MccBoard` class methods. This document is available on our web site at www.mccdaq.com/PDFmanuals/sm-ul-functions.pdf.

ErrorInfo class

Most UL methods return `ErrorInfo` objects. These objects contain two properties that provide information on the status of the method called:

- `ErrorInfo.Message` property gets the text of the error message associated with a specific error code.
- `ErrorInfo.Value` property gets the named constant value associated with the `ErrorInfo` object.

The `ErrorInfo` class also includes error code enumerated values, which define the error number and associated message which can be returned when you call a method.

MccService class

The `MccService` class contains all members for calling utility UL functions. This class contains nine static methods (you do not need to create an instance of the `MccService` class to call these methods):

- `DeclareRevision()`
- `WinArrayToBuf()`
- `ErrHandling()`
- `WinBufToArray()`
- `GetRevision()`
- `WinBufAlloc()`
- `FileGetInfo()`
- `WinBufFree()`
- `FileRead()`

The following code examples demonstrate how to call a UL for .NET memory management method from within a Universal Library program:

```
WindowHandle=MccService.WinBuffAlloc(1000)
MccService.WinBuffFree(WindowHandle)
```

GlobalConfig class

The `GlobalConfig` class contains all of the members for getting global configuration information. This class contains three properties:

- `MccDaq.GlobalConfig.NumBoards` property returns the maximum number of boards that you can install at one time. `ConfigGlobal=MccDaq.GlobalConfig.NumBoards`
- `MccDaq.GlobalConfig.NumExpBoards` property returns the maximum number of expansions boards that are allowed to be installed on the board. `ConfigGlobal=MccDaq.GlobalConfig.NumExpBoards`
- `MccDaq.GlobalConfig.Version` property is used to determine compatibility with the library version. `ConfigGlobal=MccDaq.GlobalConfig.Version`

Each of these properties is typed as an Integer.

MccDaq enumerations

The `MccDaq` Namespace contains enumerated values which are used by many of the methods available from the `MccDaq` classes (see Table 5-1). Refer to specific method descriptions in the Universal Library Function Reference for the values of each enumerated type. This document is available on our web site at www.mccdaq.com/PDFmanuals/sm-ul-functions.pdf.

Table 5-1. MccDaq Enumerated Values

Enumeration Name	Description
<code>MccDaq.BCDMode</code>	Lists all of the counting format options.
<code>MccDaq.C8254Mode</code>	Lists all of the operating modes for 8254 counters.
<code>MccDaq.CompareValue</code>	List all options for comparing values while configuring a 9513 counter.
<code>MccDaq.ConnectionPin</code>	Defines the connector pins to associate with the signal type and direction when calling the <code>SelectSignal()</code> method.
<code>MccDaq.CounterControl</code>	Defines the possible state of each counter channel (enabled/disabled).

Enumeration Name	Description
MccDaq.CountDirection	Defines the count direction when configuring counters.
MccDaq.CountEdge	Defines the edge used for counting.
MccDaq.CounterRegister	Lists all of the register names to load the count to.
MccDaq.CounterSource	Lists all counter input sources.
MccDaq.CountingMode	Lists all valid modes for a C7266 counter configuration.
MccDaq.CtrlOutput	Lists all of the options for linking counter 1 to counter 2.
MccDaq.DACUpdate	Defines the available DAC update modes
MccDaq.DataEncoding	Lists the format of the data that is returned by a counter.
MccDaq.DigitalPortDirection	Configures a digital I/O port as input or output.
MccDaq.DigitalLogicState	Defines all digital logic states.
MccDaq.DigitalPortType	Defines all digital port types.
MccDaq.DTMode	Lists all modes to transfer to/from the memory boards.
MccDaq.ErrorHandling	Defines all error handling options.
MccDaq.ErrorReporting	Defines all error reporting options.
MccDaq.EventType	Lists all available event conditions.
MccDaq.FlagPins	Lists all signals types that can be routed to the FLG1 and FLG2 pins on the 7266 counters.
MccDaq.FunctionType	List all valid function types used with data acquisition methods.
MccDaq.GateControl	List all of the gating modes for configuring a 9513 counter.
MccDaq.IndexMode	List the actions to be taken when the Index signal is received by a 7266 counter.
MccDaq.InfoType	Lists all configuration information to be used with the MccBoard class configuration methods.
MccDaq.OptionState	Enables or disables various options.
MccDaq.C9513OutputControl	List all of the types of output from a 9513 counters.
MccDaq.C8536OutputControl	Lists all of the types of output from an 8536 counters.
MccDaq.Quadrature	Lists all of the resolution multipliers for quadrature input.
MccDaq.Range	Defines the set of ranges within the UL for A/D and D/A operations.
MccDaq.RecycleMode	Lists the recycle mode options for 9513 and 8536 counters.
MccDaq.Reload	Lists the options for reloading the 9513 counter.
MccDaq.ScanOptions	List the available options for paced input/output methods.
MccDaq.SignalType	List all signal types associated with a connector pin on boards supporting ATCC.
MccDaq.SignalDirection	Lists all of the directions available from a specified signal type assigned to a connector pin.
MccDaq.SignalPolarity	List all available polarities for a specified signal.
MccDaq.SignalSource	List all of the signal sources of the signal from which the frequency will be calculated.
MccDaq.StatusBits	List all status bits available when reading counter status.
MccDaq.TempScale	Lists valid temperature scales that the input can be converted to.
MccDaq.TimeOfDay	List all time of day options for initializing a 9513 counter.
MccDaq.TriggerType	List all valid trigger types for the MccBoard.SetTrigger method.
MccDaq.ThermocoupleOptions	Specifies whether or not to apply smoothing to temperature readings.

Parameter data types

Many of the Universal Library for .NET methods are overloaded to provide for signed or unsigned data types as parameters. The `AConvertData()` method is shown below using both signed and unsigned data types.

VB.NET	Public Function AConvertData (ByVal numPoints As Integer, ByRef adData As Short, ByRef chanTags As Short) As MccDaq.ErrorInfo Member of MccDaq.MccBoard
	Public Function AConvertData (ByVal numPoints As Integer, ByRef adData As System.UInt16, ByRef chanTags As System.UInt16) As MccDaq.ErrorInfo Member of MccDaq.MccBoard
C# .NET	public MccDaq.ErrorInfo AConvertData (System.Int32 numPoints, System.Int16 adData, System.Int16 chanTags) Member of MccDaq.MccBoard
	public MccDaq.ErrorInfo AConvertData (System.Int32 numPoints, System.UInt16 adData, System.UInt16 chanTags) Member of MccDaq.MccBoard

For most data acquisition applications, unsigned data values are easier to manage. However, since Visual Basic (version 6 and earlier) does not support unsigned data types, it may be easier to port these programs to .NET if the signed data types are used for the method parameters. For additional information on using signed data types, refer to the section "[16-bit values using a signed integer data type](#)" on page 8.

The short (Int16) data type is Common Language Specification (CLS) compliant, is supported in VB, and will be included in any future .NET language developed for the .NET framework. Using CLS-compliant data types ensures future compatibility. Unsigned data types are not CLS compliant, but are still supported by various .NET languages, such as C#.

Differences between the UL and UL for .NET

Table 5-2 lists the differences between the Universal Library and the Universal Library for .NET.

Table 5-2. Differences between UL and UL for .NET

	Universal Library	Universal Library for .NET
Board Number	The board number is included as a parameter to the board functions.	An MccBoard class is created for each board installed, and the board number is passed to that board class.
Functions	Set of function calls defined in a header.	Set of methods. Methods of MccBoard or MccService classes. To access a method, instantiate a UL for .NET class and call the appropriate method using that class.
Constants	Constants are defined and assigned a value in the "header" file.	Constants are defined as enumerated types.
Return value	The return value is an Error code.	The return value is an ErrorInfo object that contains the error's number and message.

Board number

In a .NET application, multiple boards may be programmed by creating an `MccBoard` Class object for each board installed:

<code>Board0 = new MccBoard (0)</code>
<code>Board1 = new MccBoard (1)</code>
<code>Board2 = new MccBoard (2)</code>

Note that the board number may be passed into the `MccBoard` class, which eliminates the need to include the board number as a parameter to the board methods.

MCC classes

To use board-specific Universal Library functions inside a .NET application, you use methods of the appropriate class. UL for .NET classes are listed in Table 5-3.

Table 5-3. UL for .NET Board Classes

UL for .NET Class	Description
MccBoard	Access board-related Universal Library functions.
ErrorInfo	Utility class for storing and reporting error codes and messages.
BoardConfig	Gets and sets board configuration settings.
CtrConfig	Gets and sets counter board configuration settings.
DioConfig	Gets and sets digital I/O configuration settings.
ExpansionConfig	Gets and sets expansion board configuration settings.
GlobalConfig	Gets and sets global configuration settings.
MccService	Access utility Universal Library functions.

Refer to the Universal Library Function Reference (available on our web site at www.mccdaq.com/PDFmanuals/sm-ul-functions.pdf) for additional class information.

Methods

Methods are accessed through the class containing them. The following example demonstrates how to call the `AIN()` method from within a 32-bit Windows application and also from a .NET application.

VB Application using CBW32.DLL	VB .NET Application using MCCDAQ.DLL
<pre>Dim Board As Integer Dim Channel As Integer Dim Range As Integer Dim ULStat As Integer Dim DataValue As Short Board =0 Channel = 0 Range =BIP5VOLTS; ULStat =cbAIN(Board, Channel, Range, DataValue)</pre>	<pre>Dim Board0 As MccBoard Board0 = new MccDaq.MccBoard(0) Dim Channel As Integer Dim Range As MccDaq.Range Dim ULStat As ErrorInfo Dim DataValue As UInt16 Channel = 0 Range =Range.BIP5VOLTS; ULStat =Board0.AIn(Channel, Range, DataValue)</pre>

Enumerated types

Instead of using constants such as `BIP5VOLTS`, the Universal Library for .NET uses enumerated types. An enumerated type takes settings such as range types, scan options or digital port numbers and puts them into logical groups. Some examples are:

Range.Bip5Volts
Range.Bip10Volts
Range.Uni5Volts
Range.Uni10Volts
ScanOptions.Background
ScanOptions.Continuous
ScanOptions.BurstMode

If you are programming inside of Visual Studio .NET, the types that are available for a particular enumerated value display automatically when you type code:

```
int Gain =Range.
```



Error handling

For .NET applications, the return value for the Universal Library functions is an object (ErrorInfo), rather than a single integer value. The ErrorInfo object contains both the numeric value for the error that occurred, as well as the associated error message. Within a .NET application, error checking may be performed as follows:

```
ULStat=Board0.AIn(Channel, Range, DataValue)
`check the numeric value of ULStat
If Not ULStat.Value = ErrorInfo.ErrorCode.NoErrors Then
    `if there was an error, then display the error message
    MsgBox ULStat.Message
EndIf
```

Service methods

You can access other Universal Library functions that are not board-specific through the MccService class. This class contains a set of static methods you can access directly, without having to instantiate an MccService object. The following examples demonstrate library calls to .NET memory management methods:

```
WindowHandle = MccService.WinBuffAlloc(1000)
MccService.WinBuffFree(WindowHandle)
```

Configuration methods

In 32-bit Windows applications, you access board configuration information by calling the `cbGetConfig` and `cbSetConfig` API functions. In .NET applications, you access board configuration information through separate classes, such as `cBoardConfig`, `cCtrConfig`, `cDioConfig`, and `cExpansionConfig`. Each configuration item has a separate get and set method.

Some examples of how to access board configuration within a .NET application are shown below:

- `ULStat = Board0.BoardConfig.GetRange(RangeValue)`
- `ULStat = Board1.DioConfig.GetNumBits(DevNumber, Number)`
- `ULStat = Board2.CtrConfig.GetCtrType(DevNumber, CounterType)`
- `ULStat = Board3.BoardConfig.SetClock(ClockSource)`
- `ULStat = Board4.ExpansionConfig.SetCJCChan(DevNumber, CjcChan)`

How to Use the "Streamer" File Functions

File functions overview

The Universal Library can collect very large amounts of data to a "streamer" file. Once all of the data is streamed to a file, your program reads it back into arrays and processes it in chunks. This feature is particularly useful when you are using the Universal Library from DOS, where memory is limited. The library contains four functions that are used with "streamer" files:

- `cbFileAInScan()` and `cbFilePretrig()` read the A/D and store the data in a "streamer" file. The equivalent UL for .Net methods are `FileAInScan()` and `FilePretrig()`.
- `cbFileGetInfo()` returns information about the streamer file (the equivalent UL for .Net method is `FileGetInfo()`.)
- `cbFileRead()` reads data from a "streamer" file to an array (the equivalent UL for .Net method is `FileRead()`.)

In addition to these library functions, the library comes with three utility programs for use with the 16-bit version of the library; MAKESTRM.EXE, FRAGTEST.EXE and RDSTREAM.EXE. These utilities are not compatible with the 32-bit version of the library.

MAKESTRM creates a "streamer" file. When using the 16 bit library, this program should be run to allocate a file large enough to hold all of the data that will be later collected with `cbFileAInScan()` or `cbFilePretrig()` / `FileAInScan()` or `FilePretrig()`. The syntax is:

```
C:\MAKESTRM filename # <enter>
```

FRAGTEST checks an existing disk file to see if it is fragmented. In order to run at the faster sampling rates, the "streamer" file must not be fragmented. Refer to "[Speeding up Disk Files \(De-fragmenting\)](#)" on page 26 for more information. The syntax is:

```
C:\FRAGTEST filename <enter>
```

RDSTREAM reads a "streamer" file and prints its contents on the screen. The syntax is:

```
C:\RDSTREAM filename <enter>
```

Hard disk vs. RAM disk files

The simplest type of file to use is a standard DOS file on a hard disk. Hard disk files have the disadvantage of being slower than RAM disks. RAM disk (or virtual disk) files are faster but they are limited in size by the amount of available memory in your computer.

Maximum sampling speed

The maximum sustainable sampling rate that can be specified with the `cbFile` functions is very hard to predict. It depends on the speed of the CPU and the speed of the disk.

In addition to the variation in sampling speed from machine to machine, there can also be variations on the same machine between consecutive operations of the same program. When reading an A/D to memory (non-streaming modes) there is a hard and fast maximum sampling speed that cannot be exceeded. When using the streaming modes the maximum rate is much fuzzier and must be arrived at by trial and error.

A rough guideline of attainable speeds are those on a 33 MHz 80386 machine with a fast hard disk it should be possible to collect a megabyte of data at 200 kHz sampling rate to a disk file. It should also be possible to collect a megabyte of data to a RAM disk at 330 kHz. In general the maximum sustainable speed for `cbFilePretrig()` / `FilePretrig()` will be somewhat less than for `cbFileAInScan()` / `FileAInScan()`.

Another characteristic of these "streaming" modes is that the more data you collect the lower the maximum speed will be. On any machine with any speed disk, you can collect 32000 samples to a disk file at the maximum A/D speed of 330 kHz. If you are pushing the upper limits of speed you will find that you can collect 100K samples at a faster rate than you can collect 500K samples, etc.

How to determine the maximum sampling speed

The only way to determine the maximum safe speed is to run it repeatedly. The speed may work the first time but may not necessarily work the next time. The only way to be sure that you can reliably run at a particular speed is to try it numerous times. Another method is to increase the speed to the point where it begins to fail every time so that you get some sense of whether or not you are pushing the speed limit on your computer.

To test it, write a program that calls `cbFileAInScan()` or `cbFilePretrig()` / `FileAInScan()` or `FilePretrig()` (depending on whether you need pre-trigger data). Check the returned error code. If you get an `OVERRUN` error (error code of 29), the sampling rate is too high. Whenever you get `OVERRUN` error, some data was collected but not all of it. It is often useful to check how much data was collected to find out whether it was almost fast enough or not even close.

Speeding up disk files (defragmenting)

Because of the way that disks work, the time that it takes to write to them can vary tremendously. A large disk file is made up of many small pieces that are written individually to the disk. If the file is contiguous (each piece is side by side) the speed is very fast. If the file is fragmented (pieces are in different places on the disk) the speed is much slower. If you create a large disk file, it will most likely be fragmented to some degree, and the maximum sampling speed will be much lower than it would be for an unfragmented file.

To get around this problem, you should use a disk optimizer or defragmenter program immediately before creating the streamer file with `MAKESTRM`. After you create the streamer file, it will remain unfragmented so long as you do not erase and recreate it. The disk optimizer program included with Norton Utilities™, is called Speed Disk, or SD. To run it type:

```
SD /Q
```

This will execute the "Quick" optimize, which works as well as the full optimization.

After de-fragmenting the disk, create a streamer file that is large enough to hold as much data as you plan to collect with `cbFileAInScan()` or `cbFilePretrig()`. To create the disk file, run the standalone `MAKESTRM.EXE` program. This will create a streamer file of the required size.

After the file is created, run `FRAGTEST.EXE` to see whether or not the file is fragmented. It is possible that the file may be fragmented even though you just de-fragmented the disk. This is because the disk may contain some bad sectors that could not be moved when the disk was optimized. When you create the new file and it hits one of these bad sectors, it has to skip over it, hence fragmented.

If `FRAGTEST` reports that the file is fragmented, create a second file and test that with `FRAGTEST`. Repeat this until `FRAGTEST` reports that the file is OK. After you have an unfragmented disk file you can try using it with `cbFileAInScan()` or `cbFilePretrig()` / `FileAInScan()` or `FilePretrig()` to collect data. If the maximum sampling speed is still too slow, you should probably switch to a RAM disk.

RAM disks

A RAM disk is not really a disk. It is a device driver that sets aside some of the computer's memory and makes it appear to DOS as a disk drive. When you install a RAM disk on your computer, it appears exactly as if you have another VERY fast hard disk drive. For example, if you have one hard disk (drive C:) then when you install the RAM disk it will appear as if you have another hard disk, drive D.

After the RAM disk is installed, all DOS commands work exactly the same on the RAM disk as on the hard disk. For example you can COPY, DEL, MKDIR, CD just as you would on a hard disk.

Installing a RAM disk

The RAM disk driver comes with DOS. Refer to your DOS manual for more information. In older versions of DOS it is called either RAMDRIVE.SYS or VDISK.SYS. To install it you must add one line to your \CONFIG.SYS file. Find which directory the DOS files are installed in on your machine. CD to that directory and look for a file called RAMDRIVE.SYS or VDISK.SYS. If it is not there look at the other .SYS files in the directory and refer to your DOS manual to find out if any of them are a RAM Disk driver. After you have located the file add an entry to the \CONFIG.SYS file.

If the RAMDRIVE.SYS file was in a directory called DOS then you would add the following line to the \CONFIG.SYS file.

```
device=c:\dos\ramdrive.sys
```

The default size for the RAM disk is usually 64K. You will almost certainly want to make it larger than that. The larger you make it the more data you can collect but the less memory will be available for other programs.

To set up a 4 megabyte RAM disk, add the following line to your CONFIG.SYS file:

```
device=c:\dos\ramdrive.sys 4000
```

If your computer is an 80x86, install the RAM disk in extended memory (above 1M) by specifying the /e option:

```
device=c:\dos\ramdrive.sys 4000 /e
```

After you add the new line to the \CONFIG.SYS file, reboot the computer (Press *CTRL-ALT-DEL*) to install the RAM disk. When the machine reboots it should print a message on the screen that describes the RAM disk.

Using the RAM disk

To use the RAM disk, specify the drive letter in the FileName argument of `cbFileAInScan()` or `cbFilePreTrig()/FileAInScan()` or `FilePreTrig()`. For example, if the RAM disk is drive D: on your system, you could set the name of the "streamer" file in your program to "D:TEST.DAT"

This file can be created with the MAKESTRM.EXE program supplied with the Universal Library. To set up a file large enough to hold a million samples, include the following line in your AUTOEXEC.BAT file:

```
C:\CB\MAKESTRM D:\TEST.DAT 1000000
```

The name TEST.DAT is an example. Use the name of your preference. When you execute `cbFileAInScan()` or `cbFilePreTrig()/FileAInScan()` or `FilePreTrig()`, it will fill up the file on your RAM drive. This file will be lost as soon as the power is switched off, so if you wish to keep the data you must copy it to the hard disk before turning the computer off.

Analog Input Boards

Introduction

All boards that have analog input support the `cbAIn()`/`AIn()` and `cbAInScan()`/`AInScan()` functions, except expansion boards, which only support `cbAIn()`. Boards released after the printing of this manual are described in README files contained on the Universal Library disk.

When hardware-paced A/D conversion is not supported, `cbAInScan()`/`AInScan()` loops through software paced conversions. The scan will execute at the maximum speed possible. This speed will vary with CPU speed. The only valid option in this case is `CONVERTDATA`.

Concurrent analog input and output for paced analog inputs, paced analog outputs

For boards with both paced analog inputs and paced analog outputs, concurrent analog input and output scans are supported. That is, these boards allow operations with analog input functions (`cbAInScan/AInScan()` and `cbAPretrig/APretrig`) and analog output functions (`cbAOutScan/AOutScan()`) to overlap without having to call `cbStopBackground()/StopBackground()` between the start of input and output scans.

Trigger support

Digital Trigger

If trigger support is "Polled gate" (as opposed to "Hardware"), you implement a trigger by gating the on-board pacer. This disables the on-board pacer. The trigger input is then polled continuously until the trigger occurs. When that happens, the software disables the gate input so that when the trigger returns to its original state, it does not affect the pacer and acquisition continues until the requested number of samples has been acquired. There are two side effects to this type of trigger:

- The polling portion of the function does not occur in the background, even if the `BACKGROUND` option was specified (although the actual data acquisition does).
- The trigger does not necessarily occur on the rising edge. Acquisition can start at any time after the function is called if the trigger input is at "active" level. For this reason, it is best to use a trigger that goes active for a much shorter time than it is inactive.

Similar to 'Polled gate' triggering is 'Polled digital input' triggering, where the pacer is disabled while the state of a digital input is polled. When the state changes to active, the pacer is enabled by the software. The polled digital input trigger type limitations are very similar to the polled gate type explained above.

Analog Trigger

You set up the trigger levels for an analog trigger using the function `cbSetTrigger / SetTrigger`, passing the appropriate values to the `HighThreshold` and `LowThreshold` arguments.

For most boards that support analog triggering, you can calculate the `HighThreshold` and `LowThreshold` values by passing the required trigger voltage level and the appropriate `Range` to the `cbFromEngUnits/FromEngUnits` function.

However, for some boards, you must manually calculate `HighThreshold` and `LowThreshold`. If a board requires manual calculation, that information will be included in the Trigger information for the specific product in this section. The procedure for manually calculating these values is detailed in the Universal Library Function Reference in the description of the `cbSetTrigger / SetTrigger` function.

Sampling rate using SINGLEIO

When using this mode of data transfer, the maximum analog sampling rate is dependent on the speed of the computer in which the board is installed. In general, it is in the range of 5 to 50 kHz. If the requested speed cannot be sustained, an overrun error will occur. Data will be returned, but likely there will be gaps. Some boards, such as the **CIO-DAS08**, support only this mode, so the maximum rate attainable with these boards is system-dependent.

PCI-DAS6000 Series

Analog Input

Analog input functions and methods supported

UL: cbAIn(), cbAInScan(), cbATrig(), cbAPretrig(), cbFileAInScan(),
 cbFilePretrig(), cbALoadQueue()

UL for .NET: AIn(), AInScan(), ATrig(), APretrig(), FileAInScan(), FilePretrig(),
 ALoadQueue()

Analog input argument values

Options BACKGROUND, CONTINUOUS, EXTCLOCK, CONVERTDATA, SINGLEIO, DMAIO, BLOCKIO,
 BURSTMODE, EXTTRIGGER

Packet size is 512 for all PCI-6000 Series in most configurations. The exceptions are shown below.

Device	Aggregate rate	Packet size
PCI-DAS6040	400 kHz – 800 kHz	1024
PCI-DAS6070	Greater than 800 kHz	2048
PCI-DAS6071		

HighChan 0 to 15 in single-ended mode, 0 to 7 in differential mode

For **PCI-DAS6031**, **PCI-DAS6033** and **PCI-DAS6071**, the following additional argument values are also valid:

16 to 63 in single-ended mode, 8 to 31 in differential mode

Rate

PCI-DAS6030, **PCI-DAS6031**, **PCI-DAS6032**, and **PCI-DAS6033**

Up to 100000

PCI-DAS6013, **PCI-DAS6014**, **PCI-DAS6023**, **PCI-DAS6025**, **PCI-DAS6034**,
PCI-DAS6035 and **PCI-DAS6036**

Up to 200000

PCI-DAS6040

Up to 500000 Single-channel

Up to 250000 Multi-channel

PCI-DAS6052

Up to 333000

PCI-DAS6070, **PCI-DAS6071**

Up to 1250000

Range

PCI-DAS6013, **PCI-DAS6014**, **PCI-DAS6023**, **PCI-DAS6025**, **PCI-DAS6034**,
PCI-DAS6035 and **PCI-DAS6036**

BIP10VOLTS (± 10 volts (V))

BIP5VOLTS (± 5 V)

BIPP5VOLTS (± 0.5 V)

BIPP05VOLTS (± 0.05 V)

PCI-DAS6030, PCI-DAS6031, PCI-DAS6032 and PCI-DAS6033

BIP10VOLTS	(± 10 V)	UNI10VOLTS	(0 to 10 V)
BIP5VOLTS	(± 5 V)	UNI5VOLTS	(0 to 5 V)
BIP2VOLTS	(± 2 V)	UNI2VOLTS	(0 to 2 V)
BIP1VOLTS	(± 1 V)	UNI1VOLTS	(0 to 1 V)
BIPPT5VOLTS	(± 0.5 V)	UNIPT5VOLTS	(0 to 0.5 V)
BIPPT2VOLTS	(± 0.2 V)	UNIPT2VOLTS	(0 to 0.2 V)
BIPPT1VOLT	(± 0.1 V)	UNIPT1VOLTS	(0 to 0.1 V)

PCI-DAS6040, PCI-DAS6052, PCI-DAS6070 and PCI-DAS6071

BIP10VOLTS	(± 10 V)	UNI10VOLTS	(0 to 10 V)
BIP5VOLTS	(± 5 V)	UNI5VOLTS	(0 to 5 V)
BIP2PT5VOLTS	(± 2.5 V)	UNI2VOLTS	(0 to 2 V)
BIP1VOLT	(± 1 V)	UNI1VOLT	(0 to 1 V)
BIPPT5VOLTS	(± 0.5 V)	UNIPT5VOLTS	(0 to 0.5 V)
BIPPT25VOLTS	(± 0.25 V)	UNIPT2VOLTS	(0 to 0.2 V)
BIPPT1VOLT	(± 0.1 V)	UNIPT1VOLT	(0 to 0.1 V)
BIPPT05VOLTS	(0.05 V)		

Analog output

PCI-DAS6014, PCI-DAS6025, PCI-DAS6030, PCI-DAS6031, PCI-DAS6035, PCI-DAS6036, PCI-DAS6040, PCI-DAS6052, PCI-DAS6070 and PCI-DAS6071

Analog output functions and methods supported

UL: cbAOut (), cbAOutScan ()
 UL for .NET: AOut (), AOutScan ()

Analog output argument values

Options SIMULTANEOUS, BACKGROUND, EXTCLOCK, CONTINUOUS (packet size = 512)

HighChan 0 to 1

Rate **PCI-DAS6014, PCI-DAS6025, PCI-DAS6035, PCI-DAS6036**

10 kHz

PCI-DAS6030 and PCI-DAS6031

100 kHz

PCI-DAS6040

500 kHz single-channel

250 kHz multi-channel

PCI-DAS6052

333 kHz

PCI-DAS6070 and PCI-DAS6071

1.0 MHz

Range **PCI-DAS6014, PCI-DAS6025, PCI-DAS6035 and PCI-DAS6036**

BIP10VOLTS (± 10 V)

PCI-DAS6030, PCI-DAS6031, PCI-DAS6040, PCI-DAS6052, PCI-DAS6070 and PCI-DAS6071

BIP10VOLTS (± 10 V) UNI10VOLTS (0 to 10 V)

DataValue 0 to 4095

For the **PCI-DAS6014, PCI-DAS6030, PCI-DAS6031, PCI-DAS6036** and **PCI-DAS6052**, the following additional argument value is also valid:

0 to 65535 (Refer to "[16-bit values using a signed integer data type](#)" on page 8 for information on 16-bit values using unsigned integers).

Pacing Hardware pacing, external or internal clock supported.

Digital I/O**Digital I/O functions and methods supported**

UL: `cbDOut()`, `cbDIn()`, `cbDBitIn()`, `cbDBitOut()`, `cbDConfigBit()`,
`cbDConfigPort()`

UL for .NET: `DOut()`, `DIn()`, `DBitIn()`, `DBitOut()`, `DConfigBit()`, `DConfigPort()`,
`GetDInMask()`, `GetDOutMask()`

Digital I/O argument values

PortNum AUXPORT*

DataValue 0 to 255

BitNum 0 to 7

For the **PCI-DAS6025**, the following additional argument values are also valid

PortNum FIRSTPORTA, FIRSTPORTB, FIRSTPORTCL, FIRSTPORTCH

DataValue 0 to 15 for FIRSTPORTCL or FIRSTPORTCH;
0 to 255 for FIRSTPORTA or FIRSTPORTB

BitNum 0 to 23 for FIRSTFIRSTPORTA

*AUXPORT is bitwise configurable for these boards, and must be configured using `cbDConfigBit()/DConfigBit()` or `cbDConfigPort()/DConfigPort()` before use.

Counter I/O**Counter functions and methods supported**

UL: `cbC8254Config()`, `cbCIn()`, `cbCLoad()`

UL for .NET: `C8254Config()`, `CIn()`, `CLoad()`

Counter argument values

CounterNum 1 to 2

Config HIGHONLASTCOUNT, ONESHOT, RATEGENERATOR, SQUAREWAVE, SOFTWARESTROBE,
HARDWARESTROBE

LoadValue 0 to 65535 (Refer to "[16-bit values using a signed integer data type](#)" on page 8 for information on 16-bit values using unsigned integers.)

RegNum: LOADREG1, LOADREG2

Triggering

Trigger functions and methods supported

UL: `cbSetTrigger()`

UL for .NET: `SetTrigger()`

Trigger argument values

TrigType `TRIGPOSEDGE, TRIGNEGEDGE, GATEHIGH, GATELOW`

For the **PCI-DAS6030, PCI-DAS6031, PCI-DAS6032, PCI-DAS6033, PCI-DAS6040, PCI-DAS6052, PCI-DAS6070** and **PCI-DAS6071**, the following additional argument values are valid:

`TRIGABOVE, TRIGBELOW, GATENEGHYS, GATEPOSHYS, GATEABOVE, GATEBELOW, GATEINWINDOW, GATEOUTWINDOW`

Threshold **PCI-DAS6040, PCI-DAS6070** and **PCI-DAS6071**
0 to 255

PCI-DAS6030, PCI-DAS6031, PCI-DAS6032, PCI-DAS6033, and PCI-DAS6052
0 to 4095

Event notification

Event notification functions and methods supported

UL: `cbEnableEvent(), cbDisableEvent()`

UL for .NET: `EnableEvent(), DisableEvent()`

Event notification argument values

EventType `ON_SCAN_ERROR, ON_PRETRIGGER*, ON_DATA_AVAILABLE, ON_END_AI_SCAN, ON_END_OF_AO_SCAN**`

*Note that the `EventData` for `ON_PRETRIGGER` events may not be accurate. In general, this value will be below the actual number of pretrigger samples available in the buffer.

Not supported for **PCI-DAS6013, PCI-DAS6023, PCI-DAS6032, PCI-DAS6033 and **PCI-DAS6034**.

Hardware considerations

Advanced timing and control configuration

You can access the advanced features provided by the Auxiliary Input/Output and DAQ-Sync interfaces through the board configuration page of *InstaCal* and the UL functions `cbGetSignal()` and `cbSelectSignal()`, or the UL for .NET methods `GetSignal()` and `SelectSignal()*`.

`ADC_TB_SRC` and `DAC_TB_SRC` are intended to synchronize the timebase of the analog input and output pacers across two or more boards. Internal calculations of sampling and update rates assume that the external timebase has the same frequency as its internal clock. Adjust sample rates to compensate for differences in clock frequencies.

For example, if the external timebase has a frequency of 10 MHz on a board that has an internal clock frequency of 40 MHz, the scan function samples or updates at a rate of about 1/4 the rate entered. However, while compensating for differences in the external timebase and internal clock frequency, if the rate entered results in an invalid pacer count, the function returns a `BADRATE` error.

*Although the PCI-DAS6013 and PCI-DAS6014 both support `cbSelectSignal/SelectSignal()`, these boards do not support DAQ-Sync. Therefore:

- Using the `DS_CONNECT` option with the `Connection` argument for the `cbSelectSignal()` function generates a `BADCONNECTION` error.
- Using the `DsConnect` option with the `connectionPin` parameter for the `SelectSignal()` method generates a `BADCONNECTION` error.

Pacing analog input

Hardware pacing, external or internal clock supported. The clock edge is selectable through `InstaCal` and `cbSelectSignal/SelectSignal()`.

When using `EXTCLOCK` and `BURSTMODE` together, do not use the A/D External Pacer to supply the clock. Use the A/D Start Trigger input instead. Since `BURSTMODE` is actually paced by the internal burst clock, specifying `EXTCLOCK` when using `BURSTMODE` is equivalent to specifying `EXTTRIGGER`.

Except for `SINGLEIO` transfers, `CONTINUOUS` mode scans require enough memory for two packets, or 1024 samples. The packet size is 512 samples.

Analog input configuration

16 channel boards: The analog input mode may be 8 channel differential, 16 channel single-ended referenced to ground or 16 channel single-ended non-referenced, and may be selected using `InstaCal`.

64-channel boards: The analog input mode may be 32 channel differential, 64 channel single-ended referenced to ground, or 64 channel single-ended non-referenced, and may be selected using `InstaCal`.

Triggering and gating

Digital (TTL) hardware triggering is supported for the entire series. `cbSetTrigger()/SetTrigger()` is supported for `GATEHIGH`, `GATELOW`, `TRIGPOSEDGE`, `TRIGNEGEDGE`.

The A/D PACER GATE input is used for gating with `GATEHIGH` or `GATELOW`. The A/D START TRIGGER input is used for triggering with `TRIGPOSEDGE` and `TRIGNEGEDGE`.

When using `cbAPretrig()` or `cbFilePretrig()/APretrig()` or `FilePretrig()`, use the A/D Stop Trigger input to supply the trigger.

For the **PCI-DAS6030, PCI-DAS6031, PCI-DAS6032, PCI-DAS6033, PCI-DAS6040, PCI-DAS6052, PCI-DAS6070** and **PCI-DAS6071**: Analog hardware triggering and gating are supported.

`cbSetTrigger()/SetTrigger()` is supported for `TRIGABOVE`, `TRIGBELOW`, `GATENEGHYS`, `GATEPOSHYS`, `GATEABOVE`, `GATEBELOW`, `GATEINWINDOW`, `GATEOUTWINDOW`.

The analog trigger source may be set via `InstaCal` as either the ATRIG input (pin #43 on the I/O connector), or as the first channel in the scan (CH# IN). To use the ATRIG input as the trigger source, set the `InstaCal` "Analog Input Trig Source" to "Analog Trigger Pin." To use the first scanned channel as the trigger source, set `InstaCal` to "1st Chan in the Scan."

Recommended trigger source when using analog gating features

If using analog gating features, we strongly recommend setting the ATRIG input as the trigger source.

Using the ATRIG input as the Trigger Input

When the trigger source is set to "Analog Trigger Pin," analog thresholds are set relative to the ± 10 V range.

Using the "First Channel in Scan" as the Trigger Input

When the trigger source is set to "1st Chan in Scan," the range used for the thresholds is the same as the A/D channel. When using analog gating features with "1st Channel in Scan" as the trigger source, be careful to only scan a single channel.

Calculating Analog Trigger Thresholds

Analog thresholds for the **PCI-DAS6030**, **PCI-DAS6031**, **PCI-DAS6032**, **PCI-DAS6033** and **PCI-DAS6052** are 12-bit values. For example: a threshold value of 0 equates to -10 volts (V), while a threshold value of 4095 equates to +9.9976 volts (V). Analog thresholds for the **PCI-DAS6040**, **PCI-DAS6070** and **PCI-DAS6071** are 8-bit values. For example: a threshold value of 0 equates to 10 V, while a threshold value of 255 equates to +9.92188 V.

You need to manually calculate trigger threshold values for these PCI-DAS6000 Series boards. For information on calculating thresholds, refer to the "Notes" section in the "cbSetTrigger()" and "SetTrigger()" in the *Universal Library Function Reference*.

Channel-Gain queue

When using `cbALoadQueue()/ALoadQueue()`, up to 8k elements may be loaded into the queue.

Analog Output

Using `cbAOutScan()/AOutScan()` in CONTINUOUS mode requires a minimum sample size of two packets. A packet is 512 samples.

Digital I/O configuration

AUXPORT is bitwise configurable for these boards, and must be configured using `cbDConfigBit()` or `cbDConfigPort()/DConfigBit()` or `DConfigPort()` before use.

Counters

The source for counters 1 and 2 may be internal 10 MHz, internal 100 kHz or external, and is selectable using *InstaCal*.

PCI-DAS4020 Series

Analog Input

Analog input functions and methods supported

UL:	cbAIn(), cbAInScan(), cbATrig(), cbAPretrig(), cbFileAInScan(), cbFilePretrig()
UL for .NET:	AIn(), AInScan(), ATrig(), APretrig(), FileAInScan(), FilePretrig()

Analog input argument values

Options	BACKGROUND, CONTINUOUS, EXTCLOCK, CONVERTDATA, SINGLEIO, DMAIO, BLOCKIO, EXTTRIGGER
HighChan	3 max (when scanning multiple channels, the number of channels scanned must be even)
Rate	Up to 20000000 (Contiguous memory may be required to achieve maximum performance. Refer to " Memory configuration " on page 38 for details.)
Range	BIP5VOLTS (± 5 V) BIP1VOLTS (± 1 V)

Analog output

Analog output functions and methods supported

UL:	cbAOut(), cbAOutScan()
UL for .NET:	AOut(), AOutScan()

Analog output argument values

Options	NONE
HighChan	1 max
Count	2
Rate	Ignored
Range	BIP10VOLTS (± 10 V) BIP5VOLTS (± 5 V)
DataValue	0 to 4095
Pacing	Software only

Digital I/O

Digital I/O functions and methods supported

UL:	cbDOut(), cbDIn(), cbDBitIn(), cbDBitOut(), cbDConfigPort()
UL for .NET:	DOut(), DIn(), DBitIn(), DBitOut(), DConfigPort()

Digital I/O argument values

PortNum	FIRSTPORTA, FIRSTPORTB, FIRSTPORTCL, FIRSTPORTCH
DataValue	0 to 255 for FIRSTPORTA or FIRSTPORTB; 0 to 15 for FIRSTPORTCL or FIRSTPORTCH
BitNum	0 to 23 for FIRSTPORTA

Counter I/O

Counter functions and methods supported

None

Triggering

Trigger functions and methods supported

UL: `cbSetTrigger()`

UL for .NET: `SetTrigger()`

Trigger argument values

TrigType	TRIGPOSEDGE, TRIGNEGEDGE, TRIGABOVE, TRIGBELOW, GATEHIGH, GATELOW, GATENEGHYS, GATEPOSHYS, GATEABOVE, GATEBELOW, GATEINWINDOW, GATEOUTWINDOW
Threshold	0 to 4095

Event notification

Event notification functions and methods supported

UL: `cbEnableEvent()`, `cbDisableEvent()`

UL for .NET: `EnableEvent()`, `DisableEvent()`

Event notification argument values

EventType	ON_SCAN_ERROR, ON_PRETRIGGER†, ON_DATA_AVAILABLE, ON_END_OF_AI_SCAN
-----------	---

Hardware considerations

Pacing analog input

Hardware pacing, external or internal clock supported. The clock source can be set via *InstaCal* to either the "Trig/Ext Clk" BNC input or the "A/D External Clock" input on the 40 pin connector (P3). Configuring for the BNC clock input will disable the clock input (pin 10) on the 40-pin connector. When the `EXTCLOCK` option is used, the clock signal presented to the "Trig/Ext Clk" BNC input or the "A/D External Clock" input is divided by 2 in one or two channel mode and is divided by 4 in four channel mode. If both `EXTCLOCK` and `EXTTRIGGER` are used, both the Trigger BNC and pin 10 on the 40-pin connector require signals. This is further explained in the "Triggering and gating" section below. When using `EXTCLOCK`, the `Rate` argument is used by the Universal Library to calculate the appropriate chain size. Set the `Rate` argument to the approximate rate used by the external clock to pace acquisitions.

When executing `cbAInScan()/AInScan()` with the `EXCLOCK` option, the first three clock pulses are used to set up the PCI-DAS4020/12, and the first sample is actually taken on the fourth clock pulse.

The packet size varies. See "[Memory configuration](#)" on page 38 for more information.

Triggering and gating

Digital (TTL) hardware triggering supported. The trigger source can be set via *InstaCal* to either the "Trig/Ext Clk" BNC input, the "A/D Start Trigger" input on the 40-pin connector (P3) or the "A/D Stop Trigger" input on the 40-pin connector (P3). Use the A/D Start Trigger input for the `cbAInScan()` and `cbFileAInScan()` functions, and `AInScan()` and `FileAInScan()` methods. For the `cbAPretrig()` or `cbFilePretrig()` functions, and the `APretrig()` or `FilePretrig()` method, use the A/D Stop Trigger input.

† The `EventData` for `ON_PRETRIGGER` events may not be accurate. In general, this value is below the actual number of pretrigger samples available in the buffer.

When using both EXTCLK and EXTTRIGGER options, one of the signals (either clock or trigger) must be assigned to the Trig/Ext Clk BNC input. The function of the Trigger BNC is determined by the setting of "Trig/Ext Clock Mode" in *InstaCal*. The Trig/Ext Clock BNC can be set to function as either the trigger ("A/D Start Trigger") or the clock ("A/D External Clock"). Pin 10 on the 40-pin connector then assumes the opposite function.

Analog hardware triggering supported. The trigger source can be set via *InstaCal* to any of the analog BNC inputs. `cbSetTrigger()/SetTrigger()` is supported for TRIGBELOW and TRIGABOVE trigger types. Analog thresholds are set relative to the voltage range set in the scan. For example, using a range of BIP1VOLTS during a `cbAInScan()/AInScan()`, (0) corresponds to -1 volt (V) and 4095 corresponds to +1 V.

When using the `cbAPretrig()` function or the `APretrig()` method, use either the TRIGGER BNC or pin 8 of the 40 pin connector. To use the BNC, set *InstaCal* "Trig/Ext Clock Mode" to A/D Stop Trigger; otherwise, if not set to this selection, pin 8 of the 40-pin connector is used.

When using `cbAPretrig()/APretrig()` with EXTCLK, the two inputs are required. The TRIGGER BNC can be set to function as either the pacer clock or the trigger. For the BNC to be setup as the pacer clock, set *InstaCal* "Trig/Ext Clk Mode" to A/D External Clock. To use the BNC as the trigger, set this *InstaCal* option to A/D Stop Trigger. If neither of these selections are used, the 40-pin connector will be used for both inputs; pin 8 will be input for A/D Stop Trigger, and pin 10 will be input for the pacer clock signal.

Digital (TTL) hardware gating supported. The gate source can be set via *InstaCal* to either the "Trig/Ext Clk" BNC input or the "A/D Pacer Gate" input on the 40-pin connector (P3).

Analog hardware gating supported. Analog thresholds are set relative to the voltage range set in the scan. For example, using a range of BIP1VOLTS during a `cbAInScan()/AInScan()`, (0) corresponds to (-1V) and 4095 corresponds to +1V.

The gate must be in the active (enabled) state before starting an acquisition.

For EXTCLK or EXTTRIGGER (digital triggering) using the BNC connector, *InstaCal* provides a configuration setting for thresholds. The selections available are either 0 V or 2.5 V. Use 0 V if the incoming signal is BIPOLAR. Use the 2.5 V option if the signal is UNIPOLAR, for example, standard TTL.

When using both EXTCLK and EXTTRIGGER options, one of the signals (either clock or trigger) must be assigned to the Trig/Ext Clk BNC input.

Memory configuration

In order to achieve the maximum sample rate under some conditions, a contiguous area of memory must be set up. The following is a guide that can be used to determine whether or not you need to set up this memory and how to accomplish it using *InstaCal*.

If the number of samples you are acquiring is less than 2K (2,048) samples then you do NOT need to set up contiguous memory (leave the **Memory Size** edit box in *InstaCal* at zero).

If you are acquiring more than 2048 samples, contiguous memory may be required depending on sample rate. Use the table below to determine if contiguous memory is required.

# of Channels	Rate Requiring Contiguous Memory (when sample count > 2048)
1	> 4 MHz
2	>2 MHz
4	>1 MHz

If contiguous memory is required, follow the *InstaCal* procedures below to set the size of the contiguous memory to reserve:

1. Run *InstaCal*, select the **PCI-DAS4020** board and click the **Configure** tab.
2. In the **Memory Size** edit box for the **Contiguous Memory Settings**, enter the amount of memory in kilobytes that you need for the acquisition.

To calculate the number of kilobytes required, use the following formula:

$$(\text{\# of kilobytes (KB)}) = \{(\text{\# of samples}) \times (2 \text{ bytes/sample}) \times (1 \text{ KB}/1024 \text{ bytes})\}$$

or

$$(\text{\# of KB}) = \{(\text{\# of samples})/512\}$$

Memory is allocated in blocks of 4 KB. As a consequence, *InstaCal* adjusts the amount entered upward to the nearest integer multiple of 4 KB. For example, the contiguous memory requirements for a 10,000-sample acquisition would be:

$$(10,000/512) = 19.5 \text{ rounded up to multiple of 4 KB} = 20 \text{ KB.}$$

Note that the maximum number of samples allowed for the given contiguous memory size is displayed as the **Sample Count** (displayed below the **Memory Size** edit box).

3. Reboot the computer. The Universal Library attempts to reserve the desired amount of contiguous memory at boot up time. If it is unable to reserve all the memory requested, the amount successfully reserved memory displays in the **Memory Size** entry when you run *InstaCal*.
4. Run *InstaCal*. In the **Memory Size** entry, verify the size of the contiguous memory that was successfully reserved.

Repeat this procedure to change or free the contiguous memory.

The size of the block shown in *InstaCal* is the *total contiguous memory* that is available to *all boards installed*. Other installed boards that call the `cbWinBufAlloc()` function or `WinBufAlloc()` method will also use this contiguous memory, so plan the size of the contiguous memory buffer accordingly.

With the following functions and methods, be aware of packet size, and adjust the number of samples acquired accordingly:

- `cbAPretrig()/APretrig()`
- `cbAInScan()/AInScan()` with the `CONTINUOUS` scan option.

These functions and methods use a circular buffer. Align the data by packets in the buffer. For these functions, the total number of samples must be greater than one packet (refer to the following table), and must be an integer multiple of packet size. In addition, contiguous memory must be used if noted in the following table. The minimum value for contiguous memory is calculated using the formula from step 2 above:

$$(\text{\# of KB}) = \{(\text{\# of samples}) / 512\}$$

For example, to run `cbAInScan` on one channel at 18 MHz with the `CONTINUOUS` option set, determine the minimum sample size from the table to be 262,144 (since the `Rate` is between 14 and 20 MHz). The minimum contiguous memory is calculated as:

$$(262,144 / 512) = 512 \text{ KB}$$

Number of Channels	Rate in MHz	Packet Size in Samples	Minimum Sample Size (two packets)	Contiguous Memory	Min Contiguous Memory (based on Min Sample Size)
1	20 >= Rate >= 13.3	131,072	262,144	Required	512 KB
	13.3 > Rate >= 4	65,536	131,072	Required	256 KB
	4 > Rate >= 2	4,096	8,192	Not Required	0 KB
	2 > Rate	2,048	4,096	Not Required	0 KB
2	20 >= Rate >= 6.6	131,072	262,144	Required	512 KB
	6.6 > Rate >= 2	65,536	131,072	Required	256 KB
	2 > Rate >= 1	4,096	8,192	Not Required	0 KB
	1 > Rate	2,048	4,096	Not Required	0 KB
4	20 >= Rate >= 3.3	131,072	262,144	Required	512 KB
	3.3 > Rate >= 1	65,536	131,072	Required	256 KB
	1 > Rate >= 0.5	4,096	8,192	Not Required	0 KB
	0.5 > Rate	2,048	4,096	Not Required	0 KB

*Note that the EventData for ON_PRETRIGGER events may not be accurate. In general, this value will be below the actual number of pretrigger samples available in the buffer.

Notes for SoftWIRE® users

Memory configuration

The Analog In Scan control may require more contiguous memory than listed in the prior table. When the CONTINUOUS option is set for the Analog In Scan control, the control allocates a buffer large enough to hold four times as much data as required for a single scan. As a consequence, if you will be running CONTINUOUS scans with the Analog In Scan control, you will need to allocate a minimum of four times that shown in the table above.

For example, using the Analog In Scan control to run a CONTINUOUS scan of one channel at 18 MHz will require a minimum scan Count Per Channel of 262,144 samples, but will require at least 2048 KB (= 4*262144/512 KB) of contiguous memory.

The Analog In PreTrigger control may require more contiguous memory than listed in the prior table. When the Analog In PreTrigger control is run, it allocates a buffer that will hold 512 samples larger than requested by the user. As a consequence, when contiguous memory is required for the scan, the Analog In PreTrigger control will require an extra 4-KB worth of contiguous memory be allocated.

For example, using the Analog In PreTrigger control to run a scan with one channel at 18 MHz requires a minimum count per channel of 262,144 samples, and at least 516 KB (= 512 KB + 4 KB) of contiguous memory.

PCI-DAS64/Mx/16 Series

Analog input

Analog input functions and methods supported

UL:	cbAIn(), cbAInScan(), cbATrig(), cbAPretrig(), cbFileAInScan(), cbFilePretrig(), cbALoadQueue()
UL for .NET:	AIn(), AInScan(), ATrig(), APretrig(), FileAInScan(), FilePretrig(), ALoadQueue()

Analog input argument values

Options	BACKGROUND, CONTINUOUS, EXTCLOCK, CONVERTDATA, SINGLEIO, DMAIO, BLOCKIO, BURSTMODE, EXTTRIGGER
HighChan	0 to 63 in single-ended mode, 0 to 31 in differential mode
Rate	PCI-DAS64/M3/16 Single-channel, Single-range: Up to 3000000 Multi-channel, Single-range: Up to 1500000 Channel/Gain Queue: Up to 750000 PCI-DAS64/M2/16 Single-channel, Single-range: Up to 2000000 Multi-channel, Single-range: Up to 1500000 Channel/Gain Queue: Up to 750000 PCI-DAS64/M1/16 Single-channel, Single-range: Up to 1000000 Multi-channel, Single-range: Up to 1000000 Channel/Gain Queue: Up to 750000
Range	BIP5VOLTS (±5 V) UNI5VOLTS (0-5 V) BIP2PT5VOLTS (±2.5 V) UNI2PT5VOLTS (0-2.5 V) BIP1PT25VOLTS (±1.25 V) UNI1PT25VOLTS (0-1.25 V) BIPP625VOLTS (±.625 V)

Analog output

Analog output functions and methods supported

UL:	cbAOut(), cbAOutScan()
UL for .NET:	AOut(), AOutScan()

Analog output argument values

Options	BACKGROUND, CONTINUOUS, EXTCLOCK, SIMULTANEOUS
HighChan	1 max
Rate	Up to 100000
Range	BIP5VOLTS
DataValue	0 to 65535 (Refer to " 16-bit values using a signed integer data type " on page 8 for information on 16-bit values using unsigned integers.)

Digital I/O

Digital I/O functions and methods supported

UL:	cbDOut (), cbDIn (), cbDBitIn (), cbDBitOut (), cbDConfigPort ()
UL for .NET:	DOut (), DIn (), DBitIn (), DBitOut (), DConfigPort ()

Digital I/O argument values

PortNum	FIRSTPORTA, FIRSTPORTB, FIRSTPORTCL, FIRSTPORTCH, AUXPORT
DataValue	0 to 15 for FIRSTPORTCL or FIRSTPORTCH or AUXPORT 0 to 255 for FIRSTPORTA or FIRSTPORTB
BitNum	0 to 23 for FIRSTPORTA 0 to 3 for AUXPORT

Counter I/O

Counter functions and methods supported

UL:	cbC8254Config (), cbCIn (), cbCLoad ()
UL for .NET:	C8254Config (), CIn (), CLoad ()

Counter argument values

CounterNum	1
Config	HIGHONLASTCOUNT, ONSHOT, RATEGENERATOR, SQUAREWAVE, SOFTWARESTROBE, HARDWARESTROBE
LoadValue	0 to 65535 (Refer to " 16-bit values using a signed integer data type " on page 8 for information on 16-bit values using unsigned integers.)
RegNum:	LOADREG1

Triggering

Trigger functions and methods supported

UL:	cbSetTrigger ()
UL for .NET:	SetTrigger ()

Trigger argument values

TrigType	TRIGPOSEDGE, TRIGNEGEDGE, TRIGABOVE, TRIGBELOW, GATEHIGH, GATELOW, GATENEGHYS, GATEPOSHYS, GATEABOVE, GATEBELOW, GATEINWINDOW, GATEOUTWINDOW
Threshold	0 to 65535 (Refer to " 16-bit values using a signed integer data type " on page 8 for information on 16-bit values using unsigned integers.)

Event notification

Event notification functions and methods supported

UL:	cbEnableEvent (), cbDisableEvent ()
UL for .NET:	EnableEvent (), DisableEvent ()

Event notification argument values

EventType	ON_SCAN_ERROR, ON_PRETRIGGER, ON_DATA_AVAILABLE, ON_END_OF_AI_SCAN, ON_END_OF_AO_SCAN
-----------	---

Hardware considerations

Pacing analog input

- Hardware pacing, external or internal clock supported.
- The clock edge used to trigger acquisition for the external pacer may be rising or falling and is selectable using *InstaCal*.
- The packet size is 512 samples.

Analog Input configuration

The analog input mode may be 32 channel differential or 64 channel single-ended and may be selected using *InstaCal*.

Analog Input options

Except for SINGLEIO transfers, CONTINUOUS mode scans require enough memory for half FIFO of memory.

Triggering and gating

Digital (TTL) hardware triggering supported. Use the A/D Start Trigger Input (pin 55) for triggering and gating with `cbAInScan()` and `cbFileAInScan()` / `AInScan()` and `FileAInScan()`. Use the A/D Stop Trigger Input (pin 54) for `cbAPretrig()` and `cbFilePretrig()` / `APretrig()` and `FilePretrig()`.

Analog hardware triggering and gating are supported. `cbSetTrigger()` / `SetTrigger()` are supported for TRIGABOVE, TRIGBELOW, GATENEGHYS, GATEPOSHYS, GATEABOVE, GATEBELOW, GATEINWINDOW, GATEOUTWINDOW. Use the Analog Trigger Input (pin 56) for analog triggering. Analog thresholds are set relative to the ± 5 V range. For example: a threshold of 0 equates to -5 V, and a threshold of 65535 equates to +4.999847 V.

When using analog trigger feature, one or both of the DACs are used to set the threshold and are unavailable for other functions. If the trigger function requires a single reference (GATEABOVE, GATEBELOW, TRIGABOVE, TRIGBELOW) then DAC0 is available. If the trigger function requires two references (GATEINWINDOW, GATEOUTWINDOW, GATENEGHYS, GATEPOSHYS) then neither DAC is available for other functions.

Caution! Gating should NOT be used with BURSTMODE scans.

Pacing analog output

- Hardware pacing, external or internal clock supported.
- The clock edge used to trigger analog output updates for the external pacer may be rising or falling and is selectable using *InstaCal*.
- `EventData` for ON_PRETRIGGER events may not be accurate. In general, this value will be below the actual number of pretrigger samples available in the buffer.

These boards support concurrent analog input and output scans. That is, these boards allow for operations of analog input functions and methods (`cbAInScan()` and `cbAPretrig()` / `AInScan()` and `APretrig()`) and analog output functions and methods (`cbAOutScan()` / `AOutScan()`) to overlap without having to call `cbStopBackground()` between the start of input and output scans.

Output pin 59 configuration

Pin 59 may be configured as the DAC Pacer Output, SSH Output with hold configured as high level, or SSH Output with hold configured as low level. These options are selected via *InstaCal*

PCI- and CIO-DAS6402 and DAS3202 Series

Analog Input

Analog input functions and methods supported

UL: cbAIn (), cbAInScan (), cbATrig (), cbAPretrig (), cbFileAInScan (),
 cbFilePretrig ()

For **PCI-Versions**, the following function also applies:
 cbALoadQueue ()

UL for .NET: AIn (), AInScan (), ATrig (), APretrig (), FileAInScan (), FilePretrig ()

For **PCI-Versions**, the following method also applies:
 ALoadQueue ()

Analog input argument values

Options	BACKGROUND, CONTINUOUS, EXTCLOCK, CONVERTDATA, SINGLEIO, BLOCKIO, BURSTMODE, EXTTRIGGER		
HighChan	PCI-DAS6402 and CIO-DAS6402 0 to 63 in single-ended mode, 0 to 31 in differential mode		
	PCI-DAS3202 0 to 31		
Rate	CIO-DAS6402/12 Up to 330000	CIO-DAS6402/16 Up to 100000	All others Up to 200000
Range	BIP10VOLTS BIP5VOLTS BIP2PT5VOLTS BIP1PT25VOLTS	UNI10VOLTS UNI5VOLTS UNI2PT5VOLTS UNI1PT25VOLTS	

Analog output

Analog output functions and methods supported

UL: cbAOut (), cbAOutScan ()

UL for .NET: AOut (), AOutScan ()

Analog output argument values

Options	SIMULTANEOUS	
	For PCI Versions , the following argument values are also valid: BACKGROUND, EXTCLOCK, CONTINUOUS	
HighChan	1 max	
Rate	PCI Versions Up to 100000	CIO Versions Ignored
Range	PCI Versions, CIO-DAS6402/12 BIP10VOLTS BIP5VOLTS UNI10VOLTS UNI5VOLTS	CIO-DAS6402/16 Ignored

DataValue 0 to 4095

For PCI-DAS6402/16, PCI-DAS3202/16, CIO-DAS6402/16, the following additional argument values are also valid: 0 to 65535 (Refer to "[16-bit values using a signed integer data type](#)" on page 8 for information on 16-bit values using unsigned integers.)

Digital I/O

Digital I/O functions and methods supported

UL: cbDOut (), cbDIn (), cbDBitIn (), cbDBitOut ()

For PCI- Versions, the following additional function is also valid:
cbDConfigPort ()

UL for .NET: DOut (), DIn (), DBitIn (), DBitOut ()

For PCI- Versions, the following additional method is also valid:
DConfigPort ()

Digital I/O argument values

PortNum AUXPORT*

DataValue 0 to 15

BitNum 0 to 3

* AUXPORT is not configurable for these boards.

For PCI- Versions, the following additional argument values are also valid:

PortNum FIRSTPORTA, FIRSTPORTB, FIRSTPORTCL, FIRSTPORTCH

DataValue 0 to 15 for PORTCL or PORTCH;
0 to 255 for PORTA or PORTB

BitNum 0 to 23 for FIRSTPORTA

Counter I/O

Counter functions and methods supported

UL: cbC8254Config (), cbCIn (), cbCLoad ()

UL for .NET: C8254Config (), CIn (), CLoad ()

Counter argument values

CounterNum 1

Config HIGHONLASTCOUNT, ONESHOT, RATEGENERATOR, SQUAREWAVE, SOFTWARESTROBE,
HARDWARESTROBE

LoadValue 0 to 65535 (Refer to "[16-bit values using a signed integer data type](#)" on page 8 for information on 16-bit values using unsigned integers.)

RegNum: LOADREG1

Triggering

Trigger functions and methods supported

UL: cbSetTrigger ()

UL for .NET: SetTrigger ()

Trigger argument values

TrigType TRIGPOSEDGE, TRIGNEGEDGE, GATEHIGH, GATELOW

For **PCI- versions**, the following additional argument values are also valid:
TRIGABOVE, TRIGBELOW, GATENEHYS, GATEPOSHYS, GATEABOVE, GATEBELOW,
GATEINWINDOW, GATEOUTWINDOW

Threshold 0 to 4095

For **/16 versions** the following argument values are also valid:
0 to 65535 (Refer to "[16-bit values using a signed integer data type](#)" on page 8 for
information on 16-bit values using unsigned integers).

Event notification

Event notification functions and methods supported (PCI versions Only)

UL: cbEnableEvent (), cbDisableEvent ()

UL for .NET: EnableEvent (), DisableEvent ()

Event notification argument values

EventType ON_SCAN_ERROR, ON_PRETRIGGER, ON_DATA_AVAILABLE, ON_END_OF_AI_SCAN,
ON_END_OF_AO_SCAN

Hardware considerations

Pacing Analog input

Hardware pacing, external or internal clock supported. The packet size is 512 samples for **CIO versions**, and 2048 for **PCI versions**.

Triggering and gating

Digital (TTL) hardware triggering supported. The **PCI version** also supports analog hardware triggering. Analog thresholds are set relative to the ± 10 V range. For example, a threshold of 0 equates to -10 V and a threshold of 65535 equates to +9.999695 V.

When using the UL functions `cbAPretrig()` or `cbFilePretrig()` (or the UL for .NET methods `APretrig()` or `FilePretrig()`) on the **PCI-DAS6402/16** or **PCI-DAS3202/16**, use the A/D Stop Trigger In (pin 47) input to supply the trigger.

When using both `EXTCLOCK` and `BURSTMODE` on the **PCI-DAS6402/16** or **PCI-DAS3202/16**, use the A/D Start Trigger In (pin 45) input to supply the clock and not the A/D External Pacer (pin 42). Since `BURSTMODE` is actually paced by the internal burst clock, specifying `EXTCLOCK` when using `BURSTMODE` is equivalent to specifying `EXTTRIGGER`.

When using analog trigger feature, one or both of the DACs are used to set the threshold and are unavailable for other functions. If the trigger function requires a single reference (`GATEABOVE`, `GATEBELOW`, `TRIGABOVE`, `TRIGBELOW`) then DAC0 is available. If the trigger function requires two references (`GATEINWINDOW`, `GATEOUTWINDOW`, `GATENEHYS`, `GATEPOSHYS`), then neither DAC is available for other functions.

Caution! Gating should NOT be used with `BURSTMODE` scans.

Gain queue

When using the UL function `cbALoadQueue()` or the UL for .NET method `ALoadQueue()` with the **PCI version**, up to 8k elements can be loaded into the queue.

Pacing analog output

CIO Version: Software only

PCI Version: Hardware pacing, external or internal clock supported.

Output pin 49 configuration

On the **PCI version**, pin 49 may be configured as the DAC Pacer Output, SSH Output with hold configured as high level or SSH Output with hold configured as low level. These options are selected via *InstaCal*

Event notification:

The **PCI- versions** of these boards support concurrent analog input and output scans. That is, these boards allow for operations of analog input functions (`cbAInScan()` and `cbAPretrig()`) and analog output functions (`cbAOutScan()`) to overlap without having to call `cbStopBackground()` between the start of input and output scans. Equivalent UL for .NET methods are `AInScan()`, `APretrig()`, `AOutScan()` and `StopBackground()`.

PCI-DAS1602, PCI-DAS1200 & PCI-DAS1000 Series

Analog input

Analog input functions and methods supported

UL:	cbAIn (), cbAInScan (), cbATrig (), cbAPretrig (), cbFileAInScan (), cbFilePretrig ()
UL for .NET:	AIn (), AInScan (), ATrig (), APretrig (), FileAInScan (), FilePretrig ()

Analog input argument values

Options	BACKGROUND, CONTINUOUS, EXTCLOCK, CONVERTDATA, SINGLEIO, BLOCKIO, BURSTMODE, EXTTRIGGER
HighChan	0 to 15 in single-ended mode, 0 to 7 in differential mode
Rate	PCI-DAS1602/12, PCI-DAS1200, PCI-DAS1200/JR Up to 330000 PCI-DAS1000 Up to 250000 PCI-DAS1602/16, PCI-DAS1002 Up to 200000 PCI-DAS1001 Up to 150000
Range	PCI-DAS1602/12, PCI-DAS1602/16, PCI-DAS1200, PCI-DAS1200Jr, PCI-DAS1002, PCI-DAS1000 BIP10VOLTS UNI10VOLTS BIP5VOLTS UNI5VOLTS BIP2PT5VOLTS UNI2PT5VOLTS BIP1PT25VOLTS UNI1PT25VOLTS PCI-DAS1001 BIP10VOLTS UNI10VOLTS BIP1VOLTS UNI1VOLTS BIPPT1VOLTS UNIPT1VOLTS BIPPT01VOLTS UNIPT01VOLTS

Analog output

Excludes **PCI-DAS1200Jr**.

Analog output functions and methods supported

UL:	cbAOut (), cbAOutScan ()
UL for .NET:	AOut (), AOutScan ()

Analog output argument values

Options	SIMULTANEOUS		
	For PCI-DAS1602 Series , the following argument values are also valid: BACKGROUND, CONTINUOUS, EXTCLOCK		
HighChan	0 to 1		
Rate	PCI-DAS1602/16 Up to 100000	PCI-DAS1602/12 Up to 250000	All others Ignored

Range	BIP10VOLTS BIP5VOLTS	UNI10VOLTS UNI5VOLTS
DataValue	0 to 4095	

For **PCI-DAS1602/16**, the following argument values are also valid: 0 to 65535 (Refer to "[16-bit values using a signed integer data type](#)" on page 8 for information on 16-bit values using unsigned integers.)

Digital I/O

Digital I/O functions and methods supported

UL:	cbDOut (), cbDIn (), cbDBitIn (), cbDBitOut (), cbDConfigPort ()
UL for .NET:	DOut (), DIn (), DBitIn (), DBitOut (), DConfigPort ()

Digital I/O argument values

PortNum	FIRSTPORTA, FIRSTPORTB, FIRSTPORTCL, FIRSTPORTCH
DataValue	0 to 15 for PORTCL or PORTCH 0 to 255 for PORTA or PORTB
BitNum	0 to 23 for FIRSTPORTA

Counter I/O

Counter functions and methods supported

UL:	cbC8254Config (), cbCIn (), cbCLoad ()
UL for .NET:	C8254Config (), CIn (), CLoad ()

Counter argument values

CounterNum	4 to 6
Config	HIGHONLASTCOUNT, ONESHOT, RATEGENERATOR, SQUAREWAVE, SOFTWARESTROBE, HARDWARESTROBE
LoadValue	0 to 65535 (Refer to " 16-bit values using a signed integer data type " on page 8 for information on 16-bit values using unsigned integers.)
RegNum:	LOADREG4, LOADREG5, LOADREG6

Triggering

PCI-DAS1602/16 and PCI-DAS1602/12 only

Trigger functions and methods supported

UL:	cbSetTrigger ()
UL for .NET:	SetTrigger ()

Trigger argument values

TrigType	TRIGPOSEDGE, TRIGNEGEDGE, TRIGABOVE, TRIGBELOW, GATEHIGH, GATELOW, GATENEHYS, GATEPOSHYS, GATEABOVE, GATEBELOW, GATEINWINDOW, GATEOUTWINDOW
Threshold	PCI-DAS1602/16: 0 to 65535 PCI-DAS1602/12: 0 to 4095

Event notification

Event notification functions and methods supported

PCI Versions Only

UL: cbEnableEvent (), cbDisableEvent ()

UL for .NET: EnableEvent (), DisableEvent ()

Event notification argument values

EventType ON_SCAN_ERROR, ON_PRETRIGGER, ON_DATA_AVAILABLE, ON_END_OF_AI_SCAN

For **PCI-DAS1602/16** and **PCI-DAS1602/12** the following argument values are also valid:

ON_END_OF_AO_SCAN

Hardware considerations

Pacing analog input

Hardware pacing, external or internal clock supported.

The clock edge used to trigger acquisition for the external pacer may be *rising* or *falling*, and is selectable using *InstaCal*.

For the **PCI-DAS1602/16**, the packet size is 256 samples. All others in this series have a packet size of 512 samples.

Analog input configuration

The analog input mode is selectable via *InstaCal* for either 8-channel differential or 16-channel single-ended.

Triggering and gating - PCI-DAS1602 Series

Digital (TTL) and analog hardware triggering supported.

Analog thresholds are set relative to the ± 10 V range. For example: a threshold of 0 equates to -10 V. Thresholds of 65535 and 4095 correspond to +9.999695 and +9.995116 V for the 16-bit and 12-bit boards, respectively.

When using analog trigger feature, one or both of the DACs are unavailable for other functions. If the trigger function requires a single reference (*GATE_ABOVE*, *GATE_BELOW*, *TRIGABOVE*, and *TRIGBELOW*), DAC0 is available. If the trigger function requires two references (*GATE_IN_WINDOW*, *GATE_OUT_WINDOW*, *GATE_NEG_HYS* and *GATE_POS_HYS*), neither DAC is available for other functions.

Triggering and gating - PCI-DAS1200, PCI-DAS1000 Series

Digital (TTL) hardware triggering supported.

Concurrent operations - PCI-DAS1602 Series

Concurrent analog input and output scans supported. That is, PCI-DAS1602 Series boards allow for operations of analog input functions (*cbAInScan ()* and *cbAPretrig ()*) and analog output functions (*cbAOutScan ()*) to overlap without having to call *cbStopBackground ()* between the start of input and output scans. Equivalent UL for .NET methods are *AInScan ()*, *APretrig ()*, *AOutScan ()*, and *StopBackground ()*.

Pacing analog output - PCI-DAS1602 Series

Hardware pacing, external or internal clock supported.

The clock edge used to trigger analog output updates for the external pacer may be rising or falling and is selectable using *InstaCal*.

Counters

The source for counter 4 may be internal or external and is selectable using *InstaCal*.

Although counters 4, 5 and 6 are programmable through the counter functions, the primary purpose for some of these counters may conflict with these functions.

Potential conflicts include:

- **PCI-DAS1200, PCI-DAS1000** Series: Counters 5 and 6 are always available to the user. Counter 4 is used as a residual counter by some of the analog input functions and methods.
- **PCI-DAS1602** Series: Counters 5 and 6 are used as DAC pacers by some analog output functions and methods. Counter 4 is used as a residual counter by some of the analog input functions and methods.

PCIM-DAS1602 and PCIM-DAS16JR Series

Analog input

Analog input functions and methods supported

UL: cbAIn (), cbAInScan (), cbFileAInScan (), cbATrig ()

UL for .NET: AIn (), AInScan (), FileAInScan (), ATrig ()

Analog input argument values

Options BACKGROUND, CONTINUOUS, EXTCLOCK, CONVERTDATA, SINGLEIO, BLOCKIO, BURSTMODE, EXTTRIGGER

HighChan 0 to 15 in single-ended mode, 0 to 7 in differential mode

Rate 100000

Range	BIP10VOLTS	UNI10VOLTS
	BIP5VOLTS	UNI5VOLTS
	BIP2PT5VOLTS	UNI2PT5VOLTS
	BIP1PT25VOLTS	UNI1PT25VOLTS

Analog output (PCIM-DAS1602/16 only)

Analog output functions and methods supported

UL: cbAOut (), cbAOutScan ()

UL for .NET: AOut (), AOutScan ()

Analog output argument values

Options Ignored

HighChan 1 max

Count 2

Rate Ignored

Range Ignored

DataValue 0 to 4095

Digital I/O

Digital I/O functions and methods supported

UL: cbDOut (), cbDIn (), cbDBitIn (), cbDBitOut ()

UL for .NET: DOut (), DIn (), DBitIn (), DBitOut ()

The PCIM-DAS1602/16 also supports:

UL: cbDConfigPort ()

UL for .NET: DConfigPort ()

Digital I/O argument values

PortNum: AUXPORT*

The PCIM-DAS1602/16 also supports:

PortNum: FIRSTPORTA, FIRSTPORTB, FIRSTPORTCL, FIRSTPORTCH

DataValue: 0 to 15 FIRSTPORTCL, FIRSTPORTCH or AUXPORT*

0 to 255 for FIRSTPORTA or FIRSTPORTB

BitNum: 0 to 23 for FIRSTPORTA

0 to 3 for AUXPORT*

*AUXPORT is not configurable for these boards.

Counter I/O**Counter functions and methods supported**

UL: cbC8254Config(), cbCIn(), cbCLoad()

UL for .NET: C8254Config(), CIn(), CLoad()

Counter argument values

CounterNum 1 to 3

Config HIGHONLASTCOUNT, ONSHOT, RATEGENERATOR, SQUAREWAVE, SOFTWARESTROBE, HARDWARESTROBE

LoadValue 0 to 65535 (Refer to "[16-bit values using a signed integer data type](#)" on page 8 for information on 16-bit values using unsigned integers.)

RegNum: LOADREG1, LOADREG2, LOADREG3

Event notification**Event notification functions and methods supported**

UL: cbEnableEvent(), cbDisableEvent()

UL for .NET: EnableEvent(), DisableEvent()

Event notification argument values

EventType ON_SCAN_ERROR, ON_DATA_AVAILABLE, ON_END_OF_AI_SCAN

Triggering**Trigger functions and methods supported**

UL: cbSetTrigger()

UL for .NET: SetTrigger()

Trigger argument values

TrigType TRIGPOSEEDGE, TRIGNEGEDGE, GATEHIGH, GATELOW

Hardware considerations**Pacing analog input**

Hardware pacing, external or internal clock supported.

Analog input ranges

For the **PCIM-DAS1602/16**, the A/D ranges are configured with a combination of a switch (Unipolar / Bipolar) and a programmable gain code. The state of this switch is set in the configuration file using *InstaCal*. After the UNI/BIP switch setting is selected, only matching ranges can be used in Universal Library programs.

Triggering and gating

Digital (TTL) hardware triggering supported.

Pacing analog output

Software pacing only

CIO-DAS800 Series

Analog input

Analog input functions and methods supported

UL: cbAIn (), cbAInScan (), cbATrig (), cbFileAInScan ()
 UL for .NET: AIn (), AInScan (), ATrig (), FileAInScan ()

Analog input argument values

Options BACKGROUND, CONTINUOUS, EXTCLOCK, CONVERTDATA, SINGLEIO, BLOCKIO, EXTTRIGGER

HighChan 0 to 7

Rate **CIO-DAS802/16**
 100000

All others in series
 50,000

Range **CIO-DAS800**
 Range is not programmable so the Range argument is ignored.

CIO-DAS801 supports the following A/D ranges

BIP10VOLTS	UNI10VOLTS
BIP5VOLTS	UNI1VOLTS
BIP1VOLTS	UNIPT1VOLTS
BIPPT5VOLTS	UNIPT01VOLTS
BIPPT05VOLTS	
BIPPT01VOLTS	

CIO-DAS802 supports the following A/D ranges

BIP10VOLTS	UNI10VOLTS
BIP5VOLTS	UNI5VOLTS
BIP2PT5VOLTS	UNI2PT5VOLTS
BIP1PT25VOLTS	UNI1PT25VOLTS
BIPPT625VOLTS	

CIO-DAS802/16 supports the following A/D ranges

BIP10VOLTS	UNI10VOLTS
BIP5VOLTS	UNI5VOLTS
BIP2PT5VOLTS	UNI2PT5VOLTS
BIP1PT25VOLTS	UNI1PT25VOLTS

Analog Output

These boards do not have D/A converters and do not support analog output functions.

Digital I/O

Digital I/O functions and methods supported

UL: cbDOut (), cbDIn (), cbDBitIn (), cbDBitOut ()
 UL for .NET: DOut (), DIn (), DBitIn (), DBitOut ()

Digital I/O argument values

PortNum AUXPORT (not configurable for these boards)

DataValue cbDOut () cbDIn ()
 0 to 15 0 to 7

BitNum	cbDOut ()	cbDIn ()
	0 to 3	0 to 2

Counter I/O

Counter functions and methods supported

UL:	cbC8254Config (), cbCIn (), cbCLoad ()
UL for .NET:	C8254Config (), CIn (), CLoad ()

Counter argument values

CounterNum	1 to 3
Config	HIGHONLASTCOUNT, ONESHOT, RATEGENERATOR, SQUAREWAVE, SOFTWARESTROBE, HARDWARESTROBE
LoadValue	0 to 65535 (Refer to " 16-bit values using a signed integer data type " on page 8 for information on 16-bit values using unsigned integers.)
RegNum:	LOADREG1, LOADREG2, LOADREG3

Hardware considerations

Pacing analog input

Hardware pacing, external or internal clock supported.

The packet size is 128 samples. Note that digital output is not compatible with concurrent `cbAInScan () / AInScan ()` operation, since the channel multiplexer control shares the register with the digital output control. Writing to this register during a scan may adversely affect the scan.

Triggering and gating

Digital hardware triggering supported.

CIO-, PCI-, and PC104-DAS08 Series

Analog input

Analog input functions and methods supported

UL: cbAIn(), cbAInScan(), cbATrig(), cbFileAInScan()

UL for .NET: AIn(), AInScan(), ATrig(), FileAInScan()

Analog input argument values

Options BACKGROUND, CONTINUOUS, EXTCLOCK, CONVERTDATA, SINGLEIO, EXTTRIGGER

HighChan 0 to 7

Rate From 63 up to 50000 (Refer to the "[Sampling Rate using SINGLEIO](#)" on page 29.)

Range **DAS08 series**
 Since the **DAS08** series does not have programmable gain, the Range arguments for the analog input functions are ignored.

PCI-DAS08

BIP5VOLTS (±5 V)

CIO-DAS08 and PC104-DAS08

BIP10VOLTS UNI10VOLTS
 BIP5VOLTS

CIO-DAS08-PGH and CIO-DAS08-AOH

BIP10VOLTS UNI10VOLTS
 BIP5VOLTS UNI1VOLTS
 BIP1VOLTS UNIPT1VOLTS
 BIPPT5VOLTS UNIPT01VOLTS
 BIPPT1VOLTS BIPPT01VOLTS
 BIPPT05VOLTS BIPPT005VOLTS

CIO-DAS08-PGL and CIO-DAS08-AOL

BIP10VOLTS UNI10VOLTS
 BIP5VOLTS UNI5VOLTS
 BIP2PT5VOLTS UNI2PT5VOLTS
 BIP1PT25VOLTS UNI1PT25VOLTS
 BIPPT625VOLTS

CIO-DAS08-PGM and CIO-DAS08-AOM

BIP10VOLTS UNI10VOLTS
 BIP5VOLTS UNI1VOLTS
 BIPPT5VOLTS UNIPT1VOLTS
 BIPPT1VOLTS UNIPT01VOLTS
 BIPPT05VOLTS

Analog output

AO, -AOH, -AOM, -AOL versions only

Analog output functions and methods supported

UL: cbAOut(), AOutScan()

UL for .NET: AOut(), AOutScan()

Analog output argument values

Options SIMULTANEOUS

HighChan 1 max

Rate Ignored

Count	2 max
Range	Ignored
DataValue	0 to 4095

Digital I/O

Digital I/O functions and methods supported

UL: cbDOut (), cbDIn (), cbDBitIn (), cbDBitOut ()

UL for .NET: DOut (), DIn (), DBitIn (), DBitOut ()

For **CIO-DAS08** and **CIO-DAS08-AOx**, the following function and method is also supported:

UL: cbDConfigPort ()

UL for .NET: DConfigPort ()

Digital I/O argument values

PortNum AUXPORT

DataValue 0 to 15 using cbDOut () or DOut ()

0 to 7 using cbDIn () or DIn ()

BitNum 0 to 3 using cbDBitOut () or DBitOut ()

0 to 2 using cbDBitIn () or DBitIn ()

For **CIO-DAS08** and **CIO-DAS08-AOx** the following argument values are also valid:

FIRSTPORTA, FIRSTPORTB, FIRSTPORTCL, FIRSTPORTCH

PortNum 0 to 15 for FIRSTPORTCL or FIRSTPORTCH

0 to 255 for FIRSTPORTA or FIRSTPORTB

DataValue 0 to 15 for FIRSTPORTCL or FIRSTPORTCH

0 to 255 for FIRSTPORTA or FIRSTPORTB

BitNum 0 to 23 for FIRSTPORTA

Counter I/O

Counter functions and methods supported

UL: cbC8254Config (), cbCIn (), cbCLoad ()

UL for .NET: C8254Config (), CIn (), CLoad ()

Counter argument values

CounterNum 1 to 3

Config HIGHONLASTCOUNT, ONESHOT, RATEGENERATOR, SQUAREWAVE, SOFTWARESTROBE, HARDWARESTROBE

LoadValue 0 to 65535 (Refer to "[16-bit values using a signed integer data type](#)" on page 8 for information on 16-bit values using unsigned integers.)

RegNum: LOADREG1, LOADREG2, LOADREG3

Hardware considerations

Pacing analog input

Hardware pacing, external or internal clock supported.

Before using the `cbAInScan()` function or the `AInScan()` method for timed analog input with a **CIO-** or **PC104-** series board, the output of counter 1 must be wired to the Interrupt input; if you have a **CIO-DAS08** board revision 3 or higher, a jumper is provided on the board to accomplish this. An interrupt level must have been selected in *InstaCal* and the *CB.CFG* file saved.

Triggering and gating

Digital (TTL) polled digital input triggering supported. Refer to "[Trigger support](#)" on page 28.

Pacing analog output

Software pacing only

CIO-DAS08/Jr and CIO-DAS08/Jr/16 Series

Analog Input

Analog input functions and methods supported

UL:	cbAIn(), cbAInScan(), cbATrig(), cbFileAInScan()
UL for .NET:	AIn(), AInScan(), ATrig(), FileAInScan()

Analog input argument values

Options	CONVERTDATA
HighChan	0 to 7
Rate	Ignored
Range	Since these boards do not have programmable gain, the Range arguments for the analog input functions are ignored.

Analog output

(If optional D/A converters are installed)

Analog output functions and methods supported

UL:	cbAOut(), cbAOutScan()
UL for .NET:	AOut(), AOutScan()

Analog output argument values

Options	SIMULTANEOUS
HighChan	1 max
Rate	Ignored
Count	2 max
Range	Ignored
DataValue	0 to 4095

For CIO-DAS08/Jr/16-AO, the following argument values are also valid:
0 to 65535 (Refer to "[16-bit values using a signed integer data type](#)" on page 8 for information on 16-bit values using unsigned integers.)

Digital I/O

Digital I/O functions and methods supported

UL:	cbDOut(), cbDIn(), cbDBitIn(), cbDBitOut()
UL for .NET:	DOut(), DIn(), DBitIn(), DBitOut()

Digital I/O argument values

PortNum	AUXPORT*
DataValue	0 to 255
BitNum	0 to 7

* AUXPORT is not configurable for these boards.

Counter I/O

Counter functions and methods supported

None

Hardware considerations

Pacing analog input

Software pacing only

PCM-DAS08

Analog Input

Analog input functions and methods supported

UL:	cbAIn(), cbAInScan(), cbATrig(), cbFileAInScan()
UL for .NET	AIn(), AInScan(), ATrig(), FileAInScan()

Analog input argument values

Options	BACKGROUND, CONTINUOUS, EXTCLOCK, CONVERTDATA, SINGLEIO, NOTODINTS, EXTTRIGGER, NOCALIBRATEDATA
HighChan	0 to 7
Rate	25000 max. For other restrictions, refer to the PCM-DAS08 User's Manual at www.mccdaq.com/PDFmanuals/pcm-das08.pdf .
Range	This board does not have programmable gain so the Range argument to analog input functions is ignored.

Digital I/O

Digital I/O functions and methods supported

UL:	cbDIn(), cbDOut(), cbDBitIn(), cbDBitOut()
UL for .NET:	DIn(), DOut(), DBitIn(), DBitOut()

Digital I/O argument values

PortNum	AUXPORT
DataValue	0 to 7
BitNum	0 to 2

Hardware considerations

Pacing analog input

Internal or external clock

Maximizing sampling rates

When paced by the onboard clock, the rate is set by an onboard oscillator running at 25 kHz. The oscillator output may be divided by 2, 4 or 8, resulting in rates of 12.5 kHz, 6.25 kHz or 3.13 kHz. When pacing a single channel from the onboard clock, these are the four choices of rate available. When a rate is requested within the range of 3000 to 25000, the library selects the closest of the four available rates.

Scanning more than one channel divides the rate requested among the number of channels requested. The maximum rate when scanning eight channels is 3130 (25000 divided by eight channels).

Although the **PCM-DAS08** is capable of 25 kHz analog to digital conversions, not all computers in all configurations can transfer the converted samples fast enough to sustain a 25 kHz sample and transfer rate without missing some samples. This is especially true in the windows environment. Unfortunately, there isn't much you can do to improve sampling rates in windows, but in DOS, where you have more control over the process, you may be able to attain the full 25 kHz sampling rate.

Determining the maximum sampling rate in DOS

If you have installed the DOS version of the Universal Library, a utility program called `MAXRATE` is installed in the UL installation directory (C:\MCC by default). `MAXRATE` tests your computer and advise you of the maximum sustainable convert and transfer rate.

The maximum rate for your computer is reported for two conditions. The first is with all interrupts enabled, the second is with the time of day interrupt disabled (`TOD`). The convert and transfer rate with `TOD` disabled will usually be faster.

Time of Day interrupt and A/D conversions

Many TSR's and device drivers "hook" into the `TOD` interrupt. Using the `TOD` clock tick guarantees that every 1/18th of a second the routine will be woken up and can check status or do whatever the routine is designed to do. Unfortunately this can create considerable overhead in the `TOD` interrupt service routine and will introduce gaps in your sample data at high rates.

Using the `cbAInScan () / AInScan ()` option argument to turn off the `TOD` interrupt increases the speed that you can maintain with your **PCM-DAS08**. Turning off the `TOD` prevents your computer's clock from incrementing while `cbAInScan () / AInScan ()` is running. Your clock will lose time.

Transfer rate

Any rate below 5 kHz is sustainable with or without `TOD` interrupt enabled. If your maximum required rate is less than 5 kHz, then your computer can handle that. If the required rate is greater than 10K, run `MAXRATE`. Remember, we are discussing the **TOTAL** rate, not the per channel rate. If you want 3 channels at 5 kHz, the total rate is 15 kHz. Run `MAXRATE` to see if your computer is up to the task.

Background operation

`MAXRATE` tests your computer using the `cbAInScan () / AInScan ()` routine in the foreground. If you choose background operation, it may not sustain the maximum rate returned by `MAXRATE`. For the fastest performance, use `cbAInScan () / AInScan ()` in the foreground, with the `TOD` interrupt disabled.

PPIO-AI08

Analog Input

Analog input functions and methods supported

UL: cbAIn(), cbAInScan(), cbATrig(), cbFileAInScan()

UL for .NET: AIn(), AInScan(), ATrig(), FileAInScan()

Analog input argument values

Options CONVERTDATA

HighChan 0 to 7

Rate Ignored

Range This board does not have programmable gain, so the Range arguments for the analog input functions are ignored.

Digital I/O

Digital I/O functions and methods supported

UL: cbDOut(), cbDIn(), cbDBitIn(), cbDBitOut()

UL for .NET: DOut(), DIn(), DBitIn(), DBitOut()

Digital I/O argument values

PortNum AUXPORT*

DataValue cbDOut() cbDIn()
 0 to 15 0 to 7

BitNum cbDOut() cbDIn()
 0 to 3 0 to 2

* AUXPORT is not configurable for this board.

Hardware considerations

Pacing analog input

Software pacing only

CIO- and PC104-DAS16

Analog Input

Analog input functions and methods supported

UL: cbAIn(), cbAInScan(), cbATrig(), cbFileAInScan()

UL for .NET: AIn(), AInScan(), ATrig(), FileAInScan()

The **DAS16/330**, **DAS16/330i**, **DAS16/M1**, and **DAS16/M1/16** also support:

UL: cbAPretrig(), cbFileAInScan(), cbFilePretrig()

UL for .NET: APretrig(), FileAInScan(), FilePretrig()

The **DAS16/330i** and **DAS16/M1** also support:

UL: cbALoadQueue()

UL for .NET: cbALoadQueue()

Analog input argument values

Options BACKGROUND, CONTINUOUS, EXTCLOCK, CONVERTDATA, EXTTRIGGER

For **DAS16/330**, **DAS16/330i**, **DAS16/M1** and **DAS16/M1/16**, the following argument values are also valid:

DTCONNECT, BLOCKIO (packet size: 512), EXTMEMORY

For **DAS16**, **DAS16/F**, **DAS16/Jr**, **DAS16/Jr/16** and **PC104-DAS16Jr** series, the following argument values are also valid:

SINGLEEIO, DMAIO

For **DAS16/M1/16**, the following argument value is also valid:

BURSTMODE

HighChan **DAS16/M1** and **DAS16/M1/16**
0 to 7

All others

0 to 15 in single-ended mode, 0 to 7 in differential mode

Rate **DAS16/M1 & DAS16/M1/16** **DAS16/330 & 330i**
Up to 1000000 Up to 330000

PC104-DAS16Jr/12 **CIO-DAS16Jr**
Up to 160000 Up to 130000

DAS16/F & DAS16Jr/16 CIO-DAS16
Up to 100000 Up to 50000

Range **CIO-DAS16 & CIO-DAS16/F**

These boards do not have programmable gain so the Range argument to analog input functions is ignored.

All other boards in this series support the following ranges:

BIP5VOLTS	UNI10VOLTS
BIP2PT5VOLTS	UNI5VOLTS
BIP1PT25VOLTS	UNI2PT5VOLTS
	UNI1PT25VOLTS

For all programmable gain boards in this series **except** the **DAS16/M1/16**, the following argument value is also valid:

BIP10VOLTS

For all programmable gain boards in this series **except** the **CIO-DAS16Jr/16** and **PC104-DAS16Jr/16**, the following argument value is also valid:
BIPPT625VOLTS

Analog output

CIO-DAS16 & CIO-DAS16/F only

Analog output functions and methods supported

UL: cbAOut (), cbAOutScan ()
UL for .NET: AOut (), AOutScan ()

Analog output argument values

Options	SIMULTANEOUS
HighChan	1 max
Rate	Ignored
Count	2 max
Range	Ignored
DataValue	0 to 4095

Digital I/O

Digital I/O functions and methods supported

UL: cbDOut (), cbDIn (), cbDBitIn (), cbDBitOut ()
UL for .NET: DOut (), DIn (), DBitIn (), DBitOut ()

The **CIO-DAS16 & 16/F**, **CIO-DAS16/M1** and **CIO-DAS16/M1/16**, the following function is also supported:

UL: cbDConfigPort ()
UL for .NET: DConfigPort ()

Digital I/O argument values

PortNum	AUXPORT*
DataValue	0 to 15
BitNum	0 to 3

* AUXPORT is not configurable for these boards.

For **CIO-DAS16 & 16/F**, **CIO-DAS16/M1** and **CIO-DAS16/M1/16** the following additional argument values are also valid:

PortNum	FIRSTPORTA, FIRSTPORTB, FIRSTPORTCL, FIRSTPORTCH
DataValue	0 to 15 for FIRSTPORTCL or FIRSTPORTCH 0 to 255 for FIRSTPORTA or FIRSTPORTB
BitNum	0 to 23 for FIRSTPORTA

Counter I/O

Counter functions and methods supported

UL:	<code>cbC8254Config()</code> , <code>cbCIn()</code> , <code>cbCLoad()</code>
UL for .NET:	<code>C8254Config()</code> , <code>CIn()</code> , <code>CLoad()</code>

Counter argument values

CounterNum	1 to 3
	The CIO-DAS16/M1/16 also supports these argument values: 4 to 6
Config	HIGHONLASTCOUNT, ONESHOT, RATEGENERATOR, SQUAREWAVE, SOFTWARESTROBE, HARDWARESTROBE
LoadValue	0 to 65535 (Refer to " 16-bit values using a signed integer data type " on page 8 for information on 16-bit values using unsigned integers.)
RegNum:	LOADREG1, LOADREG2, LOADREG3
	For CIO-DAS16/M1/16 the following argument values are also valid LOADREG4, LOADREG5, LOADREG6

Triggering (CIO-DAS16/M1/16 only)

Trigger functions and methods supported

UL:	<code>cbSetTrigger()</code>
UL for .NET:	<code>SetTrigger()</code>

Trigger argument values

TrigType	TRIGPOSEDGE, TRIGNEGEDGE, GATEHIGH, GATELOW
Threshold	0 to 65535 (Refer to " 16-bit values using a signed integer data type " on page 8 for information on 16-bit values using unsigned integers.)

Hardware considerations

Pacing analog input

- Hardware pacing, external or internal clock supported.
- The packet size is 512 samples
- The DMAIO option cannot be used while using the chan/gain queue on the **DAS-330i** board.

CIO-DAS16/M1

If you use the timed analog functions with the **CIO-DAS16/M1** board to acquire more than 2048 data points, you may not be able to achieve the full 1 MHz rate. On slow machines, these functions may hang if the scan rate is fast, generally in the range of 500 to 700 kHz.

Determine the maximum rate by passing in different high rates until the maximum rate is achieved without hanging the system. If the full 1.0 MHz rate is required, add a **MEGA FIFO** memory board and specify the EXTMEMORY option on the call to `cbAInScan()` or `AInScan()`.

CIO-DAS16/M1/16 also supports counter numbers 4 through 6, with counter 4 being the only independent user counter.

Triggering and gating

- For the **CIO-DAS16/M1/16**, Digital (TTL) and analog hardware triggering is supported.
- For **all others in this series**, digital (TTL) polled gate triggering is supported. Refer to "[Trigger support](#)" on page 28

Pacing analog output

Software only

PCM- and PC-CARD-DAS16 Series

Analog Input

Analog input functions and methods supported

UL: cbAIn(), cbAInScan(), cbATrig(), cbFileAInScan()

UL for .NET: AIn(), AInScan(), ATrig(), FileAInScan()

Analog input argument values

Options BACKGROUND, CONTINUOUS*, EXTCLOCK, CONVERTDATA, SINGLEIO, BLOCKIO, EXTTIGGER, NOTODINTS, NOCALIBRATEDATA

The **PC-CARD-DAS16** series also supports BURSTMODE.

HighChan **DAS16/S and DAS16/330**

0 to 15

DAS16/D

0 to 7

Rate **DAS16/330**

330000

PC-CARD-DAS16/16

200000

All others in series

100000

Range For **DAS16x/12**, the following A/D ranges are valid:

BIP10VOLTS UNI10VOLTS

BIP5VOLTS UNI5VOLTS

BIP2PT5VOLTS UNI2PT5VOLTS

BIP1PT25VOLTS UNI1PT25VOLTS

For **DAS16x/16**, the following A/D ranges are valid:

BIP10VOLTS BIP5VOLTS

BIP2PT5VOLTS BIP1PT25VOLTS

For **DAS16/330**, the following A/D ranges are valid:

BIP10VOLTS BIP5VOLTS

Analog output

PCM-DAS16D/12AO and **PC-CARD-DAS16/xx-AO** only

Analog output functions and methods supported

UL: cbAOut(), cbAOutScan()

UL for .NET: AOut(), AOutScan()

Analog output argument values

Options SIMULTANEOUS (**PCM** version only)

HighChan 1 max

Rate	Ignored
Count	2 max
Range	BIP10VOLTS
	For PC-CARD-DAS16/12AO & PCM-DAS16D/12AO , the following argument values are also valid:
	BIP10VOLTS
	BIP5VOLTS
DataValue	0 to 4095
	For PC-CARD-DAS16/16AO , the following argument values are also valid:
	0 to 65535 (Refer to " 16-bit values using a signed integer data type " on page 8.)

Digital I/O

Digital I/O functions and methods supported

UL:	cbDOut (), cbDIn (), cbDBitIn (), cbDBitOut (), cbDConfigPort ()
UL for .NET:	DOut (), DIn (), DBitIn (), DBitOut (), DConfigPort ()

Digital I/O argument values

PortNum	PC-CARD-DAS16/xxAO FIRSTPORTA All others in this series: FIRSTPORTA, FIRSTPORTB
DataValue	PC-CARD-DAS16/xxAO 0 to 15 for FIRSTPORTA All others in this series: 0 to 15 for FIRSTPORTA or FIRSTPORTB
BitNum	PC-CARD-DAS16/xxAO 0 to 3 for FIRSTPORTA All others in this series 0 to 7 for FIRSTPORTA

Counter I/O

Counter functions and methods supported

UL:	cbC8254Config (), cbCIn (), cbCLoad ()
UL for .NET:	C8254Config (), CIn (), CLoad ()

Counter argument values

CounterNum	1 to 3
Config	HIGHONLASTCOUNT, ONESHOT, RATEGENERATOR, SQUAREWAVE, SOFTWARESTROBE, HARDWARESTROBE
LoadValue	0 to 65535 (Refer to " 16-bit values using a signed integer data type " on page 8 for information on 16-bit values using unsigned integers.)
RegNum:	LOADREG1, LOADREG2, LOADREG3

Triggering

PC-Card Only

Trigger functions and methods supported

UL: `cbSetTrigger()`

UL for .NET: `SetTrigger()`

Trigger argument values

TrigType `TRIGPOSEDGE, TRIGNEGEDGE, GATEHIGH, GATELOW` (All at A/D External trigger input)

Hardware considerations

Pacing analog input

- Internal or external clock
- The packet size is 256 samples for **PCM** boards; 2048 samples for **PC-CARD** boards.
For `CONTINUOUS` mode scans, the sample count should be at least one packet size (≥ 2048 samples) for the **PC-CARD-** boards.

These cards do not have residual counters, so `BLOCKIO` transfers must acquire integer multiples of the packet size before completing the scan. This can be lengthy for the **PC-CARDS** which must acquire 2048 samples between interrupts for `BLOCKIO` transfers. In general, it is best to allow the library to determine the best transfer mode (`SINGLEIO` vs. `BLOCKIO`) for these boards.

Triggering and gating

- External digital (TTL) polled gate trigger supported on **PCM** versions. Refer to "[Trigger support](#)" on page 28.
- External digital (TTL) hardware trigger supported on **PC-CARD** versions.

CIO-DAS1400 and CIO-DAS1600 Series

Analog Input

Analog input functions and methods supported

UL: cbAIn (), cbAInScan (), cbATrig (), cbFileAInScan ()

UL for .NET: AIn (), AInScan (), ATrig (), FileAInScan ()

Analog input argument values

Options BACKGROUND, CONTINUOUS, EXTCLOCK, CONVERTDATA, SINGLEIO, DMAIO, BURSTMODE, EXTTRIGGER

For **CIO-DAS1600**, the following argument values are also valid:

DTCONNECT, EXTMEMORY.

HighChan 0 to 15 in single-ended mode, 0 to 7 in differential mode

Rate **DAS1401/12, DAS1402/12, DAS1601/12, DAS1602/12**
160000

DAS1602/16, DAS1402/16

100000

DAS1401/12, DAS1402/12, DAS1601/12, DAS1602/12 to external memory
330000

Range **CIO-DAS1402, CIO-DAS1602, CIO-DAS1402/16 and CIO-DAS1602/16**

BIP10VOLTS	UNI10VOLTS
BIP5VOLTS	UNI5VOLTS
BIP2PT5VOLTS	UNI2PT5VOLTS
BIP1PT25VOLTS	UNI1PT25VOLTS

CIO-DAS1401 and CIO-DAS1601

BIP10VOLTS	UNI10VOLTS
BIP1VOLTS	UNI1VOLTS
BIPPT1VOLTS	UNIPT1VOLTS
BIPPT01VOLTS	UNIPT01VOLTS

Analog output (CIO-DAS1600 series only)

Analog output functions and methods supported

UL: cbAOut (), cbAOutScan ()

UL for .NET: AOut (), AOutScan ()

Analog output argument values

Options SIMULTANEOUS

HighChan 1 max

Count 2 max

Rate Ignored

Pacing Software pacing only

Range Analog output gain is not programmable, so the Range argument is ignored.

DataValue 0 to 4095

Digital I/O

Digital I/O functions and methods supported

UL: cbDOut (), cbDIn (), cbDBitIn (), cbDBitOut ()

UL for .NET: DOut (), DIn (), DBitIn (), DBitOut ()

For **DAS1600**, the following function and method are also valid:

UL: cbDConfigPort ()

UL for .NET: DConfigPort ()

Digital I/O argument values

PortNum AUXPORT*

DataValue 0 to 15

BitNum 0 to 3

* AUXPORT is not configurable for these boards.

For **DAS1600**, the following additional argument values are also valid:

PortNum FIRSTPORTA, FIRSTPORTB, FIRSTPORTCL, FIRSTPORTCH

DataValue 0 to 15 for FIRSTPORTCL or FIRSTPORTCH;
0 to 255 for FIRSTPORTA or FIRSTPORTB

BitNum 0 to 23 for FIRSTPORTA

Counter I/O

Counter functions and methods supported

UL: cbC8254Config (), cbCIn (), cbCLoad ()

UL for .NET: C8254Config (), CIn (), CLoad ()

Counter argument values

CounterNum 1 to 3

Config HIGHONLASTCOUNT, ONESHOT, RATEGENERATOR, SQUAREWAVE, SOFTWARESTROBE,
HARDWARESTROBE

LoadValue 0 to 65535 (Refer to "[16-bit values using a signed integer data type](#)" on page 8 for
information on 16-bit values using unsigned integers.)

RegNum: LOADREG1, LOADREG2, LOADREG3

Hardware considerations

Pacing analog input

Hardware pacing, external or internal clock supported.

Specifying SINGLEIO while also specifying BURSTMODE is not recommended. If this combination is used, the Count value should be set as low as possible, preferably to the number of channels in the scan. Otherwise, overruns may occur.

When EXTMEMORY is used with the **CIO-DAS1600** the cbGetStatus () function or GetStatus () method does not return the current count and current index. This is a limitation imposed by maintaining identical registers to the KM-DAS1600.

Triggering and gating

External digital (TTL) polled gate trigger supported. Refer to "[Trigger support](#)" on page 28.

Range

The **CIO-DAS1400** and **CIO-DAS1600** A/D ranges are configured with a combination of a switch (Unipolar / Bipolar) and a programmable gain code. The state of this switch is set in the configuration file using *InstaCal*. After the UNI/BIP switch setting is selected, only matching ranges can be used in Universal Library programs.

CIO-DAS48/PGA

Analog Input

Analog input functions and methods supported

UL: cbAIn(), cbAInScan(), cbATrig(), cbFileAInScan()

UL for .NET: AIn(), AInScan(), ATrig(), FileAInScan()

Analog input argument values

Options CONVERTDATA

HighChan 47 (23 differential)

Rate This board does not have a timer, so the Rate argument to the analog scanning functions is ignored.

Range The board may be configured with a jumper for either voltage or current input.

In voltage mode

BIP10VOLTS	UNI10VOLTS
BIP5VOLTS	UNI5VOLTS
BIP2PT5VOLTS	UNI2PT5VOLTS
BIP1PT25VOLTS	UNI1PT25VOLTS
BIPP625VOLTS	

In current mode

MA4TO20	MA2TO10
MA1TO5	MAP5TO2PT5

Analog output

Analog output functions and methods supported

The CIO-DAS48/PGA board does not support any of the analog output functions.

Digital I/O

Digital I/O functions and methods supported

The CIO-DAS48/PGA does not support any of the digital I/O functions.

Counter I/O

Counter functions and methods supported

The CIO-DAS48/PGA does not support any of the counter I/O functions.

DAS-TC Series

Temperature Input

Temperature input functions and methods supported

UL: `cbTIn()`, `cbTInScan()`

UL for .NET: `TIn()`, `TInScan()`

Temperature input argument values

Options `NOFILTER`

Scale `CELSIUS`, `FAHRENHEIT`, `KELVIN`

HighChan 0 to 15

Hardware considerations

Pacing input

The rate of measurement is fixed at approximately 25 samples per second.

Selecting thermocouples

J, K, E, T, R, S or B type thermocouples may be selected using *InstaCal*.

Open thermocouples

When using `cbTInScan()` or `TInScan()` with the **DAS-TC**, an open thermocouple error (`OPENCONNECTION`) on any of the channels will cause all data to be returned as `-9999.0`. This is a hardware limitation. If your application requires isolating channels with defective thermocouples attached and returning valid data for the remainder of the channels, use the `cbTIn()` function or `TIn()` method instead.

To read the voltage input of the thermocouple, select `VOLTS` for the `Scale` parameter in `cbTIn()` and `cbTInScan()`, or `TIn()` and `TInScan()`.

CIO-DAS-TEMP

Temperature input

Temperature input functions and methods supported

UL: `cbTIn()`, `cbTInScan()`

UL for .NET: `TIn()`, `TInScan()`

Temperature input argument values

Options `NOFILTER`

Scale `CELSIUS`, `FAHRENHEIT`, `KELVIN`

HighChan `0 to 31`

Hardware considerations

Pacing Input

The rate of measurement is fixed at approximately 25 samples per second.

Selecting Thermocouples

J, K, E, T, R, S or B type thermocouples may be selected using *InstaCal*.

USB-TEMP, USB-TC

The Measurement Computing brand USB-TEMP and USB-TC support the following UL and UL for .NET features.

Temperature input

Temperature input functions and methods supported

UL:	<code>cbTIn()</code> , <code>cbTInScan()</code>
UL for .NET:	<code>TIn()</code> , <code>TInScan()</code>

Temperature input argument values

Options	N/A
Scale	CELSIUS, FAHRENHEIT, KELVIN
HighChan	0 to 7

Digital I/O

Digital I/O functions and methods supported

UL:	<code>cbDIn()</code> , <code>cbDOut()</code> , <code>cbDBitIn()</code> , <code>cbDBitOut()</code> , <code>cbDConfigBit()</code>
UL for .NET:	<code>DIn()</code> , <code>DOut()</code> , <code>DBitIn()</code> , <code>DBitOut()</code> , <code>DConfigBit()</code>

Digital I/O argument values

PortNum	AUXPORT
DataValue	0 to 255
BitNum	0 to 7

Hardware considerations

Pacing temperature readings

The internal update rate for temperature measurement is a fixed value for these devices. If the UL reads the device faster than the internal update rate, temperature readings "repeat." For example, if using `cbTIn()` in a loop to measure a rapidly changing temperature, readings do not change for several iterations of the loop, then "jump" when the update occurs internally.

Using single sensors with `cbTInScan()`

When using single sensors for RTD or thermistor sensors, you should ignore the data for channels that do not have sensors attached. It is best to use `cbTIn()` for these configurations, since you can select which channels to read. If you use `cbTInScan()`, however, data for all channels over the entire range of channels are returned. Since some channels are not populated in this configuration, you should filter out the data for channels without sensors.

Saving configuration settings

InstaCal allows you to save USB-TEMP and USB-TC configuration settings to a file or load a configuration from a previously saved file.

- Each USB-TEMP channel can be configured to measure temperature data collected by one of five categories of temperature sensors: thermistors, thermocouples, RTDs, semiconductors, and *Disabled*.
- Each USB-TC channel can be configured to measure temperature data collected by one of eight types of thermocouples.

Recommended warm up time (USB-TEMP only)

Allow the USB-TEMP to warm up for 30 minutes before taking measurements. This warm up time minimizes thermal drift and achieves the specified rated accuracy of measurements.

For RTD or thermistor measurements, this warm-up time is also required to stabilize the internal current reference.

Calibration

Any time the sensor category is changed in the configuration for the USB-TEMP, a calibration is automatically performed by *InstaCal*. If the device has not been warmed up when this occurs, you should recalibrate after the specified warmup time.

Error codes

- The UL returns *-9999* when a value is out of range or an open connection is detected.
- The UL returns *-9000* when the device is not ready. This usually occurs right after the device is powered up and calibration factors are being loaded.

Miscellaneous functions and methods supported

UL: cbFlashLED()

UL for .NET: FlashLED()

Causes the USB LED on a Measurement Computing USB module to blink.

When you have several modules connected to the computer, use these functions to identify a particular module by making its LED blink.

miniLAB 1008

The Measurement Computing brand miniLAB 1008 supports the following UL and UL for .NET features.

Analog Input

Analog input functions and methods supported

UL: cbAIn (), cbAInScan (), cbALoadQueue () *, cbFileAInScan (), cbATrig ()

UL for .NET: AIn (), AInScan (), ALoadQueue () *, FileAInScan (), ATrig ()

*The channel-gain queues are limited to eight channel-gain pairs.

Analog input argument values

Options BACKGROUND, BLOCKIO***, BURSTIO**, CONTINUOUS, EXTTRIGGER, CONVERTDATA, and NOCALIBRATEDATA.

**BURSTIO cannot be used with the CONTINUOUS option.

** BURSTIO can only be used with sample count scans of 4096 or less.

*** The BLOCKIO packet size is 64 samples wide.

HighChan 0 to 7 in single-ended mode, 0 to 3 in differential mode.

Rate 8000 maximum for BURSTIO mode (1200 maximum for all other modes.)

When using cbAInScan () or AInScan (), the minimum rate is 100 S/s aggregate.

Range **Single-ended mode:**

BIP10VOLTS (± 10 V)

Differential mode:

BIP20VOLTS (± 20 V) BIP2PT5VOLTS (± 2.5 V)

BIP10VOLTS (± 10 V) BIP2VOLTS (± 2 V)

BIP5VOLTS (± 5 V) BIP1PT25VOLTS (± 1.25 V)

BIP4VOLTS (± 4 V) BIP1VOLT (± 1 V)

Pacing Hardware pacing, internal clock supported.

Triggering

Trigger functions and methods supported

UL: cbSetTrigger ()

UL for .NET: SetTrigger ()

Trigger argument values

TrigType TRIGHIGH, TRIGLOW

Digital (TTL) hardware triggering supported. The hardware trigger is source selectable via InstaCal (AUXPORT inputs 0–3).

Analog output

Analog output functions and methods supported

UL: cbAOut ()

UL for .NET: AOut ()

Analog output argument values

HighChan	1
Range	UNI5VOLTS (0 to 5 V)
DataValue	0 to 1023

Digital I/O

Digital I/O functions and methods supported

UL:	cbDOut (), cbDIn (), cbDBitIn (), cbDBitOut (), cbDConfigBit (), cbDConfigPort ()
UL for .NET:	DOut (), DIn (), DBitIn (), DBitOut (), DConfigBit (), DConfigPort ()

Digital I/O argument values

PortNum	AUXPORT*, FIRSTPORTA
DataValue	0 to 15 for AUXPORT, FIRSTPORTCL or FIRSTPORTCH 0 to 255 for FIRSTPORTA or FIRSTPORTB
BitNum	0 to 3 for AUXPORT 0 to 23 for FIRSTPORTA

*AUXPORT is bitwise configurable for this board, and must be configured using cbDConfigBit () or cbDConfigPort () (or the UL for .NET methods DConfigBit () or DConfigPort ()) before use for output.

Counter I/O

Counter I/O functions and methods supported

UL:	cbCIn () *, cbCIn32 (), cbCLoad () **, cbCLoad32 () **
UL for .NET:	CIn () *, CIn32 (), CLoad () **, CLoad32 () **

*Although cbCIn () and CIn () are valid for use with this counter, cbCIn32 () or CIn32 () may be more appropriate. The values returned may be greater than the data types that are used by cbCIn () and CIn () can handle.

**cbCLoad (), CLoad32 (), CLoad () and CLoad32 () only accept Count=0. These functions are used to reset the counter.

Counter I/O argument values

CounterNum	1
Count:	2 ³² -1 when reading the counter.
LoadValue	0 when loading the counter.

cbCLoad () and cbCLoad32 () / CLoad () and CLoad32 () are only used to reset the counter for this board to 0. No other values are valid.

The “[Basic signed integers](#)” guidelines on page 102 apply when using cbCIn () or CIn () for values greater than 32767, and when using cbCIn32 () or CIn32 () for values greater than 2147483647.

RegNum:	LOADREG1
---------	----------

Event notification

Even notification functions and methods supported

UL:	<code>cbEnableEvent()</code> , <code>cbDisableEvent()</code>
UL for .NET:	<code>EnableEvent()</code> , <code>DisableEvent()</code>
Event types:	<code>ON_SCAN_ERROR</code> , <code>ON_DATA_AVAILABLE</code> , <code>ON_END_OF_AI_SCAN</code>

Hardware considerations

Resolution

When configured for single-ended mode, the resolution of the data is 11 bits (data values between 0 and 2047). However, the Universal Library maps this data to 12-bit values, so the range of data is no different from the differential configuration. Consequently, the data returned contains only even numbers between 0 and 4094.

BURSTIO

Allows higher sampling rates (up to 8000 hertz (Hz)) for sample counts up to 4096. Data is collected into the **miniLAB 1008's** local FIFO. Data is collected into the USB device's local FIFO. Data transfers to the PC don't occur until the scan completes. For `BACKGROUND` scans, the `Count` and `Index` returned by `cbGetStatus()` and `GetStatus()` remain 0, and `Status=RUNNING` until the scan finishes. The `Count` and `Index` are not updated until the scan is completed. When the scan is complete and the data is retrieved, `cbGetStatus()` and `GetStatus()` are updated to the current `Count` and `Index`, and `Status = IDLE`.

`BURSTIO` is the default mode for non-`CONTINUOUS` fast scans (aggregate sample rates above 1000 Hz) with sample counts up to 4096. `BURSTIO` mode allows higher sampling rates (up to 8000 Hz) for sample counts up to 4096. Non-`BURSTIO` scans are limited to a maximum of 1200 Hz. To avoid the `BURSTIO` default, specify `BLOCKIO` mode.

Continuous scans

When running `cbAInScan()` with the `CONTINUOUS` option, you should consider the packet size and the number of channels being scanned. In order to keep the data aligned properly in the array, make the total number of samples an integer multiple of the packet size and the number of channels.

Concurrent operations

Concurrent operations on a particular USB device are not allowed. If you invoke a UL or UL for .NET function on a USB device while another function is running on that USB device, the **ALREADYACTIVE** error is returned.

Miscellaneous functions and methods supported

UL:	<code>cbFlashLED()</code>
UL for .NET:	<code>FlashLED()</code>

Causes the LED on a Measurement Computing USB device to blink.

When you have several USB devices connected to the computer, use these functions to identify a particular device by making its LED blink.

USB-1208 Series

The Measurement Computing brand USB-1208LS and USB-1208FS support the following UL and UL for .NET features.

Analog input

Analog input functions and methods supported

UL: cbAIn (), cbAInScan (), cbALoadQueue () *, cbFileAInScan (), cbATrig ()

UL for .NET: AIn (), AInScan (), ALoadQueue (), FileAInScan (), ATrig ()

Analog input argument values

Options **USB-1208LS**
 BACKGROUND, BLOCKIO*, BURSTIO**, CONTINUOUS, EXTTRIGGER, NOCALIBRATEDATA, and CONVERTDATA,

USB-1208FS
 BACKGROUND, BLOCKIO*, CONTINUOUS, EXTCLOCK, EXTTRIGGER, NOCALIBRATEDATA, and SINGLEIO

*USB-1208 Series packet size based on Options settings are as follows:

Device	Options setting	Packet size
USB-1208LS	BLOCKIO	64
USB-1208FS	BLOCKIO	31
	SINGLEIO	1

** BURSTIO can only be used with the number of samples (Count) set equal to the size of the FIFO or less. The USB-1208LS FIFO holds 4096 samples. BURSTIO cannot be used with the CONTINUOUS option.

HighChan 0 to 7 in single-ended mode
 0 to 3 in differential mode.

Count In CONTINUOUS mode, Count *must* be an integer multiple of the number of channels in the scan.

Rate **USB-1208LS**
 8000 Hz maximum for BURSTIO mode. The maximum rate is 1200 Hz for all other modes. When using cbAInScan () or AInScan (), the minimum sample rate is 100 Hz.

USB-1208FS
 50 kHz maximum for BLOCKIO mode. The throughput is system dependant. Most systems will be able to achieve 40 kHz aggregate. Best results will be obtained using Windows XP. When using cbAInScan() or AInScan() the minimum sample rate is 1 Hz.

Range **Single-ended mode:**
 BIP10VOLTS (± 10 V)

Differential mode:

BIP20VOLTS	(± 20 V)	BIP2PT5VOLTS	(± 2.5 V)
BIP10VOLTS	(± 10 V)	BIP2VOLTS	(± 2 V)
BIP5VOLTS	(± 5 V)	BIP1PT25VOLTS	(± 1.25 V)
BIP4VOLTS	(± 4 V)	BIP1VOLT	(± 1 V)

Triggering**Trigger functions and methods supported**

UL:	<code>cbSetTrigger()</code>
UL for .NET:	<code>SetTrigger()</code>

Trigger argument values

TrigType	USB-1208LS TRIGHIGH and TRIGLOW
	USB-1208FS TRIGPOSEEDGE and TRIGNEGEDGE

Both products support external digital (TTL) hardware triggering. Use the `Trig_In` input (pin # 18 on the screw terminal) for the external trigger signal.

Analog output**Analog output functions and methods supported**

UL:	<code>cbAOut()</code> , <code>cbAOutScan()</code>
UL for .NET:	<code>AOut()</code> , <code>AOutScan()</code>

Analog output argument values

Options	USB-1208LS Ignored
	USB-1208FS BACKGROUND, CONTINUOUS For the USB-1208FS, the number of samples (<code>Count</code>) in a CONTINUOUS scan needs to be an integer multiple of the packet size (32).
HighChan	0 to 1
Count	USB-1208LS (<code>HighChan-LowChan</code>) + 1 USB-1208FS For the USB-1208FS, <code>Count</code> needs to be an integer multiple of the number of channels in the scan. In a CONTINUOUS scan, <code>Count</code> needs to be an integer multiple of the packet size (32).
Rate	USB-1208LS Ignored USB-1208FS 10 kHz for single channel 5 kHz for two channels

	Performance varies when operating on non-XP systems.
Range	USB-1208LS UNI5VOLTS (0 to 5 V)
	USB-1208FS UNI4VOLTS (0 to 4 V, nominal. Actual range is 0 to 4.096 V)
DataValue	USB-1208LS 0 to 1023
	USB-1208FS 0 to 4095

Digital I/O

Digital I/O functions and methods supported

UL:	cbDOut (), cbDIn (), cbDBitIn (), cbDBitOut (), cbDConfigPort ()
UL for .NET:	DOut (), DIn (), DBitIn (), DBitOut (), DConfigPort ()

Digital I/O argument values

PortNum	FIRSTPORTA, FIRSTPORTB
DataValue	0 to 255 for FIRSTPORTA or FIRSTPORTB
BitNum	0 to 15 for FIRSTPORTA

Counter I/O

Counter I/O functions and methods supported

UL:	cbCIn () *, cbCIn32 (), cbCLoad () **, cbCLoad32 () **
UL for .NET:	CIn () *, CIn32 (), CLoad () **, CLoad32 () **

*Although `cbCIn ()` and `CIn ()` are valid for use with this counter, `cbCIn32 ()` or `CIn32 ()` may be more appropriate, since the values returned may be greater than the data types used by `cbCIn ()` and `CIn ()` can handle.

**`cbCLoad ()`, `cbCLoad32 ()`, `CLoad ()` and `CLoad32 ()` only accept `Count=0`. These functions are used to reset the counter.

Counter I/O argument values

CounterNum	1
Count	2 ³² -1 when reading the counter. 0 when loading the counter. <code>cbCLoad ()</code> and <code>cbCLoad32 ()</code> / <code>CLoad ()</code> and <code>CLoad32 ()</code> are only used to reset the counter for this board to 0. No other values are valid. The “ Basic signed integers ” guidelines on page 102 apply when using <code>cbCIn ()</code> or <code>CIn ()</code> for values greater than 32767, and when using <code>cbCIn32 ()</code> or <code>CIn32 ()</code> for values greater than 2147483647.
RegNum	LOADREG1

Event notification

Even notification functions and methods supported

UL:	<code>cbEnableEvent()</code> , <code>cbDisableEvent()</code>
UL for .NET:	<code>EnableEvent()</code> , <code>DisableEvent()</code>
Event types:	<code>ON_SCAN_ERROR (analog input)</code> , <code>ON_DATA_AVAILABLE</code> , <code>ON_END_OF_AI_SCAN</code>
	The USB-1208FS also supports <code>ON_END_OF_AO_SCAN</code> and <code>ON_SCAN_ERROR (analog output)</code>

Hardware considerations

Acquisition Rate

When using the **USB-1208FS**, most systems can sustain rates of 40 kS/s aggregate in `BLOCKIO` mode, and 1 kS/s aggregate in `SINGLEIO` mode.

BURSTIO (USB-1208LS)

`BURSTIO` mode allows higher sampling rates for sample counts up to the size of the FIFO. The **USB-1208LS** FIFO holds 4096 samples. Data is collected into the device's local FIFO. Data transfers to the PC don't occur until the scan completes. For `BACKGROUND` scans, the `Count` and `Index` returned by `cbGetStatus()` and `GetStatus()` remain 0, and `Status=RUNNING` until the scan finishes. The `Count` and `Index` are not updated until the scan is completed. When the scan is complete and the data is retrieved, `cbGetStatus()` and `GetStatus()` are updated to the current `Count` and `Index`, and `Status = IDLE`.

The **USB-1208LS** uses `BURSTIO` as the default mode for non-`CONTINUOUS` fast scans with sample counts up to the size of the FIFO (4096 samples). `BURSTIO` mode allows higher sampling rates for sample counts up to the size of the FIFO. Maximum `Rate` values of non-`BURSTIO` scans are limited (see `Rate` on page 83). To avoid the `BURSTIO` default, specify `BLOCKIO` mode.

EXTCLOCK (USB-1208FS)

By default, the `SYNC` pin is configured for pacer output and provides the internal pacer A/D clock signal. To configure the pin for pacer input, use the `EXTCLOCK` option.

If you use the `EXTCLOCK` option, make sure that you disconnect from the external clock source when you test or calibrate the device with *InstaCal*, as the `SYNC` pin drives the output.

Resolution

When configured for single-ended mode, the resolution of the data is 11 bits (data values between 0 and 2047). However, the Universal Library maps this data to 12-bit values, so the range of data is no different from the differential configuration. Consequently, the data returned contains only even numbers between 0 and 4094.

Continuous scans

When running `cbAInScan()` with the `CONTINUOUS` option, consider the packet size and the number of channels being scanned. To keep the data aligned properly in the array, make the total number of samples an integer multiple of the packet size and the number of channels in the scan.

Concurrent operations

USB-1208LS: Concurrent operations are not allowed. If you invoke a UL or UL for .NET function on a **USB-1208LS** while another function is running on that same unit, the `ALREADYACTIVE` error is returned.

USB-1208FS: The following table lists the concurrent operations supported by the USB-1208FS.

UL function/method	Can be run with...
cbAOutScan () /AOutScan ()	<ul style="list-style-type: none"> ▪ cbDOut () /DOut () ▪ cbCLoad () /CLoad () ▪ cbFlashLED () /FlashLED ()
cbAOut () /AOut ()	cbAInScan () /AInScan () in BACKGROUND mode
cbAInScan () /AInScan ()	All supported digital I/O functions (cbDIn () /Din (), cbDBitIn () /DBitOut (), cbDOut () /DOut (), cbDBitOut () /DBitOut (), cbDConfigPort () /DConfigPort ())

Channel-gain queue

When using cbALoadQueue () /ALoadQueue () with the USB-1208LS, the channel gain queue is limited to eight elements. When using cbALoadQueue () /ALoadQueue () with the USB-1208FS, the channel gain queue is limited to 16 elements.

The queue accepts any combination of valid channels and gains in each element.

Analog output (USB-1208FS)

When you include both analog output channels in cbAOutScan () /AOutScan (), the two channels are updated simultaneously.

Miscellaneous functions and methods supported

- UL: cbFlashLED ()
- UL for .NET: FlashLED ()

Causes the LED on a USB device to blink.

When you have several USB devices connected to the computer, use these functions to identify a particular device by making its LED blink.

USB-1608 Series

The Measurement Computing brand USB-1608FS supports the following UL and UL for .NET features.

Analog input

Analog input functions and methods supported

UL: cbAIn (), cbAInScan (), cbALoadQueue () *, cbFileAInScan (), cbATrig ()

UL for .NET: AIn (), AInScan (), ALoadQueue () *, FileAInScan (), ATrig ()

*The channel-gain queue is limited to eight elements. The USB-1608FS accepts only unique contiguous channels in each element, but the gains may be any valid value.

Analog input argument values

Options BACKGROUND, BLOCKIO**, BURSTIO***, CONTINUOUS, EXTTRIGGER, CONVERTDATA, NOCALIBRATEDATA, SINGLEIO**, and EXTCLOCK.

**USB-1608 Series packet size based on Options settings is as follows:

Device	Options setting	Packet size
USB-1608FS	BLOCKIO	31
	SINGLEIO	Equals the number of channels being sampled.

*** BURSTIO can only be used with the number of samples (Count) set equal to the size of the FIFO or less. The USB-1608FS's FIFO holds 32,768 samples. Also, BURSTIO cannot be used with the CONTINUOUS option.

HighChan 0 to 7 in single-ended mode

Count In BURSTIO mode, Count needs to be an integer multiple of the number of channels in the scan.

- For three- and six-channel scans, the maximum Count is 32766 samples
- For five-channel scans, the maximum Count is 32765 samples
- For seven-channel scans, the maximum Count is 32767 samples
- For one-, two-, four-, and eight-channel scans, the maximum Count is 32768 samples.

Rate 200 kHz maximum for BURSTIO mode (50 kHz for any one channel). The maximum rate is 100 kHz for all other modes (50 kHz for any one channel). When using cbAInScan () or AInScan (), the minimum sample rate is 1 Hz. In BURSTIO mode, the minimum sample rate is 20 Hz/channel.

Range **Single-ended mode:**
 BIP10VOLTS (± 10 V) BIP2VOLTS (± 2 V)
 BIP5VOLTS (± 5 V) BIP1VOLT (± 1 V)

Triggering

Trigger functions and methods supported

UL:	cbSetTrigger()
UL for .NET:	SetTrigger()

Trigger argument values

TrigType	TRIGPOSEDGE and TRIGNEGEDGE. External digital (TTL) hardware triggering supported. You set the hardware trigger source with the Trig_In input (pin# 37 on the screw terminal).
----------	---

Digital I/O

Digital I/O functions and methods supported

UL:	cbDOut(), cbDIn(), cbDBitIn(), cbDBitOut(), cbDConfigBit(), cbDConfigPort()
UL for .NET:	DOut(), DIn(), DBitIn(), DBitOut(), DConfigBit(), DConfigPort()

Digital I/O argument values

PortNum	AUXPORT
DataValue	0 to 255
BitNum	0 to 7 for AUXPORT

Counter I/O

Counter I/O functions and methods supported

UL:	cbCIn()*, cbCIn32(), cbCLoad()**, cbCLoad32()**
UL for .NET:	CIn()*, CIn32(), CLoad()**, CLoad32()**

*Although `cbCIn()` and `CIn()` are valid for use with this counter, `cbCIn32()` or `CIn32()` may be more appropriate, since the values returned may be greater than the data types used by `cbCIn()` and `CIn()` can handle.

**`cbCLoad()`, `cbCLoad32()`, `CLoad()` and `CLoad32()` only accept `Count=0`. These functions are used to reset the counter.

Counter I/O argument values

CounterNum	1
Count	$2^{32}-1$ when reading the counter.
LoadValue	0 when loading the counter.

`cbCLoad()` and `cbCLoad32()` / `CLoad()` and `CLoad32()` are only used to reset the counter for this board to 0. No other values are valid.

The “[Basic signed integers](#)” guidelines on page 102 apply when using `cbCIn()` or `CIn()` for values greater than 32767, and when using `cbCIn32()` or `CIn32()` for values greater than 2147483647.

RegNum	LOADREG1
--------	----------

Event notification

Even notification functions and methods supported

UL:	<code>cbEnableEvent()</code> , <code>cbDisableEvent()</code>
UL for .NET:	<code>EnableEvent()</code> , <code>DisableEvent()</code>
Event types:	<code>ON_SCAN_ERROR</code> , <code>ON_DATA_AVAILABLE</code> , <code>ON_END_OF_AI_SCAN</code>

Hardware considerations

Acquisition rate

Since the maximum data acquisition rate depends on the system connected to the USB-1608FS, it is possible to “lose” data points when scanning at higher rates. The Universal Library cannot always detect this data loss.

Most systems can sustain rates of 80 kS/s aggregate. If you need to sample at higher rates than this, consider using the `BURSTIO` option explained above.

BURSTIO

`BURSTIO` mode allows higher sampling rates for sample counts up to the size of the FIFO. The USB-1608FS device's FIFO holds 32,768 samples. Data is collected into the device's local FIFO. Data transfers to the PC don't occur until the scan completes. For `BACKGROUND` scans, the `Count` and `Index` returned by `cbGetStatus()` and `GetStatus()` remain 0, and `Status=RUNNING` until the scan finishes. The `Count` and `Index` are not updated until the scan is completed. When the scan is complete and the data is retrieved, `cbGetStatus()` and `GetStatus()` are updated to the current `Count` and `Index`, and `Status = IDLE`.

`BURSTIO` is required for aggregate `Rate` settings above 100 kHz, but `Count` is limited to sample counts up to the size of the FIFO (32,768 samples). `Count` settings must be an integer multiple of the number of channels in the scan.

EXTCLOCK

You can set the `SYNC` pin (pin 36) as a pacer input or a pacer output from *InstaCal*. By default, this pin is set for pacer input. If set for output, using the `cbAIInScan / AIInScan` option, `EXTCLOCK` results in a `BADOPTION` error.

Continuous scans

When running `cbAIInScan()` with the `CONTINUOUS` option, you should consider the packet size and the number of channels being scanned. In order to keep the data aligned properly in the array, make the total number of samples an integer multiple of the packet size and the number of channels.

When running `cbAIInScan()` with the `CONTINUOUS` option, you **must** set the count to an integer multiple of the packet size (31) and the number of channels in the scan.

Miscellaneous functions and methods supported

UL:	<code>cbFlashLED()</code>
UL for .NET:	<code>FlashLED()</code>

Causes the LED on a USB device to blink.

When you have several USB devices connected to the computer, use these functions to identify a particular device by making its LED blink.

USB-1616 Series

The Measurement Computing brand USB-1616FS supports the following UL and UL for .NET features.

Analog input

Analog input functions and methods supported

UL: cbAIn (), cbAInScan (), cbALoadQueue () *, cbFileAInScan (), cbATrig ()

UL for .NET: AIn (), AInScan (), ALoadQueue () *, FileAInScan (), ATrig ()

*The channel-gain queue is limited to 16 elements. The USB-1616FS accepts only unique contiguous channels in each element, but the gains may be any valid value.

Analog input argument values

Options: BACKGROUND, BLOCKIO**, BURSTIO***, CONTINUOUS, EXTTTRIGGER, SINGLEIO**, and EXTCLK

**USB-1616 Series packet size based on Options settings

Device	Options setting	Packet size
USB-1616FS	BLOCKIO	62
	SINGLEIO	Equals the number of channels being sampled.

*** BURSTIO can only be used with the number of samples (Count) set equal to the size of the FIFO or less. The USB-1616FS FIFO holds 32,768 samples. Also, BURSTIO cannot be used with the CONTINUOUS option.

HighChan 0 to 15 in single-ended mode

Count In BURSTIO mode, Count needs to be an integer multiple of the number of channels in the scan.

- For one-, two-, four-, eight-, and 16-channel scans, the maximum Count is 32768 samples.
- For three- and six-channel scans, the maximum Count is 32766 samples
- For five-channel scans, the maximum Count is 32765 samples
- For seven-channel scans, the maximum Count is 32767 samples
- For 9-, 10-, 12-, 13-, 14-, and 15-channel scans, the maximum Count is 32760 samples
- For 11-channel scans, the maximum Count is 32758 samples.

Rate: 200 kilohertz (kHz) maximum for BURSTIO mode (50 kHz for any one channel). For all other modes, the maximum rate per channel depends on the number of channels being scanned.

No. of channels in scan	Maximum rate	No. of channels in scan	Maximum rate
1 or 2	50 kHz	10	14 kHz
3	36 kHz	11	12.5 kHz
4	30 kHz	12	12 kHz
5	25 kHz	13	11.25 kHz
6	22 kHz	14	10.5 kHz
7	19 kHz	15	10 kHz
8	17 kHz	16	9.5 kHz
9	15 kHz		

When using cbAInScan () or AInScan (), the minimum sample rate is 1 Hz. In BURSTIO mode, the minimum sample rate is 20 Hz/channel.

Range:	Single-ended:	
		BIP10VOLTS (± 10 volts) BIP5VOLTS (± 5 volts)
		BIP2VOLTS (± 2 volts) BIP1VOLTS (± 1 volt)
Pacing:	Hardware pacing, internal clock supported.	
	External clock supported via the SYNC pin.	

Triggering

Triggering functions and methods supported

UL:	cbSetTrigger ()
UL for .NET:	SetTrigger ()

Trigger argument values

TrigType:	TRIGPOSEEDGE, TRIGNEGEDGE
-----------	---------------------------

External digital (TTL) hardware triggering supported. You set the hardware trigger source with the TRIG_IN input terminal.

Digital I/O

Digital I/O functions and methods supported

UL:	cbDOut (), cbDIn (), cbDBitIn (), cbDBitOut (), cbDConfigBit (), cbDConfigPort ()
UL for .NET:	DOut (), DIn (), DBitIn (), DBitOut (), DConfigBit (), DConfigPort ()

Digital I/O argument values

PortNum:	AUXPORT (eight bits, bit-configurable)
DataValue:	0 to 255
BitNum:	0 to 7

Counter I/O

Counter I/O functions and methods supported

UL:	cbCIn () *, cbCIn32 (), cbCLoad () **, cbCLoad32 () **
UL for .NET:	CIn () *, CIn32 (), CLoad () **, CLoad32 () ** *

Although `cbCIn ()` and `CIn ()` are valid for use with this counter, `cbCIn32 ()` or `CIn32 ()` may be more appropriate, since the values returned may be greater than the data types used by `cbCIn ()` and `CIn ()` can handle. **`cbCLoad ()`, `cbCLoad32 ()`, `CLoad ()` and `CLoad32 ()` only accept `Count=0`. These functions are used to reset the counter.

Counter I/O argument values

CounterNum:	1
Count	232-1 when reading the counter. 0 when loading the counter.

`cbCLoad ()` and `cbCLoad32 ()` / `CLoad ()` and `CLoad32 ()` are only used to reset the counter for this board to 0. No other values are valid.

The “[Basic signed integers](#)” guidelines on page 102 apply when using `cbCIn ()` or `CIn ()` for values greater than 32767, and when using `cbCIn32 ()` or `CIn32 ()` for values greater than 2147483647.

Event notification

Even notification functions and methods supported

UL:	<code>cbEnableEvent ()</code> , <code>cbDisableEvent ()</code>
UL for .NET:	<code>EnableEvent ()</code> , <code>DisableEvent ()</code>
Event types:	<code>ON_SCAN_ERROR</code> , <code>ON_DATA_AVAILABLE</code> , <code>ON_END_OF_AI_SCAN</code>

Hardware considerations

Acquisition rate

Since the maximum data acquisition rate depends on the system connected to the USB-1616FS, it is possible to "lose" data points when scanning at higher rates. The Universal Library cannot always detect this data loss. Maximum rates may be lower in Windows operating systems that predate Windows XP. Most systems can sustain rates of 80 kS/s aggregate. If you need to sample at higher rates than this, consider using the `BURSTIO` option explained later in this topic.

EXTCLOCK

You can set the SYNC pin as a pacer input or a pacer output from *InstaCal*. By default, this pin is set for pacer input. If set for output, using the `cbAInScan ()/AInScan ()` option `EXTCLOCK` results in a `BADOPTION` error.

BURSTIO

Allows higher sampling rates up to the size of the FIFO. The USB-1616FS FIFO holds 32,768 samples. Data is collected into the USB device's local FIFO. Data transfers to the PC don't occur until the scan completes. For `BACKGROUND` scans, the `Count` and `Index` returned by `cbGetStatus ()` and `GetStatus ()` remain 0, and `STATUS=RUNNING` until the scan finishes. The `Count` and `Index` are not updated until the scan is completed. When the scan is complete and the data is retrieved, `cbGetStatus ()` and `GetStatus ()` are updated to the current `Count` and `Index`, and `STATUS=IDLE`.

`BURSTIO` is required for aggregate `Rate` settings above 100 kHz, but `Count` is limited to sample counts up to the size of the FIFO (32,768 samples). `Count` settings must be an integer multiple of the number of channels in the scan (see `Count` above).

Continuous scans

When running `cbAInScan ()/AInScan ()` with the `CONTINUOUS` option, you should consider the packet size and the number of channels being scanned. In order to keep the data aligned properly in the array, make the total number of samples an integer multiple of the packet size and the number of channels.

When running `cbAInScan ()/AInScan ()` with the `CONTINUOUS` option, you must set the count to an integer multiple of the packet size (62) and the number of channels in the scan.

Miscellaneous functions and methods supported

UL:	<code>cbFlashLED ()</code>
UL for .NET:	<code>FlashLED ()</code>

Causes the USB LED on a Measurement Computing USB module to blink.

When you have several modules connected to the computer, use these functions to identify a particular module by making its LED blink.

Analog Output Boards

Introduction

All boards with analog outputs support the `cbAOut()` and `cbAOutScan()` functions. Boards released after the printing of this manual are described in Readme files on the Universal Library disk.

`cbAOutScan()` / `AOutScan()` are designed primarily for boards that support hardware-paced analog output, but it is also useful when simultaneous update of all channels is desired. If the hardware is configured for simultaneous update, this function loads each DAC channel with the appropriate value before issuing the update command.

DAC04 HS Series

Analog output

Analog output functions and methods supported

UL: cbAOut (), cbAOutScan ()

UL for .NET: AOut (), AOutScan ()

Analog output argument values

Options BACKGROUND, CONTINUOUS, EXTCLOCK, SIMULTANEOUS

HighChan 0 to 3

Rate 500000

DataValue 0 to 4095

Digital I/O

Digital I/O functions and methods supported

UL: cbDOut (), cbDIn (), cbDBitIn (), cbDBitOut ()

UL for .NET: DOut (), DIn (), DBitIn (), DBitOut ()

Digital I/O argument values

PortNum AUXPORT*

DataValue 0 to 255

BitNum 0 to 7

* AUXPORT is not configurable for these boards.

Hardware considerations

Pacing analog output

Hardware pacing, external or internal clock supported.

The external clock is hardwired to the DAC pacer. If an internal clock is to be used, do not connect a signal to the External Pacer input.

DAC Series (Excluding HS Series)

Analog output

Analog output functions and methods supported

UL:	cbAOut (), cbAOutScan ()
UL for .NET:	AOut (), AOutScan ()

Analog output argument values

Options	SIMULTANEOUS	
HighChan	DAC02 0 to 1	DAC08 0 to 7
	DAC06 0 to 5	DAC16 0 to 15
Rate	Ignored	
Count	HighChan - LowChan + 1 max	
Range	Ignored	
DataValue	0 to 4095	

For the /16 series, the following argument values are also valid:
0 to 65535 (Refer to "[16-bit values using a signed integer data type](#)" on page 8 for information on 16-bit values using unsigned integers.)

Hardware considerations

Pacing analog output

Software only

PCI-DAC6700 Series

Analog output

Analog output functions and methods supported

UL: cbAOut (), cbAOutScan ()
 UL for .NET: AOut (), AOutScan ()

Analog output argument values

HighChan: **PCI-DAC6702: 7** **PCI-DAC6703: 15**
 Count: HighChan - LowChan + 1 max
 Rate: Ignored
 Range: BIP10VOLTS (± 10.1 V)
 DataValue: 0 to 65535 (Refer to "[16-bit values using a signed integer data type](#)" on page 8 for information on 16-bit values using unsigned integers.)

Digital I/O

Digital I/O functions and methods supported

UL: cbDOut (), cbDIn (), cbDBitIn (), cbDBitOut (), cbDConfigPort (),
 cbDConfigBit ()
 UL for .NET: DOut (), DIn (), DBitIn (), DBitOut (), DConfigPort (), DConfigBit ()

Digital I/O argument values

PortNum: AUXPORT is bitwise configurable for these boards, and must be configured using
 cbDConfigBit () or cbDConfigPort () before use as output.
 DataValue 0 to 255
 BitNum 0 to 7

Configuration

Configuration functions and methods supported

UL: cbGetConfig (), cbSetConfig ()
 UL for .NET: GetDACStartup (), GetDACUpdateMode (), SetDACStartup (),
 SetDACUpdateMode ()

Configuration argument values

ConfigItem: BIDACSTARTUP, BIDACUPDATEMODE, BIDACUPDATECMD

Hardware considerations

Pacing analog output

Software only

PCM- and PC-CARD- DAC Series

Analog output

Analog output functions and methods supported

UL:	cbAOut (), cbAOutScan ()
UL for .NET:	AOut (), AOutScan ()

Analog output argument values

Options	PCM-DAC02 Ignored	
	PCM-DAC08 and PC-CARD-DAC08 SIMULTANEOUS	
HighChan	DAC02 0 to 1	DAC08 0 to 7
Rate	Ignored	
Count	HighChan - LowChan + 1 max	
Range	PCM-DAC08 and PC-CARD-DAC08 Ignored	
	PCM-DAC02 BIP10VOLTS BIP5VOLTS UNI10VOLTS UNI5VOLTS	
DataValue	0 to 4095	

Digital I/O

Digital I/O functions and methods supported

UL:	cbDOut (), cbDIn (), cbDBitIn (), cbDBitOut (), cbDConfigPort ()
UL for .NET:	DOut (), DIn (), DBitIn (), DBitOut (), DConfigPort ()

Digital I/O argument values

PortNum	FIRSTPORTA, FIRSTPORTB
DataValue	0 to 15 for FIRSTPORTA or FIRSTPORTB
BitNum	0 to 7 using FIRSTPORTA

Hardware considerations

Pacing analog output

Software only

Digital configuration

Supports two configurable 4-bit ports—FIRSTPORTA and FIRSTPORTB. Each can be independently configured as either inputs or outputs via cbDConfigPort () or DConfigPort ().

PCIM- and CIO- DDA06 Series

Analog output

Analog output functions and methods supported

UL:	cbAOut (), cbAOutScan ()
UL for .NET:	AOut (), AOutScan ()

Analog output argument values

Options	SIMULTANEOUS (CIO-DDA06 Series only)
HighChan	0 to 5
Rate	Ignored
Count	HighChan - LowChan + 1 max
Range	Ignored
DataValue	0 to 4095

For the /16 series, the following argument values are also valid
0 to 65535 (Refer to "[16-bit values using a signed integer data type](#)" on page 8.)

Digital I/O

Digital I/O functions and methods supported

UL:	cbDOut (), cbDIn (), cbDBitIn (), cbDBitOut (), cbDConfigPort ()
UL for .NET:	DOut (), DIn (), DBitIn (), DBitOut (), DConfigPort ()

Digital I/O argument values

PortNum	FIRSTPORTA, FIRSTPORTB, FIRSTPORTCL, FIRSTPORTCH
DataValue	0 to 15 for FIRSTPORTC 0 to 255 for FIRSTPORTA or FIRSTPORTB
BitNum	0 to 23 using FIRSTPORTA

Hardware considerations

Pacing analog output

Software only

Initializing the 'zero power-up' state

When using the **CIO-DDA06** "zero power-up state" hardware option, use `cbAOutScan ()` or `AOutScan ()` to set the desired output value and enable the DAC outputs.

PCI- and CPCI- DDA Series

Analog output

Analog output functions and methods supported

UL:	cbAOut (), cbAOutScan ()
UL for .NET:	AOut (), AOutScan ()

Analog output argument ranges

Options	SIMULTANEOUS
HighChan	DDA02: 0 to 1 DDA04: 0 to 3 DDA08: 0 to 7
Rate	Ignored
Count	HighChan - LowChan + 1 max
Range	BIP10VOLTS UNI10VOLTS BIP5VOLTS UNI5VOLTS BIP2PT5VOLTS UNI2PT5VOLTS
DataValue	0 to 4095

For the /16 series, the following argument values are also valid
0 to 65535 (Refer to "[16-bit values using a signed integer data type](#)" on page 8 for information on 16-bit values using unsigned integers.)

Digital I/O

Digital I/O functions and methods supported

UL:	cbDOut (), cbDIn (), cbDBitIn (), cbDBitOut (), cbDConfigPort ()
UL for .NET:	DOut (), DIn (), DBitIn (), DBitOut (), DConfigPort ()

Digital I/O argument values

PortNum	FIRSTPORTA, FIRSTPORTB, FIRSTPORTCL, FIRSTPORTCH, SECONDPOR SECONDPORCL, SECONDPORCH
DataValue	0 to 15 for PORTC; 0 to 255 for PORTA or PORTB
BitNum	0 to 47 using FIRSTPORTA

Hardware considerations

Pacing analog output

Software only.

cSBX-DDA04

Analog output

Analog output functions and methods supported

UL: cbAOut (), cbAOutScan ()

UL for .NET: AOut (), AOutScan ()

Analog output argument ranges

Options BACKGROUND, CONTINUOUS, EXTCLOCK, SIMULTANEOUS

Rate 300,000

Pacing Hardware pacing, external or internal clock supported

Digital I/O

Digital I/O functions and methods supported

UL: cbDIn (), cbDOut (), cbDBitIn (), cbDBitOut (), cbDInScan (), cbDOutScan ()

UL for .NET: DIn (), DOut (), DBitIn (), DBitOut (), DConfigPort ()

Digital I/O argument values

PortNum AUXPORT*

DataValue 0 to 255 using cbDIn () or cbDInScan (), 0 to 16383

BitNum 0 to 7 using cbDBitIn ()
0 to 13 using cbDBitOut ()

Rate 500 kHz (refer to "Notes" below).

Pacing Hardware
* AUXPORT is not configurable for this board.

Notes

The cSBX-DDA04 board allows interleaving of analog and digital output data. To support interleaving, a control bit indicates the data type. The control bit is the MSB of each 16-bit word of analog or digital data. The MSB = 0 for analog data, and 1 for digital data. The data is passed to the board and then directed to the correct output type by hardware on the board which detects and acts on the MSB control bit.

- To use this interleaving capability with the UL, set HighChan and LowChan to NOTUSED, and indicate the data type and channel in the most significant four bits of the data values in the buffer.
- To use this interleaving capability with the UL for .NET, set HighChan and LowChan to NOTUSED, and indicate the data type and channel in the most significant four bits of the data values in the buffer.

Digital Input/Output Boards

Introduction

This section has details on using digital I/O boards in conjunction with the Universal Library. Boards released after the printing of this manual will be described in Readme files on the Universal Library disk.

Basic signed integers

When reading or writing ports that are 16-bits wide, be aware of the following issue using signed integers (as you are forced to do when using Basic):

On some boards, for example the **PDISO16**, the `AUXPORT` digital ports are set up as one 16-bit port. When using `cbDOut()` or `DOut()`, the digital values are written as a single 16-bit word. Using signed integers, writing values above `0111 1111 1111 1111` (32767 decimal) can be confusing. The next increment, `1000 0000 0000 0000`, has a decimal value of -32768. Using signed integers, this is the value that you would use for turning on the MSB only. The value for all bits on is -1. Keep this in mind if you are using Basic, since Basic does not supply unsigned integers (values from 0 to 65536).

To fully understand and maximize the performance of this and other digital input function calls, refer to the 82C55 data sheet in the Documents subdirectory of the installation. This data sheet is also available from our web site at www.mccdaq.com/PDFmanuals/82C55A.pdf. Also refer to the 8536 data sheet (this data sheet file is not available in PDF format).

AC5 Series

Digital I/O

Digital I/O functions and methods supported

UL: cbDOut (), cbDIn (), cbDBitIn (), cbDBitOut (), cbDConfigPort ()

UL for .NET: DOut (), DIn (), DBitIn (), DBitOut (), DConfigPort ()

Digital I/O argument values

All boards in this series support:

PortNum FIRSTPORTA, FIRSTPORTB, FIRSTPORTCL, FIRSTPORTCH

DataValue 0 to 15 using FIRSTPORTCL or FIRSTPORTCH
0 to 255 using FIRSTPORTA or FIRSTPORTB

BitNum 0 to 23 using FIRSTPORTA

DUAL-AC5 and QUAD-AC5 boards also support:

PortNum SECONDPORTA, SECONDPORTB, SECONDPORTCL, SECONDPORTCH

DataValue 0 to 15 using SECONDPORTCL or SECONDPORTCH
0 to 255 using SECONDPORTA or SECONDPORTB

BitNum 0 to 47 using FIRSTPORTA

QUAD-AC5 boards also support:

PortNum THIRDPOR TA, THIRDPOR TB, THIRDPOR TCL, THIRDPOR TCH, FOURTHPOR TA,
FOURTHPOR TB, FOURTHPOR TCL, FOURTHPOR TCH

DataValue 0 to 15 using THIRDPOR TCL or THIRDPOR TCH
0 to 255 using THIRDPOR TA or THIRDPOR TB

BitNum 0 to 95 using FIRSTPORTA

DIO Series

Digital I/O

Digital I/O functions and methods supported

UL: cbDOut (), cbDIn (), cbDBitIn (), cbDBitOut (), cbDConfigPort ()

UL for .NET: DOut (), DIn (), DBitIn (), DBitOut (), DConfigPort ()

Digital I/O argument values

PortNum FIRSTPORTA, FIRSTPORTB, FIRSTPORTCL, FIRSTPORTCH

For **DIO48**, **DIO48H**, **DIO96**, and **DIO192**, the following values are also valid:
SECONDPORTA, SECONDPORTB, SECONDPORTCL, SECONDPORTCH

For **DIO96**, and **DIO192**, the following argument values are also valid:
THIRDPORTA, THIRDPORTB, THIRDPORTCL, THIRDPORTCH, FOURTHPORTA,
FOURTHPORTB, FOURTHPORTCL, FOURTHPORTCH

For **DIO192**, the following values are also valid:
FIFTHPORTA through EIGHTHPORTCH

DataValue 0 to 15 for PORTCL or PORTCH
0 to 255 for PORTA or PORTB

BitNum 0 to 23 using FIRSTPORTA

For **DIO48**, **DIO48H**, **DIO96**, and **DIO192**, the following values are also valid:
24 to 47 using FIRSTPORTA

For **DIO96**, and **DIO192**, the following values are also valid:
48 to 95 using FIRSTPORTA

For **DIO192**, the following values are also valid:
96 to 191

Event notification (CIO- and PCI- DIO24 and DIO24H; PCI-DIO24/LP and PCI-DIO24/S only)

Event notification functions and methods supported

UL: cbEnableEvent (), cbDisableEvent ()

UL for .NET: EnableEvent (), DisableEvent ()

Event notification argument values

EventType ON_EXTERNAL_INTERRUPT (UL)/OnExternalInterrupt (UL for .NET)

Hardware considerations

Event Notification

DIO Series boards that support event notification only support external rising edge interrupts.

DIO24/CTR3 and D24/CTR3 Series

Digital I/O

Digital I/O functions and methods supported

UL: cbDOut (), cbDIn (), cbDBitIn (), cbDBitOut (), cbDConfigPort ()

UL for .NET: DOut (), DIn (), DBitIn (), DBitOut (), DConfigPort ()

Digital I/O argument values

PortNum FIRSTPORTA, FIRSTPORTB, FIRSTPORTCL, FIRSTPORTCH

DataValue 0 to 15 for FIRSTPORTCL or FIRSTPORTCH
0 to 255 for FIRSTPORTA or FIRSTPORTB

BitNum 0 to 23 using FIRSTPORTA

Counter I/O

Counter functions and methods supported

UL: cbC8254Config (), cbCIn (), cbCLoad ()

UL for .NET: C8254Config (), CIn (), CLoad ()

Counter argument values

CounterNum 1 to 3

Config HIGHONLASTCOUNT, ONESHOT, RATEGENERATOR, SQUAREWAVE, SOFTWARESTROBE,
HARDWARESTROBE

LoadValue 0 to 65535 (Refer to "[16-bit values using a signed integer data type](#)" on page 8.)

RegNum: LOADREG1, LOADREG2, LOADREG3

Event notification

CIO-DIO24/CTR3 and PC-CARD-D24/CTR3

Event notification functions and methods supported

UL: cbEnableEvent (), cbDisableEvent ()

UL for .NET: EnableEvent (), DisableEvent ()

Event notification argument values

EventType ON_EXTERNAL_INTERRUPT

Hardware considerations

Counter configuration

Counter source functions are programmable using *InstaCal*.

PCI-DIO48/CTR15

Digital I/O

Digital I/O functions and methods supported

UL: cbDOut(), cbDIn(), cbDBitIn(), cbDBitOut(), cbDConfigPort()
 UL for .NET: DOut(), DIn(), DBitIn(), DBitOut(), DConfigPort()

Digital I/O argument values

PortNum FIRSTPORTA, FIRSTPORTB, FIRSTPORTCL, FIRSTPORTCH, SECONDPORTA,
 SECONDPORTB, SECONDPORTCL, SECONDPORTCH
 DataValue 0 to 15 for FIRSTPORTCL or FIRSTPORTCH
 0 to 255 for FIRSTPORTA or FIRSTPORTB
 BitNum 0 to 47 using FIRSTPORTA

Counter I/O

Counter functions and methods supported

UL: cbC8254Config(), cbCIn(), cbCLoad()
 UL for .NET: C8254Config(), CIn(), CLoad()

Counter argument values

CounterNum 1 to 15
 Config HIGHONLASTCOUNT, ONESHOT, RATEGENERATOR, SQUAREWAVE, SOFTWARESTROBE,
 HARDWARESTROBE
 LoadValue 0 to 65535 (Refer to "[16-bit values using a signed integer data type](#)" on page 8 for
 information on 16-bit values using unsigned integers.)
 RegNum: LOADREG1 - LOADREG15

Event notification

Event notification functions and methods supported

UL: cbEnableEvent(), cbDisableEvent()
 UL for .NET: EnableEvent(), DisableEvent()

Event notification argument values

EventType ON_EXTERNAL_INTERRUPT

PDISO8 and PDISO16 Series

Digital I/O

Digital I/O functions and methods supported

UL: `cbDOut()`, `cbDIn()`, `cbDBitIn()`, `cbDBitOut()`

UL for .NET: `DOut()`, `DIn()`, `DBitIn()`, `DBitOut()`

Digital I/O argument values

PortNum `AUXPORT`

DataValue **PDISO8**

0 to 255

PDISO16

0 to 65535 (Refer to "[16-bit values using a signed integer data type](#)" on page 8 for information on 16-bit values using unsigned integers.)

BitNum **PDISO8**

0 to 7

PDISO16

0 to 15

Miscellaneous functions and methods supported (USB-PDISO8, USB-PDISO8/40, and E-PDISO16 only)

UL: `cbFlashLED()`

UL for .NET: `FlashLED()`

Causes the USB LED on a Measurement Computing USB module to blink. Causes the LINK LED on a Measurement Computing Ethernet module to blink.

When you have several USB modules connected to the computer or Ethernet modules on the network, use these functions to identify a particular module by making its LED blink.


Establishing and requesting control of an E-PDISO16

The first computer to establish a TCP socket establishes control over an E-PDISO16. Additional computers that contact the device can only query the state of the device and its ports.

Sending a request for control of an E-PDISO16

If another computer already has control over E-PDISO16 when you connect to it, you can send a message to the controlling computer. Do the following.

1. From *InstaCal*'s main window, double-click on the E-PDISO16.
2. From the **Ethernet Settings** tab, click on the **Request Ownership** button.
3. On the **Request Ownership** dialog, enter your message (up to 256 characters). Press **Ctrl** and **Enter** to go to a new line.
4. You can set how long the message is displayed on the computer that controls the E-PDISO16 from the **Maximum Wait** drop-down list box.
5. When you are ready to send the message, click on the **Send** button.



Receiving a request for control of an E-PDISO16

If your computer controls an E-PDISO16 and you receive a message from another person requesting control of the device, the message shows on your screen for the time the person set in the **Maximum Wait** drop-down list.



- To disconnect and give control of the E-PDISO16 to the person requesting, click on the **Yes** button.
- To retain control of the E-PDISO16, click on the **No** button.

Receiving a message

When a computer sends a message to the computer controlling the device, the message displays on the monitor of the controlling computer for the time specified by the **Time-out** value.

The message box has two buttons used to respond to the message. When you receive a message, enter a response in the message box and click on one of the following buttons.

- **Yes:** Click on **Yes** to give up ownership/control over the network device.
The computer automatically disconnects from the network connection, and control over the device transfers to the computer that sent the message. The **Device Owner** property in *InstaCal* updates with the name of the computer that gained control of the device.
- **No:** Click on **No** when you do not agree to give up ownership or control over the network device.

When you click on a button, the message box and selected response displays on the computer that sent the message.

CIO-PDMA16 and CIO-PDMA32

Digital I/O

Digital I/O functions and methods supported

UL: cbDOutScan(), cbDInScan(), cbDOut(), cbDIn(), cbDBitIn(), cbDBitOut(),
cbDConfigPort()

UL for .NET: DOutScan(), DInScan(), DOut(), DIn(), DBitIn(), DBitOut(), DConfigPort()

Digital I/O argument values

PortNum FIRSTPORTA, FIRSTPORTB, AUXPORT

DataValue 0 to 7 using AUXPORT (only cbDOut() is supported),
0 to 255 using FIRSTPORTA and FIRSTPORTB,
0 to 65535 using WORDXFER FIRSTPORTA.

BitNum 0 to 2 using AUXPORT (only cbDBitOut() and DBitOut() are supported),
0 to 15 using PORTA.

Rate **CIO-PDMA16:** 125 Kwords

CIO-PDMA32: 750 Kwords

Options BACKGROUND, CONTINUOUS, EXTCLOCK, WORDXFER

Hardware considerations

Digital I/O Pacing

Hardware pacing, external or internal clock supported.

USB-1024 and USB-DIO24 Series

The Measurement Computing brand USB-1024LS, USB-1024HLS, USB-DIO24/37, and USB-DIO24H/37 support the following UL and UL for .NET features.

Digital I/O

Digital I/O functions and methods supported

UL: cbDIn (), cbDOut (), cbDBitIn (), cbDBitOut (), cbDConfigPort ()
 UL for .NET: DIn (), DOut (), DBitIn (), DBitOut (), DConfigPort ()

Digital I/O argument values

PortNum FIRSTPORTA, FIRSTPORTB, FIRSTPORTCL, FIRSTPORTCH
 DataValue 0 to 15 for FIRSTPORTCL or FIRSTPORTCH
 0 to 255 for FIRSTPORTA or FIRSTPORTB
 BitNum 0 to 23 for FIRSTPORTA

Counter I/O

Counter functions and methods supported

UL: cbCIn () *, cbCIn32 (), cbCLoad () **, cbCLoad32 () **
 UL for .NET: CIn () *, CIn32 (), CLoad () **, CLoad32 () **
 *Although cbCIn () and CIn () are valid for use with this counter, cbCIn32 () or CIn32 () may be more appropriate, since the values returned may be greater than the data types used by cbCIn () and CIn () can handle.
 **cbCLoad (), cbCLoad32 (), CLoad () and CLoad32 () only accept Count=0. These functions are used to reset the counter.

Counter argument values

CounterNum 1
 Count 0 to $2^{32}-1$ when reading the counter.
 LoadValue 0 when loading the counter.
 cbCLoad () and cbCLoad32 () / CLoad () and CLoad32 () are only used to reset the counter for this board to 0. No other values are valid. The "[Basic signed integers](#)" guidelines on page 102 apply when using cbCIn () or CIn () for values greater than 32767, and when using cbCIn32 () or CIn32 () for values greater than 2147483647.
 RegNum LOADREG1

Miscellaneous functions and methods supported

UL: cbFlashLED ()
 UL for .NET: FlashLED ()

Causes the LED on a USB device to blink.

When you have several USB devices connected to the computer, use these functions to identify a particular device by making its LED blink.

USB-DIO96 Series (formerly USB-1096 Series)

The Measurement Computing brand USB-DIO96H, USB-DIO96H/50, and USB-1096HFS support the following UL and UL for .NET features.

Digital I/O

Digital I/O functions and methods supported

UL: cbDIn (), cbDOut (), cbDBitIn (), cbDBitOut (), cbDConfigPort ()

UL for .NET: DIn (), DOut (), DBitIn (), DBitOut (), DConfigPort ()

Digital I/O arguments

PortNum: FIRSTPORTA, FIRSTPORTB, FIRSTPORTCL, FIRSTPORTCH, SECONDPORTA, SECONDPORTB, SECONDPORTCL, SECONDPORTCH, THIRDPORTA, THIRDPORTB, THIRDPORTCL, THIRDPORTCH, FOURTHPORTA, FOURTHPORTB, FOURTHPORTCL, FOURTHPORTCH

DataValue: 0 to 15 for PORTCL or PORTCH
0 to 255 for PORTA or PORTB

BitNum: 0 to 95 for FIRSTPORTA

Counter I/O

Counter functions and methods supported

UL: cbCIn () *, cbCIn32 (), cbCLoad () **, cbCLoad32 () **

UL for .NET: CIn () *, CIn32 (), CLoad () **, CLoad32 () **

*Although `cbCIn ()/CIn ()` are valid for use with this counter, `cbCIn32 ()` or `CIn32 ()` may be more appropriate, since the values returned may be greater than the data types used by `cbCIn ()` and `CIn ()` can handle.

**`cbCLoad ()`, `cbCLoad32 ()`, `CLoad ()` and `CLoad32 ()` only accept `Count=0`. These functions are used to reset the counter.

CounterNum: 1

Count 0 to 232-1 when reading the counter.

The “[Basic signed integers](#)” guidelines on page 102 apply when using `cbCIn ()` or `CIn ()` for values greater than 32767, and when using `cbCIn32 ()` or `CIn32 ()` for values greater than 2147483647.

0 when loading the counter.

`cbCLoad ()` and `cbCLoad32 ()/CLoad ()` and `CLoad32 ()` are only used to reset the counter for this module to 0. No other values are valid.

RegNum LOADREG1

Miscellaneous functions and methods supported

UL: cbFlashLED ()

UL for .NET: FlashLED ()

Causes the USB LED on a Measurement Computing USB module to blink.

When you have several modules connected to the computer, use these functions to identify a particular module by making its LED blink.

USB-SSR Series

The Measurement Computing brand USB-SSR24 and USB-SSR08 both support the following UL and UL for .NET features unless noted otherwise.

Digital I/O

Digital I/O functions and methods supported

UL: `cbDIn ()`, `cbDOut ()`, `cbDBitIn ()`, `cbDBitOut ()`

UL for .NET: `DIn ()`, `DOut ()`, `DBitIn ()`, `DBitOut ()`

Digital I/O arguments

PortNum `FIRSTPORTCL`, `FIRSTPORTCH`

For the **USB-SSR24**, the following argument values are also valid:

`FIRSTPORTA`, `FIRSTPORTB`

DataValue 0 to 15 for `FIRSTPORTCL` and `FIRSTPORTCH`

For the **USB-SSR24**, the following argument values are also valid:

0 to 255 for `FIRSTPORTA` and `FIRSTPORTB`

BitNum For the **USB-SSR08**, the following argument values are valid:

16 to 23 for `FIRSTPORTA`

For the **USB-SSR24**, the following argument values are valid:

0 to 23 for `FIRSTPORTA`

Miscellaneous functions and methods supported

UL: `cbFlashLED ()`

UL for .NET: `FlashLED ()`

Causes the USB LED on a Measurement Computing USB module to blink.

When you have several modules connected to the computer, use these functions to identify a particular module by making its LED blink.

Hardware considerations

Do not change state of switches while program is running

Do not change the state of any switches (labeled S1, S2, and S3) on a USB-SSR module while a program is running. UL stores the current state of each switch, and changing a switch setting while a program is running can cause unpredictable results.

Switch & Sense 8/8

The Measurement Computing brand Switch & Sense 8/8 supports the following UL and UL for .NET features.

Digital I/O

Digital I/O functions and methods supported

UL: `cbDOut()`, `cbDIn()`, `cbDBitIn()`, `cbDBitOut()`

UL for .NET: `DOut()`, `DIn()`, `DBitIn()`, `DBitOut()`

Digital I/O argument values

PortNum `AUXPORT`

DataValue `0 to 255`

BitNum `0 to 7`

Miscellaneous functions and methods supported

UL: `cbFlashLED()`

UL for .NET: `FlashLED()`

Causes the USB LED on a Measurement Computing USB module to blink.

When you have several modules connected to the computer, use these functions to identify a particular module by making its LED blink.

Digital Input Boards

Introduction

This section provides details on using digital input boards in conjunction with the Universal Library. Boards released after the printing of this document will be described in Readme files on the Universal Library disk.

To fully understand and maximize the performance of this and other digital input function calls, refer to the 82C55 data sheet in the *Documents* subdirectory of the installation (C:\MCC\Documents by default), or from our web site at www.mccdaq.com/PDFmanuals/82C55A.pdf. Refer also to the 8536 data sheet (this data sheet file is not available in PDF format).

CIO- and PC104- DI Series

Digital I/O

Digital input functions and methods supported

UL: cbDIn, cbDBitIn()

UL for .NET: DIn, DBitIn()

Digital input argument values

PortNum FIRSTPORTA, FIRSTPORTB, FIRSTPORTCL and FIRSTPORTCH.

For **DI48**, **DI96**, and **DI192**, the following argument values are also valid:
SECONDPORTA, SECONDPORTB, SECONDPORTCL, SECONDPORTCH

For **DI96**, and **DI192**, the following argument values are also valid:
THIRDPORTA, THIRDPORTB, THIRDPORTCL, THIRDPORTCH, FOURTHPORTA,
FOURTHPORTB, FOURTHPORTCL, FOURTHPORTCH

For **DI192**, the following argument value is also valid:
FIFTHPORTA through EIGHTHPORTCH

DataValue 0 to 255 for PORTA or PORTB,
0 to 15 for PORTCL or PORTCH

BitNum 0 to 23 for FIRSTPORTA

For **DI48**, **DI96**, and **DI192**, the following argument values are also valid:
24 to 47 using FIRSTPORTA

For **DI96**, and **DI192**, the following argument values are also valid:
48 to 95 using FIRSTPORTA

For **DI192**, the following argument values are also valid:
96 to 191

CIO-DISO48

Digital I/O

Digital input functions and methods supported

UL: cbDIn, cbDBitIn()

UL for .NET: DIn, DBitIn()

Digital input argument values

PortNum FIRSTPORTA, SECONDPORTA, THIRDPORATA, FOURTHPORTA, FIFTHPORTA, SIXTHPORTA

DataValue 0 to 255

BitNum 0 to 47 using FIRSTPORTA

Digital Output Boards

Introduction

This chapter provides details on using digital output boards in conjunction with the Universal Library. Boards released after the printing of this document will be described in Readme files on the Universal Library disk.

To fully understand and maximize the performance of this and other digital input function calls, refer to the 82C55 data sheet in the *Documents* subdirectory of the installation (C:\MCC\Documents by default), or from our web site at www.mccdaq.com/PDFmanuals/82C55A.pdf. Refer also to the 8536 data sheet (this data sheet file is not available in PDF format).

CIO-RELAY Series

Digital I/O

Digital output functions and methods supported

UL: cbDOut, cbDBitOut ()

UL for .NET: DOut, DBitOut ()

Digital output argument values

PortNum FIRSTPORTA

For **CIO-RELAY16 & 16/M**, the following argument values are also valid:
FIRSTPORTB

For **CIO-RELAY24**, the following argument values are also valid:
SECONDPORTA

For **CIO-RELAY32**, the following argument values are also valid:
SECONDPORTE

DataValue 0 to 255

BitNum 0 to 7 using FIRSTPORTA

For **CIO-RELAY16 & 16/M**, the following argument values are also valid:
0 to 15 using FIRSTPORTA

For **CIO-RELAY24**, the following argument values are also valid:
0 to 23 using FIRSTPORTA

For **CIO-RELAY32**, the following argument values are also valid:
0 to 31 using FIRSTPORTA

USB-ERB Series

The Measurement Computing brand USB-ERB08 and USB-ERB24 support the following UL and UL for .NET features.

Digital I/O

Digital output functions and methods supported

UL: `cbDIn()`, `cbDOut()`, `cbDBitIn()`, `cbDBitOut()`

UL for .NET: `DIn()`, `DOut()`, `DBitIn()`, `DBitOut()`

Digital output argument values

PortNum `FIRSTPORTCL`, `FIRSTPORTCH`

For the **USB-ERB24**, the following argument values are also valid:

`FIRSTPORTA`, `FIRSTPORTB`

DataValue 0 to 15 for `FIRSTPORTCL` and `FIRSTPORTCH`

For the **USB-ERB24**, the following argument values are also valid:

0 to 255 for `FIRSTPORTA` and `FIRSTPORTB`

BitNum For the **USB-ERB08**, the following argument values are valid:

16 to 23 for `FIRSTPORTA`

For the **USB-ERB24**, the following argument values are valid:

0 to 23 for `FIRSTPORTA`

Miscellaneous functions and methods supported

UL: `cbFlashLED()`

UL for .NET: `FlashLED()`

Causes the USB LED on a Measurement Computing USB module to blink.

When you have several modules connected to the computer, use these functions to identify a particular module by making its LED blink.

Do not change state of invert/non-invert switch (S1) while program is running

Do not change the state of the invert/non-invert switch (labeled S1) on a USB-ERB module while a program is running. UL stores the current state of this switch, and changing the switch setting while a program is running can cause unpredictable results.

CIO- and PC104-DO Series

Digital I/O

Digital output functions and methods supported

UL: cbDOut, cbDBitOut ()

UL for .NET: DOut, DBitOut ()

Digital output argument values

PortNum FIRSTPORTA, FIRSTPORTB, FIRSTPORTCL and FIRSTPORTCH.

For **DO48H, DO48DD, DO96H** and **DO192H**, the following argument values are also valid:

SECONDPORTA, SECONDPORTB, SECONDPORTCL, SECONDPORTCH

For **DO96H** and **DO192H**, the following argument values are also valid:

THIRDPORTA, THIRDPORTB, THIRDPORTCL, THIRDPORTCH, FOURTHPORTA, FOURTHPORTB, FOURTHPORTCL, FOURTHPORTCH

For **DO192H**, the following argument values are also valid:

FIFTHPORTA through EIGHTHPORTCH

DataValue 0 to 255 for PORTA or PORTB,
0 to 15 for PORTCL or PORTCH

BitNum 0 to 23 for FIRSTPORTA

For **DO48H, DO48DD, DO96H** and **DO192H** the following argument values are also valid:

24 to 47 using FIRSTPORTA

For **DO96H** and **DO192H**, the following argument values are also valid:

48 to 95 using FIRSTPORTA

For **DO192H**, the following argument values are also valid:

96 to 191

Counter Boards

Introduction

This chapter provides details on using counter/timer boards in conjunction with the Universal Library. Boards released after the printing of this user's guide are explained in Readme files on the Universal Library installation disk.

Basic signed integers

When reading or writing ports that are 16-bits wide, be aware of the following issue using signed integers (which is required when using Basic):

On some boards, such as the **CIO-CTR10** count register or **AUXPORT** digital ports, the ports are 16-bits wide. When accessing the data at these ports, the digital values are arranged as a single 16-bit word. Using signed integers, values above 0111 1111 1111 1111 (32767 decimal) can be confusing. The next increment, 1000 0000 0000 0000 has a decimal value of -32768. Using signed integers, this is the value that is returned from a 16 bit counter at half of maximum count. The value for full count (just before the counter turns over) is -1. Keep this in mind if you are using Basic, since Basic does not supply unsigned integers (values from 0 to 65535) or unsigned longs (values from 0 to 4,294,967,295). Refer to "[16-bit values using a signed integer data type](#)" on page 8 for more information.

The Universal Library provides functions for the initialization and configuration of counter chips, and can configure a counter for any of the counter operations. However, counter configuration does not include counter-use, such as event counting and pulse width. Counter-use is accomplished by programs which use the counter functions. The Universal Library Version 1 and later provides the `cbCFreqIn()` function for counter use, while the Universal Library for .NET provides the `CFreqIn()` method. Other functions and methods may be added for counter use to later revisions.

Read the counter chip's data sheet

To use a counter for any but the simplest counting function, you must read, understand, and employ the information contained in the chip manufacturer's data sheet. Technical support of the Universal Library does not include providing, interpreting, or explaining the counter chip data sheet.

To fully understand and maximize the performance of the counter/timer boards and their related function calls, review the following related data sheet(s):

Counter/Timer	Data Sheet
82C54	82C54.pdf is located in the Documents installation subdirectory, and is also available from our web site at www.mccdaq.com/PDFmanuals/82C54.pdf .
AM9513	9513A.pdf is located in the Documents installation subdirectory, and is also available from our web site at www.mccdaq.com/PDFmanuals/9513A.pdf .
Z8536	The data book for the Z8536 counter chip is included with the product that employs this chip.
LS7266	LS7266R1.pdf is located in the Documents installation subdirectory, and is also available from our web site at www.mccdaq.com/PDFmanuals/ls7266r1.pdf .

Counter chip variables

UL counter initialization and configuration functions include names for bit patterns, such as **ALEGATE**, which stands for Active Low Enabled Gate N. In any case where the UL has a name for a bit pattern, it is allowed to substitute the bit pattern as a numeric. This will work, but your programs will be harder to read and debug.

CTR Series

Counter I/O

Counter functions and methods supported

UL:	<code>cbC9513Config()</code> , <code>cbC9513Init()</code> , <code>cbCStoreOnInt()</code> , <code>cbCFreqIn()</code> , <code>cbCIn()</code> , <code>cbCLoad()</code>
UL for .NET:	<code>C9513Config()</code> , <code>C9513Init()</code> , <code>CStoreOnInt()</code> , <code>CFreqIn()</code> , <code>CIn()</code> , <code>CLoad()</code>

Counter argument values

CounterNum	1 to 5 (All boards in this series) CTR10 & CTR10HD also support counters 6 through 10 CTR20HD also supports counters 11 through 20
RegNum:	<code>LOADREG1 - 5</code> , <code>HOLDREG1 - 5</code> , <code>ALARM1CHIP1</code> , <code>ALARM2CHIP1</code> CTR10 & CTR10HD also support <code>LOADREG6 - 10</code> , <code>HOLDREG6 - 10</code> , <code>ALARM1CHIP2</code> , <code>ALARM2CHIP2</code> CTR20HD also supports <code>LOADREG11 - 20</code> , <code>HOLDREG11 - 20</code> , <code>ALARM1CHIP3</code> , <code>ALARM2CHIP3</code> , <code>ALARM1CHIP4</code> , <code>ALARM2CHIP4</code>
LoadValue	0 to 65535 (Refer to " 16-bit values using a signed integer data type " on page 8 for information on 16-bit values using unsigned integers.)
ChipNum	1 (All boards in this series) CTR10 & CTR10HD also support chip 2 CTR20HD also support chips 3 and 4
FOutSource	<code>CTRINPUT1 - 5</code> , <code>GATE1 - 5</code> , <code>FREQ1 - 5</code> These values refer to the sources on a particular 9513 chip, so are limited to the sources on that particular chip. For example, to set the source to the input for counter 6, use <code>CTRINPUT1</code> (the first counter on the second 9513 chip).
CountSource	<code>TCPREVCTR</code> , <code>CTRINPUT1 - 5</code> , <code>GATE1 - 5</code> , <code>FREQ1 - 5</code> These values refer to the sources on a particular 9513 chip, so are limited to the sources on that particular chip. For example, to set the source to the input for counter 6, use <code>CTRINPUT1</code> (the first counter on the second 9513 chip). Likewise for the <code>TCPREVCTR</code> value; when applied to the first counter on a chip (counter 6, for example) the "previous counter" is counter 5 on that chip (for this example, counter 10).

Digital I/O

Digital I/O functions and methods supported

UL:	<code>cbDOut()</code> , <code>cbDIn()</code> , <code>cbDBitIn()</code> , <code>cbDBitOut()</code>
UL for .NET:	<code>DOut()</code> , <code>DIn()</code> , <code>DBitIn()</code> , <code>DBitOut()</code>

Digital I/O argument values

PortNum	<code>AUXPORT*</code>
DataValue	CTR05: 0 to 255 CTR10: 0 to 65535. Refer to " Basic signed integers " on page 121.
BitNum	CTR05: 0 to 7; CTR10: 0 to 15 * <code>AUXPORT</code> is not configurable for these boards.

Event notification

Event notification functions and methods supported

PCI-CTR05, PCI-CTR10 and PCI-CTR20HD only

UL: `cbEnableEvent ()`, `cbDisableEvent ()`

UL for .NET: `EnableEvent ()`, `DisableEvent ()`

Event notification argument values

EventType `ON_EXTERNAL_INTERRUPT` (UL)/`OnExternalInterrupt` (UL for .NET)

Hardware considerations

Clock input frequency (PCI boards only)

The clock source for each of the four counters is configurable with *InstaCal*:

PCI-CTR05, PCI-CTR10: 1 MHz, 1.67 MHz, 3.33 MHz, 5 MHz

PCI-CTR20HD: 1 MHz, 1.67 MHz, 3.33 MHz, 5 MHz, or External

Event Notification

`ON_EXTERNAL_INTERRUPT` cannot be used with `cbCStoreOnInt ()` or `CStoreOnInt ()`.

CTR Series boards that support event notification only support external rising edge interrupts.

INT32 Series

Counter I/O

Counter functions and methods supported

UL: `cbC8536Config()`, `cbC8536Init()`, `cbCIn()`, `cbCLoad()`

UL for .NET: `C8536Config()`, `C8536Init()`, `CIn()`, `CLoad()`

Counter argument values

CounterNum 1 to 6

ChipNum 1 or 2

RegName LOADREG1 through LOADREG6

LoadValue Values up to 65,535 ($2^{16}-1$) can be used. Refer to "[Basic signed integers](#)" on page 121 for more information.

Digital I/O

Digital I/O functions and methods supported

UL: `cbDIn()`, `cbDOut()`, `cbDBitIn()`, `cbDBitOut()`, `cbDConfigPort()`

UL for .NET: `DIn()`, `DOut()`, `DBitIn()`, `DBitOut()`, `DConfigPort()`

Digital I/O argument values

PortNum FIRSTPORTA, FIRSTPORTB, FIRSTPORTCL, SECONDPORTA, SECONDPORTB and SECONDPORTCL.

DataValue 0 to 255 using PORTA or PORTB
0 to 15 using PORTCL

BitNum 0 to 39 using FIRSTPORTA

Hardware considerations

Argument Value vs. configuration

These boards have two 8536 chips, which have both counter and digital I/O and interrupt vectoring capabilities. The numbers stated for digital I/O apply when both chips are configured for the maximum number of digital devices. The numbers stated for counter I/O apply when both chips are configured for the maximum number of counter devices.

PPIO-CTR06

Counter I/O

Counter functions and methods supported

UL: cbC8254Config(), cbCIn(), cbCLoad()

UL for .NET: C8254Config(), CIn(), CLoad()

Counter argument values

CounterNum 1 to 6

Digital I/O

Digital I/O functions and methods supported

UL: cbDIn(), cbDOut(), cbDBitIn(), cbDBitOut()

UL for .NET: DIn(), DOut(), DBitIn(), DBitOut()

Digital I/O argument values

PortNum AUXPORT*

DataValue 0 to 15, or 0 to 255, depending on jumper setting

BitNum 0 to 3, or 0 to 7, depending on jumper setting

* AUXPORT is not configurable for this board.

QUAD Series

Counter I/O

Counter functions and methods supported

UL:	<code>cbC7266Config()</code> , <code>cbCIn()</code> , <code>cbCIn32()</code> , <code>cbCLoad()</code> , <code>cbCLoad32()</code> , <code>cbCStatus()</code>
UL for .NET:	<code>C7266Config()</code> , <code>CIn()</code> , <code>CIn32()</code> , <code>CLoad()</code> , <code>CLoad32()</code> , <code>CStatus()</code>

Counter argument values

CounterNum	PCM-QUAD02, CIO-QUAD02 1 to 2 CIO-QUAD04, PCI-QUAD04 1 to 4
RegName	UL: COUNT1, COUNT2, PRESET1, PRESET2, PRESCALER1, PRESCALER2 UL for .NET: QuadCount1, QuadCount2, QuadPreset1, QuadPreset2, QuadPreScaler1, QuadPreScaler2 CIO-QUAD04, PCI-QUAD04 also support: UL: COUNT3, COUNT4, PRESET3, PRESET4, PRESCALER3, PRESCALER4 UL for .NET: QuadCount3, QuadCount4, QuadPreset3, QuadPreset4, QuadPreScaler3, QuadPreScaler4
LoadValue	When using <code>cbCLoad32()</code> or <code>CLoad32()</code> to load the COUNT# or PRESET# registers, values up to 16.78 million ($2^{24}-1$) can be loaded. Values using <code>cbCLoad()</code> and <code>CLoad()</code> are limited to 65,535 ($2^{16}-1$). Refer to " Basic signed integers " on page 121 for more information. When loading the PRESCALER# register, values can be from 0 to 255. (Digital Filter Clock frequency = 10 MHz/LoadValue + 1.)

Hardware considerations

Loading and Reading 24-bit values

The QUAD series boards feature a 24-bit counter. For counts of less than 16 bits (65535), you can use the `cbCIn()` and `cbCLoad()` functions, or the `CIn()` and `CLoad()` methods. You can use the `cbCIn32()` and `cbCLoad32()` functions, or the `CIn32()` and `CLoad32()` methods for any number supported by the LS7266 counter (24 bits = 16777216).

Cascading counters (PCI-QUAD04 only)


The PCI-QUAD04 can be set up for cascading counters. By setting the appropriate registers, you can have (4) 24-bit counters, (2) 48-bit counters, (1) 24-bit and (1) 72-bit counters, or (1) 96-bit counter. The OUTPUT pins of a counter are directed to the next counter by setting the FLG1 to CARRY/BORROW and the FLG2 to UP/DOWN. Bits 3 and 4 of the IOR Register control are set to 1,0 to accomplish this.

You can set these bits by using the functions `cbC7266Config(BoardNum, CounterNum, Quadrature, CountingMode, DataEncoding, IndexMode, InvertIndex, FlagPins, and GateEnable)`. When using the Universal Library for .NET, use the `C7266Config()` method.

The constant `CARRYBORROW_UPDOWN` (value of 3) is used for the parameter `FlagPins`.

The IOR register cannot be read. However, you can read the values of the BADR2+9 register. The value for Base 2 can be determined by looking at the resources used by the board. The 8-bit region is BADR2. The BADR+9 register contains values for PhxA and PhxB, for x = 1 to 4 to identify counters. The diagram below

indicates the routing of the FLG pins depending on the value of PhxA and PhxB. The actual values of the BADR2+9 register are shown below:



Register BADR2 + 9 D0-D6

	PH2A	PH2B	PH3A	PH3B	PH4A	PH4B1/PH4B0	Value
Case 1: (4) 24-bit counters (1/2/3/4)	0	0	0	0	0	0,0	00
Case 2: (2) 48-bit counters (1-2/3/4)	1	1	0	0	1	1,0	53
Case 3: (1) 24-bit, (1) 72-bit (1/2-3-4)	0	0	1	1	1	0,1	3C
Case 4: (1) 96-bit counter (1-2-3-4)	1	1	1	1	1	0,1	3F

Defaults to 0x00 (no inter-counter connections).

Examples

Case 1: (4) 24-bit counters (1/2/3/4)

```
cbC7266Config(0,1,0,0,2,0,0,1,0)
cbC7266Config(0,2,0,0,2,0,0,1,0)
cbC7266Config(0,3,0,0,2,0,0,1,0)
cbC7266Config(0,4,0,0,2,0,0,1,0)
```

Case 2: (2) 48-bit counters (1-2/3-4)

```
cbC7266Config(0,1,0,0,2,0,0,3,0)
cbC7266Config(0,2,0,0,2,0,0,1,0)
cbC7266Config(0,3,0,0,2,0,0,3,0)
cbC7266Config(0,4,0,0,2,0,0,1,0)
```

Case 3: (1) 24-bit & (1) 72-bit counter (1/2-3-4)

```
cbC7266Config(0,1,0,0,2,0,0,1,0)
cbC7266Config(0,2,0,0,2,0,0,3,0)
cbC7266Config(0,3,0,0,2,0,0,3,0)
cbC7266Config(0,4,0,0,2,0,0,1,0)
```

Case 4: (1) 96-bit counter (1-2-3-4)

```
cbC7266Config(0,1,0,0,2,0,0,3,0)
cbC7266Config(0,2,0,0,2,0,0,3,0)
cbC7266Config(0,3,0,0,2,0,0,3,0)
cbC7266Config(0,4,0,0,2,0,0,1,0)
```

The actual value of the BADR+9 register is not set until the `cbCLoad()/CLoad()` command is called.

Counter4 setting

Setting Counter4 to CARRYBORROW-UPDOWN is NOT VALID.

MetraBus Boards

Introduction

This section provides details on using all **MetraBus** boards in conjunction with the Universal Library. Future releases will be described in Readme files on the Universal Library installation disk.

To use any **MetraBus** I/O board, a **MetraBus** interface board, such as the **ISA-MDB64**, **PCI-MDB64** or a **CPCI-MDB64**, is required for the Universal Library functions to operate correctly. The interface board and a **MetraBus** cable provide the interface between the PC bus (ISA-, PC104-, PCI-, or CPCI-) and the **MetraBus** I/O Boards.

The **MetraBus** system is made up of at least one controller board that communicates with real world interface boards via a data bus (ribbon cable). The implication is that there will always be two or more boards in the system.

MDB64 Series

This series makes up the controller portion of the **MetraBus** system. The Universal Library contains no function to communicate specifically with this board. The functions in the library are directed to the devices on the bus instead.

For example, if this board was installed in *InstaCal* as board 0, and an **MII-32** was installed as board 1, the communication would be directed to board 1. If you wanted to read digital bits from this configuration, use the `cbDBitIn()` function or the `DBitIn()` method. The value of the `BoardNum` argument would be 1.

MIO and MII Digital I/O

All **MetraBus** boards require a cable and an interface board (such as an **ISA-**, **PC104-**, or **PCI- MDB64**) to interface to the host computer system.

Digital In

MII-32 Only

Digital input functions and methods supported

UL: `cbDIn, cbDBitIn()`

UL for .NET: `DIn, DBitIn()`

Digital input argument values

PortNum `FIRSTPORTA, FIRSTPORTB, SECONDPOR`

DataValue `0 to 255 for PORTA or PORTB`

BitNum `0 to 31 for FIRSTPORTA`

Digital Out

MIO-32 Only

Digital output functions and methods supported

UL: `cbDOut, cbDBitOut(), cbDBitIn(), cbDIn()`

UL for .NET: `DOut, DBitOut(), DBitIn(), DIn()`

Digital output argument values

PortNum `FIRSTPORTA, FIRSTPORTB, SECONDPOR`

DataValue `0 to 255 for PORTA or PORTB`

BitNum `0 to 31 for FIRSTPORTA`

Functions/methods for reading back the MIO-32 output state

Although the **MIO-32** is a digital output-only board, the state of the outputs can be read back using the UL functions `cbDIn()` and `cbDBitIn()`, or the UL for .NET methods `DIn()` and `DBitIn()`.

MEM Series Relay

All **MetraBus** boards require a cable and an interface board (such as an **ISA-**, **PC104-**, or **PCI- MDB64**) to interface to the host computer system.

Digital I/O

Digital I/O functions and methods supported

UL: `cbDOut()`, `cbDIn()`, `cbDBitIn()`, `cbDBitOut()`

UL for .NET: `DOut()`, `DIn()`, `DBitIn()`, `DBitOut()`

Digital I/O argument values

PortNum `FIRSTPORTA`

For **MEM-32**, the following argument values are also valid:

`FIRSTPORTB`, `SECONDPORATA`, `SECONDPORTEB`

DataValue 0 to 255 for `PORTA` or `PORTB`

BitNum 0 to 7 for `FIRSTPORTA`

For **MEM-32**, the following argument values are also valid:

0 to 31 for `FIRSTPORTA`

Functions/methods for reading back the MEM Series Relay output state

Although the **MEM Series Relay** is a digital output-only board, the state of the outputs can be read back using the UL functions `cbDIn()` and `cbDBitIn()`, or the UL for .NET methods `DIn()` and `DBitIn()`.

MSSR-24 SSR

All **MetraBus** boards require a cable and an interface board (such as an **ISA-**, **PC104-**, or **PCI- MDB64**) to interface to the host computer system.

Digital I/O

Digital I/O functions and methods supported

UL: cbDIn, cbDBitIn(), cbDOut, cbDBitOut()

UL for .NET: DIn, DBitIn(), DOut, DBitOut()

Digital I/O argument values

PortNum FIRSTPORTA, FIRSTPORTB, SECONDPORTA

DataValue 0 to 255

BitNum 0 to 24 using FIRSTPORTA

Expansion Boards

Introduction

This chapter provides details on using expansion (**EXP**) boards in conjunction with the Universal Library. Boards released after the printing of this user's guide are described in Readme files on the Universal Library disk.

You add an expansion board to the *InstaCal* configuration by selecting the compatible board on the main **InstaCal** form, and selecting the **Add Exp Board...** option from the **Install** menu.

CIO-EXP Series

Temperature Input

Temperature input functions and methods supported

UL: `cbTIn()`, `cbTInScan()`

UL for .NET: `TIn()`, `TInScan()`

Temperature input argument values

Options `NOFILTER`

Scale `CELSIUS`, `FAHRENHEIT`, `KELVIN`

HighChan From 16 up to 255 for 16-channel boards, and from 64 up to 303 for 64-channel boards. The value depends on the number of boards connected and the application.

Hardware considerations

CIO-EXP boards are used only in combination with an A/D board. Channel numbers for accessing the expansion boards begin at 16 for 8-channel and 16-channel boards, and at 64 for 64-channel boards. To calculate the channel number for access to **CIO-EXP** channels, use the following formula:

$$\text{Chan} = (\text{ADChan} * 16) + (16 + \text{MuxChan})$$

`MuxChan` is a number ranging from 0 to 15 that specifies the channel number on a particular bank of the expansion board. An **EXP32** has two banks, so the channel numbers for one **EXP32** connected to an A/D board would range from 16 to 47.

If all A/D channels are not used for **CIO-EXP** output, direct input to the A/D board is still available at these channels (using channel numbers below 16).

When **CIO-EXP** boards are used for **temperature input**, set the gain of the A/D board to a specific range. When using A/D boards with programmable gain, the range is set by the Universal Library. However, when using boards with switch-selectable gains, you must set the gain to a range that is dependent on the temperature sensor in use. Generally, thermocouple measurements require the A/D board to be set to 5 V bipolar, if available (or 10 V bipolar if not). RTD sensors require a setting of 10 V unipolar, if available. These checks are made when you configure the system for temperature measurement using *InstaCal*.

MEGA-FIFO

Memory I/O

Memory I/O is only used in combination with a board which has DT-Connect.

Memory functions and methods supported

UL: cbMemSetDTMode(), cbMemReset(), cbMemRead(), cbMemWrite(),
 cbMemReadPretrig()

UL for .NET: MemSetDTMode(), MemReset(), MemRead(), MemWrite(), MemReadPretrig()

Some of these functions are integrated into the `cbAInScan()` function and `AInScan()` method. For example, if you use **MEGA-FIFO** with an A/D board and select the `EXTMEMORY` option, you would not have to call the `cbMemSetDTMode()` and `cbMemWrite` functions, or the `MemSetDTMode()` and `MemWrite()` methods.

EXTMEMORY option

Continuous mode can't be used with the `EXTMEMORY/ExtMemory` option.

Other Hardware

Introduction

This chapter provides details on using miscellaneous hardware, such as communications boards in conjunction with the Universal Library and Universal Library for .NET. Boards released after the printing of this user's guide will be described in Readme files on the Universal Library disk.

COM422 Series

No library functions are supported for these boards, but *InstaCal* can be used to configure the serial protocol in conjunction with the `Set422.exe` utility. All other serial communications are handled by DOS or Windows standard serial communications handlers.

COM485 Series

The **COM485** Series board supports the UL function `cbRS485()` and the UL for .NET method `RS485()` for controlling the transmit and receive enable register. All other serial communications are handled by DOS or Windows standard serial communications handlers.

Demo-Board

The **DEMO-BOARD** is a software simulation of a data acquisition board that simulates analog input and digital I/O operations.

Analog Input

Analog input functions and methods supported

UL: `cbAIn()`, `cbAInScan()`, `cbATrig()`, `cbFileAInScan()`
 UL for .NET: `AIn()`, `AInScan()`, `ATrig()`, `FileAInScan()`

Analog input argument values

Options `BACKGROUND`, `CONTINUOUS`, `SINGLEIO`, `DMAIO`
 HighChan `7 max`
 Rate `300000`

Digital I/O

Digital I/O functions and methods supported

UL: `cbDIn()`, `cbDBitIn()`, `cbDInScan()`, `cbDOut()`, `cbDBitOut()`, `cbDOutScan()`,
 `cbDConfigPort()`
 UL for .NET: `DIn()`, `DBitIn()`, `DInScan()`, `DOut()`, `DBitOut()`, `DOutScan()`, `DConfigPort()`

Digital I/O argument values

PortNum `FIRSTPORTA`, `FIRSTPORTB`, `AUXPORT`
 DataValue `0 to 255 using FIRSTPORTA, FIRSTPORTB, or AUXPORT`
 BitNum `0 to 15 using FIRSTPORTA`
 `0 to 7 using AUXPORT`

Using the Demo Board

Analog input

The **DEMO-BOARD** simulates eight channels of 16-bit analog input. *InstaCal* is used to configure the following waveforms on the analog input channels:

- sine wave
- square wave
- saw-tooth, ramp
- damped sine wave
- input from a data file

The data file is a streamer file, so any data that has been previously saved in a streamer file can be used as a source of demo data by the board. Data files are named `DEMO0.DAT` through `DEMO7.DAT`. When a data file is assigned to a channel, the library tries to extract data for that channel from the streamer file. If data for that channel does not exist, then the first (and possibly only) channel data in the streamer is extracted and used.

For example, `DEMO2.DAT` is assigned as the data source for channel 5 on the demo board. The library will try to extract data from the file that corresponds to channel 5. If `DEMO2.DAT` has scan data that corresponds to channels 0 through 15, then channel 5 data is extracted. If `DEMO2.DAT` only has data for a single channel, the data for that channel is used as the data source for channel 5.

Digital I/O

The **DEMO-BOARD** simulates the following:

- One eight-bit `AUXPORT` non-configurable digital input port. Each bit of the `AUXPORT` generates a square wave with a different period.
- One eight-bit `AUXPORT` non-configurable digital output port.
- Two eight-bit configurable digital I/O ports—`FIRSTPORTA`, `FIRSTPORTB`—which can be used for high speed scanning. `FIRSTPORTA` functions like `AUXPORT` in that it generates square waves. Each bit of `FIRSTPORTB` generates a pulse with a different frequency.

Appendix – MCC Device IDs

This Appendix lists the device ID associated with each MCC hardware type. This information is returned by the BoardName and BoardNum arguments.

Board Name	Device ID		
PCI-DAS1602/16	1	PC-CARD-DAS16/16	56
		PC-CARD-DAS16/16-AO	57
		PC-CARD-DAS16/12	58
CIO-DAS6402/12	8	PC-CARD-DAS16/12-AO	59
CIO-DAS16/M1/16	9	PC-CARD-DAS16/330	60
CIO-DAS6402/16	10	PC-CARD-D24/CTR3	61
PCI-DIO48H	11	PC-CARD-DIO48	62
PCI-PDISO8	12	PCI-COM232	63
PCI-PDISO16	13	PCI-COM232/2	64
CPCI-GPIB	14	PCI-COM232/4	65
PCI-DAS1200	15	PCI-COM422	66
PCI-DAS1602/12	16	PCI-COM422/2	67
CIO-RELAY16M	17	PCI-COM485	68
CIO-PDMA32	18	PCI-COM485/2	69
CIO-DAC04/16-HS	19	ISA-MDB64	70
PCI-DIO24H	20	MII-32	71
PCI-DIO24H/CTR3	21	MIO-32	72
PCI-DIO48H/CTR15	22	MEM-8	73
PCI-DIO96H	23	MEM-32	74
PCI-CTR05	24	PCI-MDB64	75
PCI-DAS1200Jr	25	PCI-DAS1000	76
PCI-DAS1001	26	PCI-QUAD04	77
PCI-DAS1002	27	MSSR-24	78
PCI-DAS1602JR_16	28	PC104-MDB64	79
PCI-DAS6402/16	29	MAI-16	80
PCI-DAS6402/12	30		
PCI-DAS16/M1	31	PCI-DAS4020/12	82
PCI-DDA02/12	32	PCIM-DDA06/16	83
PCI-DDA04/12	33	PCI-DIO96	84
PCI-DDA08/12	34	CPCI-DIO24H	85
PCI-DDA02/16	35	PCIM-DAS1602/16	86
PCI-DDA04/16	36	PCI-DAS3202/16	87
PCI-DDA08/16	37	PC104-AC5	88
PCI-DAC04/12HS	38	PCI-QUAD-AC5	89
PCI-DAC04/16HS	39	CPCI-DIO96H	90
PCI-DIO24	40	CPCI-DIO48H	91
PCI-DAS08	41	PC-CARD-DAC08	92
CIO-RELAY24	42	PCI-DAS6023	93
CIO-RELAY32	43	PCI-DAS6025	94
PCI-INT32	44	PCI-DAS6030	95
DEMO-BOARD	45	PCI-DAS6031	96
CIO-DAS-TC	46	PCI-DAS6032	97
CIO-QUAD02	47	PCI-DAS6033	98
CIO-QUAD04	48	PCI-DAS6034	99
PCM-QUAD02	49	PCI-DAS6035	100
PCI-DAS64	50	PCI-DAS6040	101
PCI-DUAL-AC5	51	PCI-DAS6052	102
PCI-DAS-TC	52	PCI-DAS6070	103
PCI-DAS64/M1/16	53	PCI-DAS6071	104
PCI-DAS64/M2/16	54		
PCI-DAS64/M3/16	55	PCI-CTR10	110

PCI-DAS6036	111	CIO-DIO24H	1026
PCI-DAC6702	112	CIO-DIO48	1027
PCI-DAC6703	113	CIO-DIO96	1028
		CIO-DIO192	1029
PCI-CTR20HD	116	CIO-DIO24/CTR3	1030
miniLAB 1008	117	CIO-DIO48H	1031
PMD-1024LS	118	CIO-DUAL-AC5	1032
PCI-DIO24/LP	119	CIO-DI48	1033
PCI-DAS6013	120	CIO-DO48H	1034
PCI-DAS6014	121	CIO-DI96	1035
USB-1208LS, PMD-1208LS	122	CIO-DO96H	1036
PCIM-DAS16JR/16	123	CIO-DI192	1037
		CIO-DO192H	1038
USB-1608FS, PMD-1608FS	125	CIO-DO24DD	1039
PCI-DIO24/S	126	CIO-DO48DD	1040
USB-1024HLS, PMD-1024HLS	127	PC104-DIO48	1041
6K-EXP16	128	PC104-DI48	1042
USB-1616FS	129	PC104-DO48H	1043
USB-1208FS, PMD-1208FS	130		
USB-1096HFS	131	CIO-PDMA16	1281
Switch & Sense 8/8	132		
USB-SSR24	133	CIO-DAC02	1537
USB-SSR08	134	CIO-DAC08	1538
		CIO-DAC16	1539
E-PDISO16	137	CIO-DAC16I	1540
USB-ERB24	138	CIO-DAC08I	1541
USB-ERB08	139		
USB-PDISO8	140	PC104-DAC06	1543
USB-TEMP	141	CIO-DDA06/12	1793
		CIO-DDA06/16	1794
USB-TC	144	CIO-DDA06/Jr	1795
		CIO-DAC02/16	1796
USB-DIO96H	146	CIO-DAC08/16	1797
USB-DIO24/37	147	CIO-DAC16/16	1798
USB-DIO24H/37	148	CIO-DDA06Jr/16	1799
USB-DIO96H/50	149		
USB-PDISO8/50	150	CIO-CTR05	2049
		CIO-CTR10	2050
CIO-DAS16	257	CIO-CTR10-HD	2051
CIO-DAS16/F	258	CIO-CTR20-HD	2052
CIO-DAS16/Jr	259	PC104-CTR10-HD	2053
CIO-DAS16/330	260		
CIO-DAS16/330i	261	CIO-PDISO8	2305
CIO-DAS16/M1	262	CIO-PDISO16	2306
PC104-DAS16Jr/12	263	PC104-PDISO8	2307
PC104-DAS16Jr/16	264		
CIO-DAS16/Jr16	265	CIO-DAC04/12-HS	2564
CIO-SSH16	513	PPIO-DIO24H	2817
		PPIO-AI08	2818
CIO-EXP16	769	PPIO-CTR06	2819
CIO-EXP32	770		
CIO-EXP-GP	771	CIO-DAS08	3073
CIO-EXP-RTD	772	CIO-DAS08PGL	3074
CIO-EXP-BRIDGE	773	CIO-DAS08PGH	3075
		CIO-DAS08/AOL	3076
CIO-DIO24	1025	CIO-DAS08/AOH	3077

CIO-DAS08PGM	3078
CIO-DAS08/AOM	3079
CIO-DAS08/Jr	3080
PC104-DAS08	3081
CIO-DAS08Jr/16	3082
CIO-DAS48PGA	3329
CIO-DAS1601/12	3585
CIO-DAS1602/12	3586
CIO-DAS1602/16	3587
CIO-DAS1401/12	3588
CIO-DAS1402/12	3589
CIO-DAS1402/16	3590
MEGA-FIFO	3841
CIO-RELAY16	4097
CIO-RELAY08	4098
CIO-RELAY16/M	4099
CIO-DAS-TEMP	4353
CIO-DISO48	8193
CIO-INT32	12289
PCM-DAS08	16385
PCM-D24/CTR3	16386
PCM-DAC02	16387
PCM-COM422	16388
PCM-COM485	16389
PCM-DAS16D/12	16390
PCM-DAS16S/12	16391
PCM-DAS16D/16	16392
PCM-DAS16S/16	16393
PCM-DAS16S/330	16394
PCM-DAS16D/12AO	16395
PCM-DAC08	16401
CIO-COM422	20481
CIO-COM485	20482
CIO-DUAL422	20483
CIO-DAS800	24577
CIO-DAS801	24578
CIO-DAS802	24579
CIO-DAS802/16	24580

Measurement Computing Corporation
16 Commerce Boulevard,
Middleboro, Massachusetts 02346
(508) 946-5100
Fax: (508) 946-9500
E-mail: info@mccdaq.com
www.mccdaq.com